



Tenable and Microsoft Intune Mobile Device Management Integration Guide

Last Revised: July 12, 2023



Table of Contents

Tenable Vulnerability Management for Microsoft Intune	3
Tenable Security Center for Microsoft Intune	7



Tenable Vulnerability Management for Microsoft Intune

Before you begin:

- You must have an active Microsoft Azure subscription.
- [Create an App Registration](#) in the Microsoft Entra ID.
- [Create a User Account](#) with a **Directory** role of **Intune Administrator**.
- Add API permissions in Microsoft Azure.
- You must have an active Microsoft Intune subscription.

To configure Microsoft Azure:

Create an App Registration

You must create an App Registration to generate an Application (client) ID and Directory (tenant) ID. This information is needed for the Tenable integration.

1. Create an **App Registration**.
2. In the left navigation panel, click **Microsoft Entra ID**.

The **Microsoft Entra ID** menu appears.

3. Click **App Registrations**.
4. The **App Registrations** page appears.
5. Click the **New registration** tab.

The **Register an applicant** page appears.

6. Enter a **Name** .
7. Select the **Support account types**.
8. Provide a **Redirect URI**.

Note: The Redirect URI is required, but has no effect for this configuration; therefore, it doesn't have to be a real URI, i. e., <https://example.com>.



9. Click **Register**.
10. Under **Apps Registrations**, click on the **App registration** you just created.
11. In the **Overview** section, copy and save the **Application (client) ID** and **Directory (tenant) ID**.

Select API permissions

In the newly created App Registration, add permissions in the **Add API Permissions** section.

1. Click **API permissions**.

The API permissions page appears.

2. Click the **Add a Permission** button.
3. Select the **User.Read**, **Device.Read**, **Device.ReadWrite.All**, **DeviceManagementApps.Read.All**, **DeviceManagementConfiguration.Read.All**, **DeviceManagementManagedDevices**, **DeviceManagementRBAC.Read.All**, **DeviceManagementServiceConfig.Read.All**, and **UserRead.All** permissions.

Note: When you add the **DeviceManagementConfiguration.Read.All** and **DeviceManagementManagedDevices.Read.All** API permissions, you must select a Microsoft Graph API permission type of **Delegated**. Otherwise, you will not be able to collect any data.

4. Click **Grant admin consent for Tenable, Inc.**

Create a Client Secret

1. In the **Certificates and Secrets** section, click the **New client secret** button.

The **Add a client secret** window appears.

2. Enter a **Description**.
3. In the **Expires** section, select an expiration time.

Note: If you select **1 year** or **2 years**, you have to create a new client secret at that time. Selecting **Never** alleviates renewal.

4. Click **Add**.
5. Immediately, copy the client secret value.



Caution: Once you navigate away from this page the client secret value becomes hidden. There is no way to retrieve it once it becomes hidden. You must go through the steps again to generate another client secret.

Create a User Account

You need the user name and password to set up the Microsoft Intune account.

1. Click the **New User** button.

The **New User** section appears.

2. Type the required information for the new user.
3. In the **Directory role** option, select **Intune Administrator**.

Note: The user must have an Microsoft Entra ID account with a **Directory role** of **Intune Administrator**. You cannot use a domain account.

To configure Tenable Vulnerability Management:

1. Log in to Tenable Vulnerability Management.

2. At the top of the screen, click **New Scan**.

The **Scan Templates** page appears.

3. Click the **Mobile Device Scan** template.

The **New Scan/Mobile Device Scan** page appears.

4. In the **Name** field, enter a name for your scan.

5. (Optional) Add a description for the scan.

6. Select a **Folder**.

7. Select a **Scanner**.

8. Click the **Credentials** tab.

9. Select **Intune**.

The **Intune** configuration fields appear.



10. Provide the scan information described in the table below.

Option	Description
Tenant	The Microsoft Azure Directory (tenant) ID visible in your App registration.
Client	The Microsoft Azure Application (client) ID generated during your App registration.
Secret	The secret key generated when you created your client secret key in Microsoft Azure.
Username	The username for the account you want Tenable Vulnerability Management to use to authenticate to Intune.
Password	The password for the account you want Tenable Vulnerability Management to use to authenticate to Intune.

11. Click **Save to Managed Credentials**.

A **Save Credential** window appears.

12. In the **Credential Name** field, type a name for the credential.

13. Click **Save**.

The **My Scans** page appears.

14. To verify the integration works, click the **Launch** button next to your newly created scan.

15. Once the scan completes, click the scan to view the results.



Tenable Security Center for Microsoft Intune

Before you begin:

- You must have an active Microsoft Azure subscription.
- [Create an App Registration](#) in the Microsoft Entra ID.
- [Create a User Account](#) with a **Directory** role of **Intune Administrator**.
- Add API permissions in Microsoft Azure.
- You must have an active Microsoft Intune subscription.

To configure Microsoft Azure:

Create an App Registration

Create an App Registration to generate an Application (client) ID and Directory (tenant) ID. You need this information for the Tenable integration.

1. Create an **App Registration**.
2. In the left navigation panel, click **Microsoft Entra ID**.

The **Microsoft Entra ID** menu appears.

3. Click **App registrations**.
4. The **App Registrations** page appears.
5. Click the **New registration** tab.

The **Register an applicant** page appears.

6. Enter a **Name**.
7. Select the **Support account types**.
8. Provide a **Redirect URI**.

Note: The Redirect URI is required, but has no effect for this configuration; therefore, it doesn't have to be a real URI, i. e., <https://example.com>.

9. Click **Register**.



10. Under **Apps registrations**, click on the **App registration** you created.
11. In the **Overview** section, copy and save the **Application (client) ID** and **Directory (tenant) ID**.

Select API permissions

In the newly created App Registration, add permissions in the **Add API permissions** section.

1. Click **API permissions**.

The API permissions page appears.

2. Click the **Add a Permission** button.
3. Select the **User.Read**, **Device.Read**, **Device.ReadWrite.All**, **DeviceManagementApps.Read.All**, **DeviceManagementConfiguration.Read.All**, **DeviceManagementManagedDevices**, **DeviceManagementRBAC.Read.All**, **DeviceManagementServiceConfig.Read.All**, and **UserRead.All** permissions.

Note: When you add the **DeviceManagementConfiguration.Read.All** and **DeviceManagementManagedDevices.Read.All** API permissions, you must select a Microsoft Graph API permission type of **Delegated**. Otherwise, you will not be able to collect any data.

4. Click **Grant admin consent for Tenable, Inc.**

Create a Client Secret

1. In the **Certificates and Secrets** section, click the **New client secret** button.

The **Add a client secret** window appears.

2. Enter a **Description**.
3. Select a time for **Expires**.

4. **Note:** If you select **1 year** or **2 years**, you have to create a new client secret at that time. Selecting **Never** alleviates renewal.

5. Click **Add**.
6. Immediately, copy the client secret value.



Caution: Once you navigate away from this page the client secret value becomes hidden. There is no way to retrieve it once it becomes hidden. Go through the steps again to generate another client secret.

Create a User Account

You need the username and password to set up the Microsoft Intune account.

1. Click the **New User** button.

The **New User** section appears.

2. Type the required information for the new user.
3. In the **Directory role** option, select **Intune Administrator**.

Note: The user must have an Microsoft Entra ID account with a **Directory role** of **Intune Administrator**. You cannot use a domain account.

To configure Tenable Security Center

1. Log in to Tenable Security Center as an administrator via the user interface.
2. Click **Repositories**.

The **Repositories** page appears.

3. Click **Add**.

The **Add Repository** page appears.

4. Select **Mobile** as a repository type.

The **Mobile Repository Configuration** page appears.

5. Select **Microsoft Intune** from the **Type** drop-down box.
6. Configure the options for your repository type:

Option	Description	Default
Intune Tenant	(Required) The Microsoft Azure Directory value in your Microsoft Intune	--



Option	Description	Default
	registration.	
Intune Client	(Required) The Microsoft Azure Application value generated during your Microsoft Intune registration.	--
Intune Secret	(Required) The Microsoft Azure client secret key.	--
Intune Username	(Required) The username for the Microsoft Intune user account Tenable Security Center uses to authenticate Microsoft Intune.	--
Intune Password	(Required) The password for the Microsoft Intune user.	--
Scanner	(Required) Specifies which Nessus scanner Tenable Security Center uses when scanning the server. Tenable Security Center can only use one Nessus scanner to add data to a mobile repository.	--
Update Schedule	Specifies when Tenable Security Center scans the server to update the mobile repository. On each scan, Tenable Security Center removes the current data in the repository and replaces it with data from the latest scan.	Every day at 12:30 -04:00

7. Click **Submit**.

Tenable Security Center saves your configuration.

What to do next:



- If you added an offline repository, export one or more repositories from your other Tenable Security Center as described in [Export a Repository](#).
- If you added an offline repository, import one or more exported repository files as described in [Import a Repository](#).

For more information on Tenable Security Center scans, see [Tenable Security Center Scanning Overview](#).