



# Tenable Security Center 6.0.x User Guide

---

Last Revised: August 21, 2023



# Table of Contents

<b>Welcome to Tenable Security Center</b> .....	<b>20</b>
Get Started With Tenable Security Center .....	21
Tenable Security Center Architecture .....	26
Considerations for Air-Gapped Environments .....	28
Requirements .....	30
Hardware Requirements .....	31
Cloud Requirements .....	34
System Requirements .....	39
Customize SELinux Enforcing Mode Policies for Tenable Security Center .....	43
Use /dev/random for Random Number Data Generation .....	44
Tenable Security Center Database Journaling Modes .....	45
Enable Write-Ahead Logging .....	47
Disable Write-Ahead Logging .....	49
License Requirements .....	51
Apply a New License .....	53
Update an Existing License .....	54
Tenable Security Center+ License Expiration .....	56
Port Requirements .....	57
Browser Requirements .....	63
Tenable Integrated Product Compatibility .....	64
Large Enterprise Deployments .....	65
Installation and Upgrade .....	66
Before You Install .....	67



Install Tenable Security Center .....	69
Quick Setup .....	71
Install a Tenable Security Center Patch .....	77
Before You Upgrade .....	79
Upgrade Tenable Security Center .....	81
Restore Custom SSL Certificates .....	83
Uninstall Tenable Security Center .....	85
User Access .....	86
Log In to the Web Interface .....	87
Log in to the Web Interface via SSL Client Certificate .....	89
User Roles .....	92
Create a User Role .....	98
Edit a User Role .....	99
View User Role Details .....	101
Delete a User Role .....	103
Organizations and Groups .....	104
Organizations .....	105
Add an Organization .....	110
View Organization Details .....	111
Delete an Organization .....	113
Groups .....	114
Add a Group .....	116
View Group Details .....	117
Delete a Group .....	119



User Accounts .....	120
Add a TNS-Authenticated User .....	121
Add an LDAP-Authenticated User .....	123
Add a SAML-Authenticated User .....	126
Manage User Accounts .....	129
Edit Your User Account .....	131
View User Details .....	133
Delete a User .....	135
Linked User Accounts .....	137
Add a Linked User .....	138
Switch to a Linked User Account .....	140
Edit a Linked User Account .....	141
Delete a Linked User Account .....	143
Custom Group Permissions .....	145
Generate API Keys .....	147
Delete API Keys .....	149
User Account Options .....	150
LDAP Authentication .....	160
Add an LDAP Server .....	165
LDAP User Provisioning .....	166
Configure LDAP User Provisioning .....	167
Delete an LDAP Server .....	170
LDAP Servers with Multiple OUs .....	171
SAML Authentication .....	174



Configure SAML Authentication Automatically via the User Interface .....	177
Configure SAML Authentication Manually via the User Interface .....	179
Configure SAML Authentication via the SimpleSAML Module .....	181
SAML User Provisioning .....	185
Configure SAML User Provisioning .....	186
SAML Authentication XML Configuration Examples .....	188
Certificate Authentication .....	193
Configure Tenable Security Center to Allow SSL Client Certificate Authentication .....	194
Configure a CRL in Tenable Security Center .....	196
Configure OCSP Validation in Tenable Security Center .....	200
Search .....	202
Certificates and Certificate Authorities in Tenable Security Center .....	204
Tenable Security Center Server Certificates .....	205
Upload a Server Certificate for Tenable Security Center .....	206
Regenerate the Tenable Security Center Server Certificate .....	208
Trust a Custom CA .....	210
System Settings .....	211
Configuration Settings .....	212
Edit Plugin and Feed Settings and Schedules .....	224
Configure Plugin Text Translation .....	226
API Key Authentication .....	227
Enable API Key Authentication .....	228
Disable API Key Authentication .....	229
Enable Picture in Picture .....	230



Disable Picture in Picture .....	231
Tenable Lumin Data .....	232
View Tenable Lumin Metrics .....	233
View Tenable Lumin Data Synchronization Logs .....	235
Edit an ACR Manually .....	238
Diagnostics Settings .....	240
Generate a Diagnostics File .....	242
Diagnostics File Options .....	243
Enable Debugging Logs .....	247
Download Debugging Logs .....	248
Disable Debugging Logs .....	249
Job Queue Events .....	250
System Logs .....	251
View System Logs .....	252
Publishing Sites Settings .....	253
Keys Settings .....	254
Add a Key .....	255
Delete a Key .....	256
Download the Tenable Security Center SSH Key .....	257
Notifications .....	258
User Profile Menu Settings .....	259
Custom Plugin Packages for NASL and CA Certificate Upload .....	262
Create the Custom Plugin Package .....	264
Upload the Custom Plugin Package .....	265



Troubleshooting Issues with the custom_CA.inc File .....	266
Backup and Restore .....	268
Perform a Backup .....	271
Restore a Backup .....	273
Perform a Configuration Backup .....	275
Restore a Configuration Backup .....	277
Tenable Lumin Synchronization .....	279
Plan Your Tenable Lumin Synchronization .....	281
Network Support and Repository Overlap .....	285
Configure Tenable Lumin Synchronization .....	287
View Tenable Lumin Synchronization Status .....	292
Disable Tenable Lumin Synchronization .....	295
<b>Configure Scans .....</b>	<b>296</b>
Scanning Overview .....	297
Resources .....	299
Tenable Nessus Scanners .....	300
Add a Tenable Nessus Scanner .....	304
Add a Tenable Vulnerability Management Scanner .....	307
Tenable Nessus Scanner Statuses .....	310
Manage Nessus Scanners .....	314
View Your Nessus Scanners .....	315
View Details for a Nessus Scanner .....	317
View Tenable Nessus Instances in Tenable Security Center .....	320
Download Tenable Nessus Scanner Logs .....	322



Delete a Nessus Scanner .....	324
Tenable Nessus Network Monitor Instances .....	325
Add an Tenable Nessus Network Monitor Instance .....	327
View Your Tenable Nessus Network Monitor Instances .....	329
Tenable Nessus Network Monitor Instance Settings .....	330
Tenable Log Correlation Engines .....	332
Add a Tenable Log Correlation Engine Server .....	334
Tenable Log Correlation Engine Clients .....	336
Tenable Log Correlation Engine Client Policies .....	337
Tenable OT Security Instances .....	338
Repositories .....	339
Add a Repository .....	340
Manage Repositories .....	342
View Your Repositories .....	344
View Repository Details .....	345
Export a Repository .....	349
Import a Repository .....	352
Delete a Repository .....	353
Local Repositories .....	354
IPv4/IPv6 Repositories .....	355
Mobile Repositories .....	358
Agent Repositories .....	367
Universal Repositories .....	369
External Repositories .....	372





Offline Repositories .....	373
Remote Repositories .....	376
Tiered Remote Repositories .....	378
Configure Tiered Remote Repositories .....	379
Active Scans .....	380
Add an Active Scan .....	382
Configure vSphere Scanning .....	385
Manage Active Scans .....	388
Start or Pause a Scan .....	391
Suspend or Resume a Scheduled Active Scan .....	392
Run a Diagnostic Scan .....	393
Active Scan Settings .....	395
Launch a Remediation Scan .....	401
Attack Surface Domain Discovery .....	403
Add a Domain .....	404
View Domain Details .....	405
Delete a Domain .....	406
Active Scan Objects .....	407
Assets .....	409
Add a Template-Based Asset .....	418
Add a Custom Asset .....	420
View Asset Details .....	421
View Hosts .....	423
Export Hosts .....	425



Host Asset Filter Components .....	426
View Domain Inventory Assets .....	427
Export Domain Inventory Assets .....	428
Credentials .....	429
Add Credentials .....	430
Miscellaneous Credentials .....	432
API Gateway Credentials .....	434
Database Credentials .....	436
IBM DB2 .....	437
Informix/DRDA .....	438
MySQL .....	439
Oracle Database .....	441
PostgreSQL .....	443
SQL Server .....	444
Sybase ASE .....	445
Apache Cassandra .....	445
MongoDB .....	446
Database Credentials Authentication Method Settings .....	447
SNMP Credentials .....	458
SSH Credentials .....	459
Privilege Escalation .....	476
Windows Credentials .....	479
Audit Files .....	494
Add a Template-Based Audit File .....	496



Add a Custom Audit File .....	497
Manage Audit Files .....	499
Scan Zones .....	502
Add a Scan Zone .....	505
View Your Scan Zones .....	506
Edit a Scan Zone .....	507
Delete a Scan Zone .....	508
Scan Policies .....	509
Add a Scan Policy .....	510
Scan Policy Templates .....	512
Scan Policy Options .....	517
Configure Compliance Options .....	546
Configure Plugin Options .....	547
Host .....	550
Miscellaneous .....	551
Plaintext Authentication .....	556
Patch Management .....	560
View Your Scan Policies .....	569
View Scan Policy Details .....	570
Edit a Scan Policy .....	572
Share or Revoke Access to a Scan Policy .....	573
Export a Scan Policy .....	574
Import a Scan Policy .....	576
Copy a Scan Policy .....	578



Delete a Scan Policy .....	579
Agent Scanning .....	581
Agent Scans .....	583
Add an Agent Scan .....	584
Manage Agent Scans .....	586
Start or Pause a Scan .....	588
Agent Scan Settings .....	589
Agent Synchronization Jobs .....	592
Add an Agent Synchronization Job .....	593
Manage Agent Synchronization Jobs .....	595
Agent Synchronization Job Settings .....	598
Freeze Windows .....	601
Add a Freeze Window .....	603
Edit a Freeze Window .....	604
Delete a Freeze Window .....	605
Tags .....	606
Add a Tag .....	607
Remove or Delete a Tag .....	608
<b>Analyze Data .....</b>	<b>609</b>
Dashboards .....	610
View a Dashboard .....	612
Overview Dashboard .....	614
Health Overview Dashboard .....	616
LCE Overview Dashboard .....	620



Set a Dashboard as Your Default Dashboard .....	621
Add a Template-Based Dashboard .....	622
Add a Custom Dashboard .....	624
Dashboard and Component Templates .....	626
Import a Dashboard .....	628
Manage Dashboards .....	629
Edit Settings for a Dashboard .....	631
Share or Revoke Access to a Dashboard .....	632
Delete a Dashboard .....	633
Manage Dashboard Components .....	634
Add a Template-Based Dashboard Component .....	636
Add a Custom Dashboard Component .....	638
Custom Dashboard Component Options .....	640
Configure a Simple Matrix Dashboard Component .....	650
Interact with a Customizable Table .....	655
Scan Results .....	657
Scan Result Statuses .....	658
Manage Scan Results .....	660
View Scan Results .....	665
View Scan Result Details .....	667
Upload Scan Results .....	670
Solutions Analysis .....	672
View Solutions .....	673
View Solution Details .....	675



Export Hosts Affected by a Solution .....	677
Vulnerability Analysis .....	680
Cumulative vs. Mitigated Vulnerabilities .....	681
View Cumulative or Mitigated Vulnerabilities .....	682
CVSS vs. VPR .....	683
CVSS .....	684
Vulnerability Priority Rating .....	685
VPR Key Drivers .....	686
Vulnerability Analysis Tools .....	688
Vulnerability Analysis Filter Components .....	694
View Vulnerabilities by Host .....	706
View Vulnerabilities by Plugin .....	708
View Vulnerability Instance Details .....	711
View Host Details .....	713
View Plugin Details .....	717
Export Vulnerability Data .....	719
Event Analysis .....	720
Event Analysis Tools .....	723
Event Analysis Filter Components .....	727
Mobile Analysis .....	730
Mobile Analysis Filter Components .....	731
Reports .....	733
Manage Reports .....	734
Create a Custom Report .....	735



Create a Template Report .....	736
Data Required for Template-Based Reports .....	739
Report Templates .....	740
Edit a Report Definition .....	742
Report Options .....	743
Edit a Report Outline .....	752
Add a Custom Chapter to a Report .....	754
Add a Template Chapter to a Report .....	755
Add or Edit a Report Element .....	758
Configure a Grouping Element in a Report .....	759
Configure a Text Element in a Report .....	764
Configure a Matrix Element in a Report .....	767
Configure a Table Element in a Report .....	771
Configure a Charts Element in a Report .....	774
Reorder Report Chapters and Elements .....	778
Manage Filters for a Chapter Report .....	779
Manage Filter Components for a Single Element .....	780
Manage Filter Components for Multiple Elements .....	782
Manage Filter Components for a Non-Chapter Report .....	784
View a Report Definition .....	786
Copy a Report Definition .....	787
Export a Report Definition .....	788
Import a Report Definition .....	790
Delete a Report Definition .....	791



Launch a Report on Demand .....	792
Add a Report to a Scan .....	793
Manage Report Results .....	794
Stop a Running Report .....	795
Download a Report Result .....	796
View a Report Result .....	797
Publish a Report Result .....	798
Email a Report Result .....	799
Copy a Report Result .....	800
View Errors for a Failed Report .....	801
Delete a Report Result .....	802
CyberScope and DISA Report Attributes .....	803
Report Images .....	806
Assurance Report Cards .....	807
Add a Template-Based Assurance Report Card .....	808
Add a Custom Assurance Report Card .....	809
View Your Assurance Report Cards .....	810
View Details for an Assurance Report Card .....	812
Edit an Assurance Report Card .....	814
Share or Revoke Access to an Assurance Report Card .....	815
Export an Assurance Report Card .....	816
Copy an Assurance Report Card .....	818
Delete an Assurance Report Card .....	819
Assurance Report Card Options .....	820





Filters .....	823
Apply a Filter .....	824
Filter Components .....	826
Queries .....	830
Add or Save a Query .....	831
Load a Query .....	833
Query Options .....	834
Edit a Query .....	837
Workflow Actions .....	838
Alerts .....	839
Alert Actions .....	840
Add an Alert .....	845
View Alert Details .....	846
Alert Options .....	848
Edit an Alert .....	850
Evaluate an Alert .....	851
Delete an Alert .....	852
Tickets .....	853
Open a Ticket .....	854
View Ticket Details .....	856
Ticket Options .....	858
Edit a Ticket .....	860
Resolve and Close a Ticket .....	861
Accept Risk Rules .....	863



Add an Accept Risk Rule .....	864
Delete an Accept Risk Rule .....	866
Recast Risk Rules .....	867
Add a Recast Risk Rule .....	868
Delete a Recast Risk Rule .....	870
<b>Additional Resources .....</b>	<b>871</b>
Start, Stop, or Restart Tenable Security Center .....	872
License Declarations .....	873
Encryption Strength .....	874
Configure SSL/TLS Strong Encryption .....	876
Configure Tenable Security Center for NIAP Compliance .....	878
File and Process Allow List .....	880
Manual Log Correlation Engine Key Exchange .....	881
Manual Tenable Nessus SSL Certificate Exchange .....	884
Overview of Tenable Nessus SSL Certificates and Keys .....	885
Tenable Nessus Certificate Configuration for Unix .....	886
Tenable Nessus Certificate Configuration for Windows .....	895
Offline Tenable Security Center Plugin and Feed Updates .....	900
Perform an Offline Nessus Plugin Update .....	901
Perform an Offline Tenable Nessus Network Monitor Plugin Update .....	903
Perform an Offline Tenable Security Center Feed Update .....	905
Troubleshooting .....	907
General Tenable Security Center Troubleshooting .....	908
Tenable Log Correlation Engine Troubleshooting .....	910



---

Tenable Nessus Troubleshooting .....	912
Tenable Nessus Network Monitor Troubleshooting .....	915
Error Messages .....	917



---

## Welcome to Tenable Security Center

---

This user guide describes how to install, configure, and manage Tenable Security Center™(Formerly Tenable.sc) 6.0.x.

Tenable Security Center is a comprehensive vulnerability management solution that provides complete visibility into the security posture of your distributed and complex IT infrastructure. Tenable Security Center consolidates and evaluates vulnerability data from across your entire IT infrastructure, illustrates vulnerability trends over time, and assesses risk with actionable context for effective remediation prioritization.

To get started, see [Get Started With Tenable Security Center](#).



---

# Get Started With Tenable Security Center

---

Use the following getting started sequence to configure and mature your Tenable Security Center deployment.

1. [Prepare](#)
2. [Install](#)
3. [Configure Scans](#)
4. [Refine](#)
5. [Expand](#)

## Prepare

Before you begin, learn about Tenable Security Center and establish a deployment plan and analysis workflow to guide your configurations.

- Access Tenable Support and training resources for Tenable Security Center, including:
  - the [Tenable University](#) training courses
  - the [Tenable Scan Strategy](#) guide
- Design a deployment plan by identifying your organization's objectives and analyzing your network topology. Consider Tenable-recommended best practices for your environment. For more information about environment requirements, see [Requirements](#). For information about scan types, see [Scanning Overview](#).
- Design an analysis workflow. Identify key stakeholders in your management and operational groups, considering the data you intend to share with each stakeholder.

For more information about planning a large enterprise deployment of Tenable Security Center, see the [Tenable Security Center Large Enterprise Deployment Guide](#).

For more information about the basic architecture of a Tenable Security Center deployment, see [Tenable Security Center Architecture](#).

## Install



---

Install Tenable Security Center and perform initial configuration.

1. Depending on your environment, [install in your environment](#) or [deploy or install with Tenable Core](#).

For complete information about Tenable Core + Tenable Security Center, see the [Tenable Core User Guide](#).

2. Perform quick setup, as described in [Quick Setup](#). You can:
  - Upload licenses
  - Configure one Tenable Nessus scanner
  - Configure one Tenable Nessus Network Monitor scanner (requires a Tenable Nessus Network Monitor activation license)
  - Configure one Tenable Log Correlation Engine server (requires an Tenable Log Correlation Engine@activation license)
  - Create one repository
  - Create one organization
  - Configure one LDAP server
  - Create one administrator user account and one security manager account
  - Configure usage statistic collection

Tenable recommends following the quick setup wizard, but you can configure these features later. For example, do not configure LDAP until you have easy access to all necessary LDAP parameters.

3. Configure SMTP settings, as described in [Mail Settings](#).
4. Configure scan zones, as described in [Add a Scan Zone](#).
5. Configure additional repositories, if necessary, as described in [Repositories](#).
6. Configure additional scanners, if necessary, as described in [Tenable Nessus Scanners](#), [Tenable Nessus Network Monitor Instances](#), and [Tenable Log Correlation Engines](#).
7. Configure security settings (e.g., password complexity requirements and custom banners), as described in [Security Settings](#).



## Configure Scans

Configure and run basic scans to begin evaluating the effectiveness of your deployment plan and analysis workflow.

1. Configure credentials, as described in [Credentials](#).
2. Create static assets, as described in [Add a Custom Asset](#). For more information about asset types, see [Assets](#).
3. Configure a Host Discovery policy and a Basic Network Scan policy from Tenable-provided scan policy templates, as described in [Add a Scan Policy](#).
4. Configure and run scans for those policies, as described in [Add an Active Scan](#) and [Add an Agent Scan](#).
5. Confirm that the scans can access all areas of your network with no credential issues.
6. Configure Tenable Nessus Network Monitor scanners, as described in [Tenable Nessus Network Monitor Instances](#).
7. When the scans complete, create template-based dashboards and reports, as described in [Dashboards](#) and [Reports](#).
8. Search for vulnerabilities by CVE ID, as described in [Search](#).

Tenable recommends frequently reviewing your scan results and scan coverage. You may need to modify your scan configurations to suit your organization's objectives and reach all areas of your network.

## Refine

Configure other features, if necessary, and refine your existing configurations.

- Configure audit files, as described in [Audit Files](#).
- Create additional scan policies, as described in [Add a Scan Policy](#).
- Configure scan freeze windows, as described in [Add a Freeze Window](#).
- Configure groups, as described in [Add a Group](#).
- Create a custom user role, as described in [Create a User Role](#).



- Create additional user accounts and share objects with users, as described in [User Accounts](#).
- Create dynamic assets and combination assets, as described in [Add a Custom Asset](#). For more information about asset types, see [Assets](#).
- Review the plugin update schedule, as described in [Edit Plugin and Feed Settings and Schedules](#). Consider editing the schedules to suit your needs. For example, you may want to schedule plugin and feed updates to run a few hours before your scheduled scans.
- Add queries and use filters, as described in [Add or Save a Query](#) and [Apply a Filter](#).
- Create custom dashboards and reports, as described in [Dashboards](#) and [Reports](#).
- Create Assurance Report Cards (ARCs), as described in [Assurance Report Cards](#).
- Configure alerts, ticketing, accept risk rules, and recast risk rules, as described in [Workflow Actions](#).
- View vulnerability data and use the built-in analysis tools, as described in [Vulnerability Analysis](#).

## Expand

Review and mature your deployment plan and analysis workflow.

- Conduct weekly meetings to review your organization's responses to identified vulnerabilities.
- Conduct weekly management meetings to oversee your teams executing the analysis workflow.
- Review scan automation settings and consider revising.
- Review your scan results and scan coverage. You may need to modify your scan configurations to suit your organization's objectives and reach all areas of your network.
- Optimize and operationalize your custom dashboards to meet the needs of individual user account holders.
- Optimize and operationalize your custom reports to prepare them for distribution.
- Consider configuring API integrations, as described in the [Tenable Security Center API Guide](#) and the [Tenable Security Center API Best Practices Guide](#).





- Consider synchronizing Tenable Security Center with Tenable Vulnerability Management Tenable Lumin to take advantage of Cyber Exposure features, as described in [Tenable Lumin Synchronization](#).




# Tenable Security Center Architecture

## Physical Architecture

At a high level, a Tenable Security Center deployment has two parts:

- A central Tenable Security Center console to manage scans, reports, user access, and other application tools.
- One or more [scanners](#) to collect data and report results to the Tenable Security Center console.




## Logical Architecture

Tenable Security Center is divided into [organizations](#). Each organization has access to one or more [repositories](#) that store scan data. For example, users in Organization 1 can only see repositories that are assigned to Organization 1, however, a repository can be assigned to more than one organization.

The highest-level user in an organization is the Security Manager. For more information about user permissions, see [User Roles](#).

Very broadly, the logical layout / architecture of Tenable Security Center looks like this:



Many environments have just one organization. The following are some common use cases for multiple organizations:

- Environments where there are multiple departments or entities in a business that are logically independent, but that are all governed by the same structure.
- Acquisitions – there may be a reason to keep the acquiring company and acquired company separate.



## Considerations for Air-Gapped Environments

Consider the following when deploying Tenable Security Center in an air-gapped (offline) environment.

### Architecture

You must deploy a Tenable Security Center and a set of scanners within each air-gapped network.

If you want to consolidate data from other networks with the data generated in your air-gapped network, you can use offline repositories to export data from your air-gapped Tenable Security Center to your other instance of Tenable Security Center. This supports both consolidated and federated reporting structures.

### Upgrades and Updates

Tenable recommends performing Tenable Security Center upgrades at least once a year (quarterly preferred) and plugin/feed updates at least once a month. After you perform a plugin update, run comprehensive scans to take advantage of the new vulnerability data and generate current scan results.

**Note:** A few plugins require internet access and cannot run in an air-gapped environment. For example, Tenable Nessus plugin 52669 checks to see if a host is part of a botnet.

After you perform a plugin update or feed update, verify the files as described in the [knowledge base](#) article.

To perform a Tenable Security Center upgrade or a plugin/feed update offline:

**Tip:** You can use the API to automate some Tenable Security Center upgrade and plugin update process.

1. Download the files in a browser or [via the API](#).
2. Verify the integrity of the files.



- Tenable Security Center upgrade: Compare the download checksum with the checksum on the [Tenable downloads](#) page
  - Plugin/feed update: [Download and compare the checksums](#).
3. Move the files to your Tenable Security Center instance.
  4. Upload the files to Tenable Security Center.
    - Tenable Security Center upgrade: [via the CLI](#).
    - Plugin/feed update: [in a browser](#) or [via the API](#).

## Tenable Nessus Agents

If you deployed Tenable Nessus Manager to manage Tenable Nessus Agents in an air-gapped environment, perform an offline software update (`nessus-agent-updates-X.X.X.tar.gz` on the [Tenable Downloads](#) site) on your Tenable Nessus Manager. Tenable Nessus Manager pushes the update to the managed Tenable Nessus Agents.

For more information, see the [knowledge base](#) article.



# Requirements

You can run Tenable Security Center in the following environments.

Environment			More Information
Tenable Core	Virtual	VMware	<a href="#">Requirements</a> in the <i>Tenable Core User Guide</i>
		Microsoft Hyper-V	
	Cloud	Amazon Web Services (AWS)	
	Hardware		
Other platforms	Cloud	Amazon Web Services (AWS)	<a href="#">Cloud Requirements</a>
	Hardware		<a href="#">Hardware Requirements</a>

For general information about other requirements to run Tenable Security Center, see:

- [System Requirements](#)
- [License Requirements](#)
- [Port Requirements](#)
- [Browser Requirements](#)
- [Tenable Integrated Product Compatibility](#)

For detailed information about running Tenable Security Center in a large enterprise deployments, see [Large Enterprise Deployments](#).



---

## Hardware Requirements

---

You can run Tenable Security Center on hardware, with or without Tenable Core. For more information about Tenable Core, see the [Tenable Core User Guide](#).

**Note:** Tenable strongly discourages running Tenable Security Center or Tenable Core + Tenable Security Center in an environment shared with other Tenable applications.

## Storage Requirements

Tenable recommends installing Tenable Security Center on direct-attached storage (DAS) devices (or storage area networks [SANs], if necessary) with a storage latency of 10 milliseconds or less.

Tenable does not support installing Tenable Security Center on network-attached storage (NAS).

## Disk Space Requirements

Enterprise networks can vary in performance, capacity, protocols, and overall activity. Resource requirements to consider for deployments include raw network speed, the size of the network being monitored, and the configuration of the application. Processors, memory, and network cards will be heavily based on the former. Disk space requirements will vary depending on usage based on the amount and length of time data is stored on the system.

An important consideration is that Tenable Security Center can be configured to save a snapshot of vulnerability archives each day. In addition, the size of the vulnerability data stored by Tenable Security Center depends on the number and types of vulnerabilities, not just the number of hosts. For example, 100 hosts with 100 vulnerabilities each could consume as much data as 1,000 hosts with 10 vulnerabilities each. In addition, the output for vulnerability check plugins that do directory listings, etc. is much larger than Open Port plugins from discovery scans.

For networks of 35,000 to 50,000 hosts, Tenable has encountered data sizes of up to 25 GB. That number is based on storage of 50,000 hosts and approximately 500 KB per host.

Additionally, during active scanning sessions, large scans and multiple smaller scans have been reported to consume as much as 150 GB of disk space as results are acquired. Once a scan has completed and its results are imported, that disk space is freed up.

### Requirements When Running Basic Network Scans + Local Checks



# of Hosts Managed by Tenable Security Center	CPU Cores	Memory	Disk Space used for Vulnerability Trending
2,500 active IPs	4 2GHz cores	8 GB RAM	90 days: 125 GB 180 days: 250 GB
10,000 active IPs	8 3GHz cores	16 GB RAM	90 days: 450 GB 180 days: 900 GB
25,000 active IPs	16 3GHz cores	32 GB RAM	90 days: 1.2 TB 180 days: 2.4 TB
100,000 active IPs	32 3GHz cores	64 GB RAM	90 days: 4.5 TB 180 days: 9 TB

#### Requirements When Running Basic Network Scans + Local Checks + 1 Configuration Audit

# of Hosts Managed by Tenable Security Center	CPU Cores	Memory	Disk Space used for Vulnerability Trending
2,500 active IPs	4 2GHz cores	8 GB RAM	90 days: 225 GB 180 days: 450 GB
10,000 active IPs	8 3GHz cores	16 GB RAM	90 days: 900 GB 180 days: 1.8 TB
25,000 active IPs	16 3GHz cores	32 GB RAM	90 days: 2.25 TB 180 days: 4.5 TB
100,000 active IPs	32 3GHz cores	128 GB RAM	90 days: 9 TB 180 days: 18 TB

#### Disk Partition Requirements





Tenable Security Center installs into `/opt/sc`. Tenable highly recommends that you create the `/opt` directory on a separate disk partition. If you want to increase performance, consider using two disks: one for the operating system and one for the system deployed to `/opt`.

Tenable strongly recommends using high performance disks. Tenable Security Center is a disk-intensive application and using disks with high read/write speeds, such as SSDs, results in the best performance.

If required disk space exists outside of the `/opt` file system, mount the desired target directory using the command `mount --bind <olddir> <newdir>`. Make sure that the file system is automatically mounted on reboot by editing the `/etc/fstab` file appropriately.

**Note:** Tenable Security Center does not support using symbolic links for `/opt/sc/`. You can use symbolic links within `/opt/sc/` subdirectories if instructed by Tenable Security Center documentation or Tenable Support.

Deploying Tenable Security Center on a server configured with RAID disks can also dramatically boost performance.

**Tip:** Tenable does not require RAID disks for even our largest customers. However, in one instance, response times for queries with a faster RAID disk for a customer with more than 1 million managed vulnerabilities moved from a few seconds to less than a second.

## Network Interface Requirements

You can install Tenable Security Center in externally connected or air-gapped environments. For more information about special considerations for air-gapped environments, see [Considerations for Air-Gapped Environments](#).

Gigabit or faster network cards are recommended for use on the Tenable Security Center server. This is to increase the overall performance of web sessions, emails, Tenable Log Correlation Engine queries, and other network activities.



## Cloud Requirements

The primary method to deploy Tenable Security Center in a cloud environment is with Tenable Core + Tenable Security Center. For more information, see the [Tenable Core User Guide](#).

However, you can install Tenable Security Center in vendor-supported version of your cloud environment that meets the [operating system requirements](#) to run Tenable Security Center.

The following guidelines can help you install Tenable Security Center in an Amazon Elastic Compute Cloud (Amazon EC2) cloud-based environment or an Azure Virtual Machine (Azure Virtual Image) cloud-based environment, but they do not cover all deployment scenarios or cloud environments. For assistance with a different cloud environment, contact Tenable Professional Services.

- [Supported Amazon EC2 Instance Types](#)
- [Supported Amazon Machine Images \(AMIs\)](#)
- [Supported Azure Instance Types](#)
- [Supported Azure Machine Images](#)

## Supported Amazon EC2 Instance Types

You can install Tenable Security Center in an Amazon Elastic Compute Cloud (Amazon EC2) cloud-based environment that meets all of the following requirements.

Tenable Security Center uses a balance of networking and compute resources and requires persistent storage for proper operation. To meet these requirements, Tenable supports installing Tenable Security Center on M5 instances with General Purpose SSD (gp2) EBS storage.

Tenable recommends the following Amazon EC2 instance types based on your Tenable Security Center deployment size.

### Requirements When Running Basic Network Scans + Local Checks

# of Hosts Managed by Tenable Security Center	EC2 Instance Type	Disk Space Used for Vulnerability Trending
1 to 2,500	m5.2xlarge	90 days: 125 GB 180 days: 250 GB



2,501 to 10,000	m5.4xlarge	90 days: 450 GB 180 days: 900 GB
10,001 to 25,000	m5.8xlarge	90 days: 1.2 TB 180 days: 2.4 TB
25,001 to 50,000	m5.12xlarge	90 days: 4.5 TB 180 days: 9 TB
50,001 or more	For assistance with large enterprise deployments greater than 50,000 active IP addresses, contact your Tenable representative.	

### Requirements When Running Basic Network Scans + Local Checks + 1 Configuration Audit

# of Hosts Managed by Tenable Security Center	EC2 Instance Type	Disk Space Used for Vulnerability Trending
1 to 2,500	m5.4xlarge	90 days: 225 GB 180 days: 450 GB
2,501 to 10,000	m5.8xlarge	90 days: 900 GB 180 days: 1.8 TB
10,001 to 25,000	m5.8xlarge	90 days: 2.25 TB 180 days: 4.5 TB
25,001 to 50,000	m5.12xlarge	90 days: 9 TB 180 days: 18 TB
50,001 or more	For assistance with large enterprise deployments greater than 50,000 active IP addresses, contact your Tenable representative.	

### Supported Amazon Machine Images (AMIs)



Tenable provides an AMI for Tenable Core, but not for other cloud deployments without Tenable Core. Tenable supports using the following Amazon Marketplace AMI for Tenable Security Center without Tenable Core:

AMI	Required Configuration Changes
<a href="#">CentOS 7 (x86_64) - with Updates HVM</a>	<ul style="list-style-type: none"><li>• This AMI does not include Java, but Tenable Security Center requires OpenJDK or the Oracle Java JRE to export PDF reports. You must install OpenJDK or the Oracle Java JRE onto your AMI before hosting Tenable Security Center. For more information, see <a href="#">Dependencies</a>.</li><li>• This AMI configures an SELinux enforcing mode policy, which requires customization to be compatible with Tenable Security Center. You must use the SELinux <code>seaAlert</code> tool to identify errors and solutions. For more information, see <a href="#">Customize SELinux Enforcing Mode Policies for Tenable Security Center</a>.</li><li>• You must confirm this AMI meets all other standard requirements for operating systems. For more information, see <a href="#">Operating System Requirements</a>.</li></ul>

## Supported Azure Instance Types

You can install Tenable Security Center in an Azure Virtual Machine (Azure Virtual Image) cloud-based environment that meets all of the following requirements.

Tenable recommends the following virtual machine instance types based on your Tenable Security Center deployment size. You may need to increase the storage allocated to the virtual machine instance depending on usage.

### Requirements When Running Basic Network Scans + Local Checks

# of Hosts Managed by Tenable Security Center	Virtual Machine Instance	Disk Space Used for Vulnerability Trending
1 to 2,500	D3V2	90 days: 125 GB



		180 days: 250 GB
2,501 to 10,000	D4V2	90 days: 450 GB 180 days: 900 GB
10,001 to 25,000	F16	90 days: 1.2 TB 180 days: 2.4 TB
25,001 to 50,000	F32SV2	90 days: 4.5 TB 180 days: 9 TB
50,001 or more	For assistance with large enterprise deployments greater than 50,000 active IP addresses, contact your Tenable representative.	

### Requirements When Running Basic Network Scans + Local Checks + 1 Configuration Audit

# of Hosts Managed by Tenable Security Center	EC2 Instance Type	Disk Space Used for Vulnerability Trending
1 to 2,500	D3V2	90 days: 225 GB 180 days: 450 GB
2,501 to 10,000	D4V2	90 days: 900 GB 180 days: 1.8 TB
10,001 to 25,000	F16	90 days: 2.25 TB 180 days: 4.5 TB
25,001 to 50,000	D32SV3	90 days: 9 TB 180 days: 18 TB
50,001 or more	For assistance with large enterprise deployments greater than 50,000 active IP addresses, contact your Tenable representative.	

### Supported Azure Machine Images



Tenable provides an Azure image for Tenable Core, but not for other cloud deployments without Tenable Core. Tenable supports using the following Azure image for Tenable Security Center:

AMI	Required Configuration Changes
<a href="#">CIS CentOS Linux 7 Benchmark L1</a>	<ul style="list-style-type: none"><li>• This image does not include Java, but Tenable Security Center requires OpenJDK or the Oracle Java JRE to export PDF reports. You must install OpenJDK or the Oracle Java JRE onto your image before hosting Tenable Security Center. For more information, see <a href="#">Dependencies</a>.</li><li>• This image configures an SELinux enforcing mode policy, which requires customization to be compatible with Tenable Security Center. You must use the SELinux <code>sealert</code> tool to identify errors and solutions. For more information, see <a href="#">Customize SELinux Enforcing Mode Policies for Tenable Security Center</a>.</li><li>• You must confirm this image meets all other standard requirements for operating systems. For more information, see <a href="#">Operating System Requirements</a>.</li></ul>



---

# System Requirements

---

- [Operating System Requirements](#)
- [SELinux Requirements](#)
- [Secure Environment Requirements](#)
- [Dependencies](#)
- [Tenable Security Center Communications and Directories](#)

## Operating System Requirements

This version of Tenable Security Center is available for:

- Red Hat Enterprise Linux 7 (RHEL 7), 64-bit
- Red Hat Enterprise Linux 8 (RHEL 8), 64-bit
- Red Hat Enterprise Linux 9 (RHEL 9), 64-bit
- CentOS 7, 64-bit
- Oracle Linux 8, 64-bit
- Oracle Linux 9, 64-bit

## SELinux Requirements

Tenable Security Center supports disabled, permissive, and enforcing mode Security-Enhanced Linux (SELinux) policy configurations.

- Disabled and permissive mode policies typically do not require customization to interact with Tenable Security Center.
- Enforcing mode policies require customization to interact with Tenable Security Center. For more information, see [Customize SELinux Enforcing Mode Policies for Tenable Security Center](#).

**Note:** Tenable recommends testing your SELinux configurations before deploying on a live network.

## Secure Environment Requirements



Tenable recommends adhering to security best practices, including:

- Configure the operating system to ensure that security controls cannot be bypassed.
- Configure the network to ensure that the Tenable Security Center system resides in a secure network segment that is not accessible from the Internet.
- Configure network time synchronization to ensure that accurate time stamps are recorded in reports and log files.

**Note:** The time zone is set automatically during the installation process with no user interaction. The time zone configured in `php.ini` must be synchronized with the system time zone in `/etc/sysconfig/clock`.

- Configure access control to ensure that only authorized users have access to the operating system platform.
- Monitor system resources to ensure that adequate disk space and memory are available, as described in [Hardware Requirements](#). If system resources are exhausted, Tenable Security Center may not log audit data during system administrator troubleshooting or other activities. For more information about troubleshooting resource exhaustion, see [General Tenable Security Center Troubleshooting](#).

For information about secure administration of a Red Hat installation, see the *Red Hat Enterprise Linux Security Guide* for your version.

**Note:** Even though the security concepts from this guide are written for RHEL 6, most of the concepts and methodologies apply to earlier versions of RHEL that are supported with Tenable Security Center.

**Note:** As with any application, the security and reliability of the installation is dependent on the environment that supports it. It is strongly recommended that organizations deploying Tenable Security Center have an established and applied IT management policy that covers system administration integrity, resource monitoring, physical security, and disaster recovery.

## Dependencies

**Note:** Either OpenJDK or the Oracle Java JRE along with their accompanying dependencies must be installed on the system along with any additional Java installations removed for reporting to function properly.





**Note:** If you are running Tenable Security Center 5.20.0, you must upgrade pyTenable to version 1.4.2 or later.

**Note:** Tenable does not recommend forcing the installation without all required dependencies. If your version of Red Hat or CentOS is missing certain dependencies, it will cause problems that are not readily apparent with a wide variety of functions. Tenable Support has observed different types of failure modes for Tenable Security Center when dependencies are missing.

**Note:** To run Tenable Security Center 6.0.0, you must install binutils and initscripts. If you try to migrate from an earlier version of Tenable Security Center to Tenable Security Center 6.0.0 on a system that does not have binutils or initscripts installed, the migration will fail.

All dependencies must be installed on the system prior to installing the Tenable Security Center package. While they are not all required by the installation RPM file, some functionality of Tenable Security Center may not work properly if the packages are not installed.

**Note:** Tenable recommends using the latest stable production version of each package.

For a list of required packages, run the following command against the Tenable Security Center RPM file:

```
# yum deplist SecurityCenter-x.x.x-el6.x86_64.rpm
```

- or -

```
# dnf deplist SecurityCenter-x.x.x-el8.x86_64.rpm
```

To determine which version of a dependency is installed on your system, run the following command for each of the packages (replace “libtool” with the appropriate package):

```
# yum list installed | grep libtool
```

- or -

```
# dnf list installed | grep libtool
```

If one of the prerequisite packages is missing, it can be installed using the “yum” or “dnf” package managers. For example, install Java 1.8.0 with “yum” using the command below:



```
# yum -y install java-1.8.0-openjdk.x86_64
```

## Tenable Security Center Communications and Directories

The following table summarizes the components' primary directories and communication methods.

**Note:** Tenable Security Center does not support using symbolic links for `/opt/sc/`. You can use symbolic links within `/opt/sc/` subdirectories if instructed by Tenable Security Center documentation or Tenable Support.

### Tenable Security Center Directories

Installation Directory	<code>/opt/sc</code>
User Data	<code>/opt/sc/orgs/&lt;Organization Serial Number&gt;</code>
Repositories	<code>/opt/sc/repositories/&lt;Repository Number&gt;</code>
Admin Logs	<code>/opt/sc/admin/logs/</code>
Organization Logs	<code>/opt/sc/orgs/&lt;Organization Number&gt;/logs/</code>
Communication Interfaces	<ul style="list-style-type: none"><li>• User Access —HTTPS</li><li>• Feed Updates —Acquired over SSL from Tenable servers directly to Tenable Security Center or for <a href="#">offline installation</a>. Plugin packages are secured via 4096-bit RSA digital signatures.</li></ul> <p>For more information, see <a href="#">Port Requirements</a>.</p>

For information about data encryption in Tenable Security Center, see [Encryption Strength](#).



---

# Customize SELinux Enforcing Mode Policies for Tenable Security Center

---

Security-Enhanced Linux (SELinux) enforcing mode policies require customization to interact with Tenable Security Center.

Tenable Support does not assist with customizing SELinux policies, but Tenable recommends monitoring your SELinux logs to identify errors and solutions for your policy configuration.

Before you begin:

- Install the SELinux `sealert` tool in a test environment that resembles your production environment.

To monitor your SELinux logs to identify errors and solutions:

1. Run the `sealert` tool, where `/var/log/audit/audit.log` is the location of your SELinux audit log:

```
sealert -a /var/log/audit/audit.log
```

The tool runs and generates a summary of error alerts and solutions. For example:

```
SELinux is preventing /usr/sbin/sshd from write access on the sock_file /dev/log
SELinux is preventing /usr/libexec/postfix/pickup from using the rlimitinh access
on a process.
```

2. Execute the recommended solution for each error alert.
3. Restart Tenable Security Center, as described in [Start, Stop, or Restart Tenable Security Center](#).

Tenable Security Center restarts.

4. Run the `sealert` tool again to confirm you resolved the error alerts.



## Use /dev/random for Random Number Data Generation

**Required User Role:** Root user

If your organization requires Tenable Security Center to use /dev/random instead of /dev/urandom to generate random number data for secure communication functions, modify the random data source using an environment variable.

Unlike /dev/urandom, /dev/random blocks HTTPS and SSL/TLS functions if there is not enough entropy to perform the functions. The functions resume after the system generates enough entropy.

**Note:** If /dev/random blocks during an installation or upgrade, the system waits up to 10 minutes for more entropy to be generated before halting the operation.

Tenable does not recommend using /dev/random unless required by your organization.

To use /dev/random for random number data generation in Tenable Security Center:

1. Log in to Tenable Security Center via the command line interface (CLI).
2. In the CLI in Tenable Security Center, run the following command:

```
export TSC_ENTROPY_CHECK=true
```

Tenable Security Center recognizes the environment variable and uses /dev/random.

What to do next:

- Install or upgrade Tenable Security Center in order for your changes to take effect, as described in [Install Tenable Security Center](#) or [Upgrade Tenable Security Center](#).



---

## Tenable Security Center Database Journaling Modes

---

By default, Tenable Security Center databases that can significantly impact performance use write-ahead logging (WAL) journaling mode. All other databases use DELETE mode. Tenable Security Center also supports converting WAL journaling mode databases to DELETE mode.

For Tenable Security Center installations where WAL is not enabled, enabling WAL may resolve issues with excessive database locks. If your Tenable Security Center does not experience database locking issues, Tenable recommends leaving your Tenable Security Center databases in the default journaling mode.

Tenable strongly recommends performing a backup before converting database journaling modes and performing regular backups after converting database journaling modes. For more information, see [Backup and Restore](#).

For general information about SQLite3 database journaling modes, see the [SQLite3 documentation](#).

For more information, see:

- [Enable Write-Ahead Logging](#)
- [Disable Write-Ahead Logging](#)

**Note:** If you previously converted one or more Tenable Security Center databases to WAL journaling mode without using the `convertDatabaseMode.php` script, you must use the `convertDatabaseMode.php` script to ensure your Tenable Security Center databases are fully converted to WAL journaling mode.

### WAL Requirements

In addition to the [requirements](#) to run Tenable Security Center, your Tenable Security Center installation must be running Tenable Security Center 5.19.x or later.

### Databases Affected

Enabling or disabling WAL converts the database journaling mode for the following Tenable Security Center databases:

- `/opt/sc/application.db`
- `/opt/sc/hosts.db`



- /opt/sc/jobqueue.db
- /opt/sc/plugins.db
- /opt/sc/remediationHierarchy.db
- /opt/sc/orgs/<orgID>/organization.db (for each organization in your Tenable Security Center)
- /opt/sc/orgs/<orgID>/assets.db (for each organization in your Tenable Security Center)

The `convertDatabaseMode.php` script only converts the database journaling mode for Tenable Security Center databases that can significantly impact performance.



## Enable Write-Ahead Logging

**Required User Role:** Root user

**Note:** This topic assumes a basic understanding of Linux.

You can use the `convertDatabaseMode.php` script to enable write-ahead logging (WAL) journaling mode for Tenable Security Center databases. Enabling WAL may resolve issues with excessive database locks. If your Tenable Security Center does not experience database locking issues, Tenable recommends leaving your Tenable Security Center databases in the default DELETE journaling mode.

For more information, see [Tenable Security Center Database Journaling Modes](#).

Before you begin:

- Confirm your Tenable Security Center installation meets the requirements to enable WAL. For more information, see [WAL Requirements](#).
- Perform a backup of Tenable Security Center, as described in [Perform a Backup](#).

To enable WAL:

1. Log in to Tenable Security Center via the command line interface (CLI).
2. Stop Tenable Security Center, as described in [Start, Stop, or Restart Tenable Security Center](#).
3. In the CLI in Tenable Security Center, run the following command to start the `convertDatabaseMode.php` script:

```
/opt/sc/support/bin/php /opt/sc/src/tools/convertDatabaseMode.php -m WAL
```

The script runs.

4. If the script detects any running `tns` user processes, repeat the following steps for each `tns` user process detected:



- a. Follow the prompts in the error output to halt the tns user process.

Example error output:

```
Error! The Tenable.sc process with PID '10135' is still running and needs to
be halted before this script can be executed successfully.
  Command: /opt/sc/support/bin/php -f /opt/sc/daemons/Jobd.php
Bailing with 146.
```

- b. Run the following command to restart the `convertDatabaseMode.php` script:

```
/opt/sc/support/bin/php /opt/sc/src/tools/convertDatabaseMode.php -m WAL
```

The script restarts.

Tenable Security Center converts supported databases to WAL journaling mode. For more information, see [Databases Affected](#).

5. Start Tenable Security Center, as described in [Start, Stop, or Restart Tenable Security Center](#).

What to do next:

- Perform regular backups of Tenable Security Center, as described in [Perform a Backup](#).





## Disable Write-Ahead Logging

**Required User Role:** Root user

**Note:** This topic assumes a basic understanding of Linux.

If you experience issues with write-ahead logging (WAL), disable WAL by reverting your Tenable Security Center databases to DELETE journaling mode. For more information, see [Tenable Security Center Database Journaling Modes](#).

Before you begin:

- Perform a backup of Tenable Security Center, as described in [Perform a Backup](#).

To disable WAL:

1. Log in to Tenable Security Center via the command line interface (CLI).
2. Stop Tenable Security Center, as described in [Start, Stop, or Restart Tenable Security Center](#).
3. In the CLI in Tenable Security Center, run the following command to start the `convertDatabaseMode.php` script:

```
/opt/sc/support/bin/php /opt/sc/src/tools/convertDatabaseMode.php -m DELETE
```

The script runs.

4. If the script detects any running `tns` user processes, repeat the following steps for each `tns` user process detected:
  - a. Follow the prompts in the error output to halt the `tns` user process.

Example error output:

```
Error! The Tenable.sc process with PID '10135' is still running and needs to  
be halted before this script can be executed successfully.  
Command: /opt/sc/support/bin/php -f /opt/sc/daemons/Jobd.php  
Bailing with 146.
```



- b. Run the following command to restart the `convertDatabaseMode.php` script:

```
/opt/sc/support/bin/php /opt/sc/src/tools/convertDatabaseMode.php -m DELETE
```

The script restarts.

Tenable Security Center converts supported databases to DELETE journaling mode. For more information, see [Databases Affected](#).

5. Start Tenable Security Center, as described in [Start, Stop, or Restart Tenable Security Center](#).

What to do next:

- Perform regular backups of Tenable Security Center, as described in [Perform a Backup](#).



## License Requirements

Tenable Security Center does not support an unlicensed demo mode. License keys are required for Tenable Security Center and for all attached Tenable products. You first configure your Tenable Security Center license and additional Tenable product licenses during quick start, as described in [Quick Setup](#).

You can update your Tenable Security Center license in an externally connected or air-gapped environment, as described in [Update an Existing License](#).

Tenable Security Center requires an internet connection to validate additional Tenable product licenses. To apply a license for an additional Tenable product, see [Apply a New License](#). To update a license for an additional Tenable product, see [Update an Existing License](#).

**Tip:** For information about Tenable Security Center-Tenable product registration server communications encryption, see [Encryption Strength](#).

## Your Tenable Security Center License

Tenable Security Center licenses are valid for a specific hostname and for a maximum number of active assets (identified by IP address or UUID). Assets are counted towards your license limit depending on how Tenable Security Center discovers, or sees, the asset. In general, an asset does not count against your license limit unless it has been assessed for vulnerabilities.

For example, if you purchase a 500 asset Tenable Security Center license, you can perform host discovery on your network but you cannot assess more than 500 assets. For more information about discovery and assessment scanning, see [Scanning Overview](#).

Tenable Security Center generates a warning in the web interface when you approach or exceed the license limit. To monitor your license limit, use the **Licensing Status** widget, as described in [Overview Dashboard](#). To upgrade your license, contact your Tenable representative.

Counted Toward License	Not Counted Toward License
<ul style="list-style-type: none"><li>• IP addresses from active scans</li><li>• IP addresses from Tenable Log Correlation Engine instances</li></ul>	<ul style="list-style-type: none"><li>• IP addresses present only from imports to offline repositories</li><li>• IP addresses present only from Tenable Nessus Network Monitor instances in dis-</li></ul>



Counted Toward License	Not Counted Toward License
<ul style="list-style-type: none"><li>• IP addresses from Tenable Nessus Network Monitor instances not in discovery mode</li><li>• UUIDs from Tenable OT Security instances</li><li>• IP addresses in offline repositories that you downloaded using the same Tenable Security Center instance or license</li></ul> <p>A single IP address or UUID counts once toward your license, even if it was scanned by multiple methods or stored in multiple repositories.</p> <div style="border: 1px solid blue; padding: 5px;"><p><b>Note:</b> If you use an alternative port scanner, Tenable Security Center counts the detected IP addresses against your license.</p></div>	<p>covery mode</p> <ul style="list-style-type: none"><li>• IP addresses in offline repositories that you downloaded using the same Tenable Security Center instance with a different license</li><li>• IP addresses in offline repositories that you downloaded using a different Tenable Security Center instance and license</li><li>• The following excluded plugins:  <b>Tenable Nessus</b> —10180, 10287, 10335, 11219, 11933, 11936, 12053, 14272, 14274, 19506, 22964, 33812, 33813, 34220, 34277, 45590, 54615, 87413, 112154, and 161455.  <b>Tenable Nessus Network Monitor</b> —0, 12, 18, 19, 20, 113, and 132.  <b>LCE</b> —800000 through 800099.</li></ul>

## Your Tenable Security Center+ Product Licenses

**Tip:** Tenable rebranded Tenable Security Center Continuous View as Tenable Security Center+.

If you want to use Tenable Security Center with other Tenable products, you must add their activation codes to Tenable Security Center. For more information, see [Apply a New License](#).

## Your Tenable Lumin License

If you want to view and analyze your data in Tenable Vulnerability Management using Tenable Lumin, you must acquire a Tenable Lumin license for use with your Tenable Security Center deployment.

**Tip:** Synchronized assets that count toward your Tenable Security Center license also count toward your Tenable Vulnerability Management license.

For more information, contact your Tenable representative.



## Apply a New License

**Required User Role:** Administrator

To apply a license for an additional Tenable product, add the license activation code. To update a license for an existing Tenable product, see [Update an Existing License](#).

For general information about licensing, see [License Requirements](#). For information about adding a license during quick setup, see [Quick Setup](#).

To download Tenable Security Center, see the [Tenable Security Center downloads](#) page.

To apply a new Tenable Nessus, Tenable Nessus Network Monitor, or Log Correlation Engine license:

1. Log in to Tenable Security Center via the user interface.
2. Click **System > Configuration**.

The **Configuration** page appears.

3. Click the **License** tile.

The **License Configuration** page appears.

4. Click the product box for the license you want to apply.
5. In the box, type the activation code for the product.
6. Click **Register**.

Tenable Security Center updates the page to reflect the activation code status:

- Valid Code: A green box with a check mark.
- Invalid Code: A red box with an X.

If the code is valid, Tenable Security Center initiates a plugin download.



## Update an Existing License

**Required User Role:** Administrator

**Tip:** Tenable rebranded Tenable Security Center Continuous View as Tenable Security Center+.

If you need to replace your Tenable Security Center or Tenable Security Center+ license or the license activation code for your Tenable Nessus, Tenable Nessus Network Monitor, or Tenable Log Correlation Engine license, update the license.

To apply a new license for another Tenable product for the first time, see [Apply a New License](#).

You can update your Tenable Security Center license in an externally connected or air-gapped environment. Tenable Security Center requires an internet connection to validate product licenses for Tenable Nessus, Tenable Nessus Network Monitor, or Log Correlation Engine.

For instructions on how to install a Tenable Security Center patch, see [Install a Tenable Security Center Patch](#).

To download Tenable Security Center, see the [Tenable Security Center Downloads](#) page.

For general information about licensing, see [License Requirements](#).

To update a license:

1. Log in to Tenable Security Center via the user interface.
2. Click **System > Configuration**.

The **Configuration** page appears.

3. Click the **License** tile.

The **License Configuration** page appears.

4. To replace your Tenable Security Center license, in the **Tenable Security Center License** section:



- a. Click **Update License**.
- b. Click **Choose File** and browse to the license file you want to upload.

Tenable Security Center applies the new license.

5. To replace an activation code for an integrated product license, in the **Activation Codes** section:

- a. Click the green check mark.
- b. Click **Reset Activation Code**.
- c. In the box, paste your product license activation code.
- d. Click **Register**.

Tenable Security Center communicates with the Tenable product registration server to validate your license activation code.

If the code is valid, Tenable Security Center applies the new license and initiates a plugin download.



---

# Tenable Security Center+ License Expiration

---

**Tip:** Tenable rebranded Tenable Security Center Continuous View as Tenable Security Center+.

This topic describes the behavior of Tenable Security Center+ if you allow your software maintenance license to expire. Software maintenance licenses can be either perpetual or subscription-based.

## Tenable Security Center Console

- Perpetual license —The software remains fully functional. All user data is accessible.
- Subscription license —You can no longer access the console unless you enter a new license key. Normal operation resumes once you replace the license key.

## Tenable Nessus

When the software maintenance period expires, Tenable Nessus stops receiving plugin updates. After a period of 90 days, Tenable Nessus stops working and cannot perform new scans. Because Tenable Security Center stops receiving feeds once the maintenance period expires, the Tenable Nessus scanners managed by Tenable Security Center no longer receive updates and stop working after the 90 day period.

## Tenable Nessus Network Monitor

After 30 days with no updates, Tenable Nessus Network Monitor stops processing new data.

## Log Correlation Engine

Log Correlation Engine stops processing new logs on the day of license expiration.





## Port Requirements

Tenable Security Center port requirements include Tenable Security Center-specific and application-specific requirements.

- [Tenable Security Center](#)
- [Tenable Nessus Scanner](#)
- [Tenable Nessus Agent](#)
- [Tenable Nessus Network Monitor](#)
- [Tenable Log Correlation Engine](#)

### Tenable Security Center

Your Tenable Security Center instances require access to specific ports for inbound and outbound traffic.

#### Inbound Traffic

You must allow inbound traffic to the following ports.

Port	Traffic
TCP 22	Performing remote repository synchronization with another Tenable Security Center.
TCP 443	Accessing the Tenable Security Center interface. Communicating with Tenable Security Center Director instances. Communicating with Tenable OT Security instances. Performing the initial key push for remote repository synchronization with another Tenable Security Center. Interacting with the API.

#### Outbound Traffic

You must allow outbound traffic to the following ports.



Port	Traffic
TCP 22	Communicating with Log Correlation Engine for event query.
TCP 25	Sending SMTP email notifications.
TCP 443	Communicating with Tenable Vulnerability Management. Communicating with Tenable Lumin for synchronization. Communicating with the <code>plugins.nessus.org</code> server for plugin updates.
TCP 1243	Communicating with Tenable Log Correlation Engine.
TCP 8834	Communicating with Tenable Nessus.
TCP 8835	Communicating with Tenable Nessus Network Monitor.
UDP 53	Performing DNS resolution.

## Tenable Nessus Scanner

Your Tenable Nessus instances require access to specific ports for inbound and outbound traffic.

### Inbound Traffic

You must allow inbound traffic to the following ports.

Port	Traffic
TCP 8834	Accessing the Tenable Nessus interface. Communicating with Tenable Security Center. Interacting with the API.

### Outbound Traffic

You must allow outbound traffic to the following ports.

Port	Traffic
TCP 25	Sending SMTP email notifications.



Port	Traffic
TCP 443	Communicating with Tenable Vulnerability Management. Communicating with the <code>plugins.nessus.org</code> server for plugin updates.
UDP 53	Performing DNS resolution.

## Tenable Nessus Agent

Your Tenable Nessus Agents require access to specific ports for outbound traffic.

### Outbound Traffic

You must allow outbound traffic to the following ports.

Port	Traffic
TCP 443	Communicating with Tenable Vulnerability Management.
TCP 8834	Communicating with Tenable Nessus Manager. <b>Note:</b> The default Tenable Nessus Manager port is TCP 8834. However, this port is configurable and may be different for your organization.
UDP 53	Performing DNS resolution.

## Tenable Nessus Network Monitor

Your Tenable Nessus Network Monitor instances require access to specific ports for inbound and outbound traffic.

### Inbound Traffic

You must allow inbound traffic to the following ports.

Port	Traffic
TCP 8835	Accessing the Tenable Nessus Network Monitor interface. Communicating with Tenable Security Center.



## Outbound Traffic

You must allow outbound traffic to the following ports.

Port	Traffic
TCP 443	Communicating with Tenable Vulnerability Management. Communicating with the <code>plugins.nessus.org</code> server for plugin updates.
TCP 601	Communications for reliable TCP syslog forwarding.
UDP 53	Performing DNS resolution.
UDP 514	Communications for UDP syslog forwarding.

## Tenable Log Correlation Engine

Your Log Correlation Engine and Log Correlation Engine client instances require access to specific ports for inbound and outbound traffic.

### Inbound Traffic

You must allow inbound traffic to the following ports.

Port	Traffic
Log Correlation Engine	
TCP 22	Communicating with Tenable Security Center for Log Correlation Engine event query.
TCP 601	Communications for reliable TCP syslog forwarding.
TCP 1243	Communicating with Tenable Security Center for Log Correlation Engine event vulnerability import.
TCP 8836	Accessing the Log Correlation Engine interface.
TCP 31300	Communicating with Log Correlation Engine clients.



Port	Traffic
UDP 162	Communicating with SNMP server for receiving SNMP traps.
UDP 514	Communications for UDP syslog forwarding.
Log Correlation Engine Client	
TCP 1468	Communications between network devices and the Tenable Network Monitor.
TCP 9800	Communications between Splunk and the Log Correlation Engine Splunk Client.
TCP 18185	Communications between Check Point firewalls and the Log Correlation Engine OPSEC Client.
UDP 514	Communications between network devices and the Tenable Network Monitor.
UDP 2055	Communications between routers and the Tenable NetFlow Monitor.

## Outbound Traffic

You must allow outbound traffic to the following ports.

Port	Traffic
Log Correlation Engine	
TCP 25	Sending SMTP email notifications.
TCP 443	Communicating with Tenable Vulnerability Management. Communicating with the <code>plugins.nessus.org</code> server for plugin updates.
TCP 601	Communications for reliable TCP syslog forwarding.
UDP 53	Performing DNS resolution.
UDP 514	Communications for UDP syslog forwarding.
Log Correlation Engine Client	
TCP 135	Communicating with the targets of the Log Correlation Engine WMI Monitor Client.
TCP 443	Communicating with the web host of the Log Correlation Engine Web Query Client.



Port	Traffic
	ent.
TCP 445	Communicating with the targets of the Log Correlation Engine WMI Monitor Client.
TCP 31300	Communicating with Log Correlation Engine.



---

## Browser Requirements

---

**Note:** Tenable recommends using the newest available version of your browser.

You can access the Tenable Security Center user interface using the following browsers:

- Microsoft Internet Explorer 11 or later

**Tip:** Tenable Security Center versions 5.22 and later do not support Internet Explorer.

- Microsoft Edge 99 or later
- Mozilla Firefox 32 or later
- Google Chrome 37 or later
- Mac OS Safari 7.1 or later



---

## Tenable Integrated Product Compatibility

---

The release notes list the versions of Tenable products tested with Tenable Security Center 6.0.x. For more information, see the [Tenable Security Center Release Notes](#) for your version.





---

## Large Enterprise Deployments

---

You may have a number of unique technical and business requirements to consider when planning a large enterprise deployment of Tenable Security Center. If your organization scans 100,000 or more IP addresses, consider the information in the [Tenable Security Center Large Enterprise Deployment Guide](#) when planning, configuring, and operationalizing your Tenable Security Center deployment.



---

## Installation and Upgrade

---

To perform a fresh installation of Tenable Security Center, see [Before You Install](#) and [Install Tenable Security Center](#).

To perform an upgrade of Tenable Security Center, see [Before You Upgrade](#) and [Upgrade Tenable Security Center](#).

To uninstall Tenable Security Center, see [Uninstall Tenable Security Center](#).



## Before You Install

**Note:** A basic understanding of Linux is assumed throughout the installation, upgrade, and removal processes.

### Understand Tenable Security Center Licenses

Confirm your licenses are valid for your Tenable Security Center deployment. Tenable Security Center does not support an unlicensed demo mode.

For more information, see [License Requirements](#).

### Disable Default Web Servers

Tenable Security Center provides its own Apache web server listening on port 443. If the installation target already has another web server or other service listening on port 443, you must disable that service on that port or configure Tenable Security Center to use a different port after installation.

Identify which services, if any, are listening on port 443 by running the following command:

```
# ss -pan | grep ':443 '
```

If there are any services listening on port 443, you must either disable or run them on a different port.

### Modify Security Settings

Tenable Security Center supports disabled, permissive, and enforcing mode Security-Enhanced Linux (SELinux) policy configurations. For more information, see [SELinux Requirements](#).

### Perform Log File Rotation

The installation does not include a log rotate utility; however, the native Linux logrotate tool is supported post-installation. In most Red Hat environments, logrotate is installed by default. The following logs are rotated if the logrotate utility is installed:

- All files in `/opt/sc/support/logs` matching `*log`
- `/opt/sc/admin/logs/sc-error.log`



---

During an install/upgrade, the installer drops a file named SecurityCenter into /etc/logrotate.d/ that contains log rotate rules for the files mentioned above.

Log files are rotated on a monthly basis. This file is owned by root/root.

## Allow Tenable Sites

To allow Tenable Security Center to communicate with Tenable servers for product updates and plugin updates, Tenable recommends adding Tenable sites to an allow list at the perimeter firewall. For more information, see the [knowledge base](#) article.



# Install Tenable Security Center

**Required User Role:** Root user

**Note:** A basic understanding of Linux is assumed throughout the installation, upgrade, and removal processes.

**Caution:** When performing `sudo` installs, use `sudo -i` to ensure the proper use of environmental variables.

**Caution:** During the installation process, Tenable Security Center produces a log file in a temporary location: `/tmp/sc.install.log`. Once the installation process finishes, the file is stored here: `/opt/sc/admin/logs/install.log`. Do not remove or modify these files; they are important for debugging in case of a failed installation.

For information about new features, resolved issues, third-party product updates, and supported upgrade paths, see the [release notes](#) for Tenable Security Center 6.0.x.

Before you begin:

- Complete system prerequisites, as described in [Before You Install](#).
- Download the installation RPM file from the [Tenable Security Center downloads](#) page. If necessary, depending on the operating system of the host, move the installation RPM file onto the host.
- Confirm the integrity of the installation RPM file by comparing the download checksum with the checksum on the [Tenable Security Center downloads](#) page, as described in the [knowledge base](#) article.
- If your organization requires Tenable Security Center to use `/dev/random` instead of `/dev/urandom` to generate random number data for secure communication functions, modify the random data source as described in [Use /dev/random for Random Number Data Generation](#).

To install Tenable Security Center:

1. On the host where you want to install Tenable Security Center, open the command line interface (CLI).
2. Run one of the following commands to install the RPM:



```
# yum install SecurityCenter-x.x.x-el6.x86_64.rpm
```

- or -

```
# dnf install SecurityCenter-x.x.x-el8.x86_64.rpm
```

Output similar to the following is generated:

```
# dnf install SecurityCenter-6.x.x-es6.x86_64.rpm
Preparing...                               ##### [100%]
 1:SecurityCenter                           ##### [100%]
Installing Nessus plugins ... complete
Applying database updates ... complete.
By default, SecurityCenter will listen for HTTPS requests on ALL available
interfaces. To complete your installation, please point your web browser to one of
the following URL(s):
https://x.x.x.x
Starting SecurityCenter services
[ OK ] SecurityCenter services: [ OK ]
#
```

The system installs the package into /opt/sc and attempts to start all required daemons and web server services.

**Tip:** In rare cases, a system restart is required after installation in order to start all services. For more information, see [Start, Stop, or Restart Tenable Security Center](#).



---

## Quick Setup

---

The Tenable Security Center Quick Setup Guide walks through the following configurations:

- [License](#)
- [Tenable Nessus Scanner](#)
- [Tenable Nessus Network Monitor](#)
- [Log Correlation Engine](#)
- [Repository](#)
- [Organization](#)
- [LDAP](#)
- [User](#)
- [Additional Settings](#)

After configuring, [Review](#) and confirm.

## License

Upload your Tenable Security Center license and apply additional product licenses.

### Tenable Security Center License

1. Click **Choose File** to upload the Tenable Security Center license file you received from Tenable.

The file should follow the format:

<CompanyName>\_SC<IP Count>-<#>-<#>.key

2. Click **Activate**.

The page confirms successful upload and activation of a valid license.

### Activation Codes

Consider adding additional license activation codes:



- Tenable Security Center license activation code —required before adding any Tenable Nessus scanners. The Tenable Security Center license activation code allows Tenable Security Center to download plugins and update Tenable Nessus scanner plugins.

In the **Tenable Nessus** section, type the Tenable Security Center activation code and click **Register**.

- Tenable Nessus Network Monitor license activation code —required before using and managing attached Tenable Nessus Network Monitor scanners.

In the **Tenable Nessus Network Monitor** section, type the Tenable Nessus Network Monitor activation code and click **Register**.

- Log Correlation Engine Activation Code —required before downloading Log Correlation Engine Event vulnerability plugins to Tenable Security Center. The Log Correlation Engine Activation Code allows Tenable Security Center to download event plugins, but it does not manage plugin updates for Log Correlation Engine servers.

In the **Log Correlation Engine** section, type the Tenable Log Correlation Engine activation code and click **Register**.

Click **Next** to continue.

A plus (+) sign indicates that no license is applied for the product. A box with an X indicates an invalid activation code. Click on the plus (+) or X to add or reset a license activation code.

A box with a checkmark indicates a valid license is applied and that Tenable Security Center initiated a plugin download in the background.

The download may take several minutes and must complete before initiating any Tenable Nessus scans. After the download completes, the **Last Updated** date and time update on the Plugins page.

## Tenable Nessus Scanner

Configure your first Tenable Nessus scanner. For information about the options you can configure, see [Tenable Nessus Scanners](#). There are some limitations on the scanner options you can configure during Quick Start:





- **Agent Capable:** If you use a Tenable Vulnerability Management or Tenable Nessus Manager scanner for Tenable Nessus Agent scan imports, do not configure that scanner during the Quick Start.
- **Zones:** If you want to grant scan zones access to this scanner, you must configure the **Zones** option after the Quick Start.

## Tenable Nessus Network Monitor

If you added an Tenable Nessus Network Monitor license activation code, you can configure your first Tenable Nessus Network Monitor scanner. For information about the options you can configure, see [Tenable Nessus Network Monitor Instances](#). There are some limitations on the scanner options you can configure during Quick Start:

- **Repositories:** If you want to select repositories to store the scanner's data, you must configure the **Repositories** option after the Quick Start.

## Log Correlation Engine

If you added an Log Correlation Engine Activation Code, you can configure your first Tenable Log Correlation Engine scanner. For information about the options you can configure, see [Tenable Log Correlation Engines](#). There are some limitations on the scanner options you can configure during Quick Start:

- **Organizations:** If you want to select organizations that can access the scanner's data, you must configure the **Organizations** option after the Quick Start.
- **Repositories:** If you want to select repositories to store the scanner's data, you must configure the **Repositories** option after the Quick Start.

## Repository

You can configure your first local IPv4 or IPv6 repository.

**Caution:** When creating repositories, note that IPv4 and IPv6 addresses must be stored separately. Additional repositories may be created once the initial configuration is complete.

A repository is essentially a database of vulnerability data defined by one or more ranges of IP addresses. When the repository is created, a selection for IPv4 or IPv6 addresses must be made.



Only IP addresses of the designated type may be imported to the designated repository. The organization created in steps that follow can take advantage of one or more repositories. During installation, a single local repository is created with the ability to modify its configuration and add others post-install.

**Caution:** When creating Tenable Security Center repositories, Tenable Log Correlation Engine event source IP address ranges must be included along with the vulnerability IP address ranges or the event data is not accessible from the Tenable Security Center UI.

Local repositories are based on the IP addresses specified in the **IP Ranges** option on this page during the initial setup. *Remote* repositories use addressing information pulled over the network from a remote Tenable Security Center. Remote repositories are useful in multi-Tenable Security Center configurations where security installations are separate but reports are shared. *Offline* repositories also contain addressing information from another Tenable Security Center. However, the information is imported to the new installation via a configuration file and not via a direct network connection. For information about how this works in air-gapped environments, see [Considerations for Air-Gapped Environments](#).

For information about the options you can configure, see [Local Repositories](#). There are some limitations on the repositories and repository options you can configure during Quick Start:

- You cannot configure a local mobile repository during Quick Start.
- You cannot configure a local agent repository during Quick Start.
- You cannot configure an external repository during Quick Start.
- **Organizations:** If you want to select organizations that can access the repository's data, you must configure the **Organizations** option after the Quick Start.
- **Log Correlation Engine Correlation:** If you want to select Log Correlation Engine servers where you want Tenable Security Center to retrieve data, you must configure the **Log Correlation Engine Correlation** option after the Quick Start.

## Organization

An organization is a set of distinct users and groups and the resources they have available to them. For information about the options you can configure, see [Organizations](#).



You can configure one organization during initial setup. If you want to use multiple organizations, you must configure other organizations after the Quick Start.

## LDAP

Configuring LDAP allows you to use external LDAP servers for the Tenable Security Center user account authentication or as LDAP query assets. Type all required LDAP server settings and click **Next**. Click **Skip** if you do not want to configure LDAP during initial configuration.

You can configure one LDAP server connection during initial setup. If you want to use multiple LDAP servers, or if you want to configure additional options, you must continue configuring LDAP after the Quick Start.

For information about the options you can configure, see [LDAP Authentication](#).

## User

You must create one administrator and one security manager during initial setup. For more information, see [User Roles](#).

- Security manager —a user to manage the organization you just created. After you finish initial setup, the security manager can create other user accounts within the organization.
- Administrator —a user to manage Tenable Security Center. After you finish initial setup, the administrator can create other organizations and user accounts.

If you already configured an LDAP server, you have the option to create an LDAP user account. For more information about user account options, see [User Accounts](#).

After creating the security manager user and setting the administrator password, click **Next** to finish initial setup. The **Admin Dashboard** page appears, where you can review login configuration data.

## Additional Settings

The **Enable Usage Statistics** option specifies whether Tenable collects anonymous telemetry data about your Tenable Security Center deployment.

When enabled, Tenable collects usage statistics that cannot be attributed to a specific user or customer. Tenable does not collect personal data or personally identifying information (PII).



---

Usage statistics include, but are not limited to, data about your visited pages, your used reports and dashboards, your Tenable Security Center license, and your configured features. Tenable uses the data to improve your user experience in future Tenable Security Center releases. You can disable this option at any time to stop sharing usage statistics with Tenable.

For more information about enabling or disabling this option after initial setup, see [Configuration Settings](#).

## Review

The review page displays your currently selected configurations. If you want to make further changes, click the links in the left navigation bar.

When you are finished, click **Confirm**.



# Install a Tenable Security Center Patch

**Required User Role:** Root user

**Note:** This topic assumes a basic understanding of Linux.

For information about new patches, see the [release notes](#) for Tenable Security Center.

Some patches are available through the Tenable Security Center feed. For more information, see [Tenable Security Center Software Updates](#).

To apply a Tenable Security Center patch manually:

1. Download the patch TGZ file from the [Tenable downloads](#) page. If necessary, depending on the operating system of the host, move the upgrade TGZ file onto the host.
2. Confirm the integrity of the patch TGZ file by comparing the download checksum with the checksum on the [Tenable downloads](#) page.
3. If your organization requires Tenable Security Center to use `/dev/random` instead of `/dev/urandom` to generate random number data for secure communication functions, modify the random data source as described in [Use /dev/random for Random Number Data Generation](#).
4. Access the command line as a user with root-level permissions.
5. Run the following command to untar the patch file, where `[patch file name]` is the name of the TGZ patch file you downloaded:

```
tar xzf [patch file name]
```

6. Run the following command to change the directory to the extracted directory, where `[directory]` is the extracted directory:

```
cd [directory]
```

7. Run the following command to begin the installation:

```
sh ./install.sh
```

The installation begins and Tenable Security Center stops. After the installation finishes, Tenable Security Center automatically restarts.



8. (Optional) Confirm the patch successfully applied to Tenable Security Center, as described in the [knowledge base](#) article.

To apply a patch through the Tenable Security Center feed:

1. Log in to Tenable Security Center as an Administrator.
2. In the left navigation, click **System > Configuration**.

The **Configuration** page appears.

3. Click the **Plugins/Feed** tile.

The **Plugins/Feed Configuration** page appears.

4. On the **Plugins/Feed Configuration** page, in the **Tenable Security Center Software Updates** section, enable the **Enable Updates Through the Tenable Security Center Feed** option.

During the next scheduled feed update, Tenable Security Center applies the patch. In the **Tenable Security Center Software Updates** table, a timestamp appears in the row for the patch in the **Last Updated** column.



## Before You Upgrade

**Note:** A basic understanding of Linux is assumed throughout the installation, upgrade, and removal processes.

- [Tenable Security Center Upgrade Path](#)
- [Java Version Requirements](#)
- [Halt or Complete Running Jobs](#)
- [Perform a Tenable Security Center Backup](#)
- [Rename Your Mount Point](#)

### Tenable Security Center Upgrade Path

For more information about the upgrade paths to Tenable Security Center version 6.0.x, see the [Tenable Security Center Release Notes](#).

### Java Version Requirements

If you have not installed the Oracle Java JRE or OpenJDK, Tenable Security Center displays the following warning:

```
[WARNING] SecurityCenter has determined that Oracle Java JRE and OpenJDK is not installed. One of two must be installed for SecurityCenter reporting to function properly.
```

You must install the latest version of Oracle Java JRE or OpenJDK to take full advantage of Tenable Security Center reporting.

### Halt or Complete Running Jobs

Tenable recommends stopping all running Tenable Security Center processes before beginning an upgrade. If processes are running (for example, Tenable Nessus scans), Tenable Security Center displays the following message along with the related process names and their PIDs:



SecurityCenter has determined that the following jobs are still running. Please wait a few minutes before performing the upgrade again. This will allow the running jobs to complete their tasks.

Stop the processes manually or retry the upgrade after the processes complete.

## Perform a Tenable Security Center Backup

Perform a backup of Tenable Security Center before beginning your upgrade. For more information, see [Backup and Restore](#).

## Rename Your Mount Point

If the existing `/opt/sc` directory is or contains a mount point to another location, rename the mount point. During the RPM upgrade process, a message appears with information about the discovered mount point. Contact your system administrator for assistance.





# Upgrade Tenable Security Center

**Required User Role:** Root user

**Note:** This topic assumes a basic understanding of Linux.

**Caution:** During the upgrade process, Tenable Security Center produces a log file in a temporary location: `/tmp/sc.install.log`. Once the installation process finishes, the file is stored here: `/opt/sc/admin/logs/install.log`. Do not remove or modify these files; they are important for debugging in case of a failed upgrade.

For information about new features, resolved issues, third-party product updates, and supported upgrade paths, see the [release notes](#) for Tenable Security Center 6.0.x.

**Note:** For Tenable Security Center 5.21 and later, follow this procedure to upgrade from an early access Tenable Security Center version to the latest version.

Before you begin:

1. Complete system prerequisites, as described in [Before You Upgrade](#).

**Note:** Tenable recommends creating a backup of your Tenable Security Center data before upgrading, as described in [Perform a Backup](#).

2. Download the upgrade RPM file from the [Tenable downloads](#) page. If necessary, depending on the operating system of the host, move the upgrade RPM file onto the host.
3. Confirm the integrity of the upgrade RPM file by comparing the download checksum with the checksum on the [Tenable downloads](#) page.
4. If your organization requires Tenable Security Center to use `/dev/random` instead of `/dev/urandom` to generate random number data for secure communication functions, modify the random data source as described in [Use /dev/random for Random Number Data Generation](#).

To upgrade to Tenable Security Center 6.0.x:

1. Log in to Tenable Security Center via the user interface.
2. Pause all running scans, as described in [Start or Pause a Scan](#).



### 3. Prepare the upgrade command you intend to run:

- Use yum or dnf with the upgrade switch from the command-line of the Tenable Security Center server.
- Use “sudo -i” when performing sudo upgrades of Tenable Security Center to ensure the proper use of environmental variables.

For example:

```
# yum upgrade SecurityCenter-x.x.x-el6.x86_64.rpm
```

- or -

```
# dnf upgrade SecurityCenter-x.x.x-el8.x86_64.rpm
```

The upgrade begins. Tenable Security Center is not available until the upgrade finishes.

```
# dnf upgrade SecurityCenter-x.x.x-el6.x86_64.rpm
Preparing... ##### [100%]
Shutting down SecurityCenter services: [ OK ]
Backing up previous application files ... complete.
 1:SecurityCenter ##### [100%]

Applying database updates ... complete.
Beginning data migration.
Starting plugins database migration...complete.
(1 of 4) Converting Repository 1 ... complete.
(2 of 4) Converting Repository 2 ... complete.
(3 of 4) Converting Repository 3 ... complete.
(4 of 4) Converting Repository 4 ... complete.
Migration complete.
Starting SecurityCenter services: [ OK ]
~]#
```

What to do next:

- (Optional) If you used custom Apache SSL certificates before upgrading Tenable Security Center, restore the custom SSL certificates, as described in [Restore Custom SSL Certificates](#).



## Restore Custom SSL Certificates

**Required User Role:** Root user

If you used custom Apache SSL certificates before upgrading Tenable Security Center, you must restore the custom Apache SSL certificates after you upgrade Tenable Security Center.

Tenable Security Center creates a backup of the certificates during the upgrade process. Tenable Security Center copies the existing custom SSL certificates to the Apache configuration backup directory that the upgrade process creates in the `/tmp/[version].apache.conf-#####` directory. The exact name of the directory varies, but the system displays the name during the upgrade process and reports it in the `/opt/sc/admin/log/install.log` file.

Before you begin:

- Upgrade to a new version of Tenable Security Center, as described in [Upgrade Tenable Security Center](#).

To restore custom SSL certificates after upgrading Tenable Security Center:

1. Log in to Tenable Security Center via the command line interface (CLI).
2. In the CLI in Tenable Security Center, run the following command:

```
# cp /tmp/[version].apache.conf-#####/SecurityCenter.cert  
/opt/sc/support/conf/SecurityCenter.crt
```

3. Select yes to overwrite the existing file.
4. In the CLI in Tenable Security Center, run the following command:

```
# cp /tmp/[version].apache.conf-#####/SecurityCenter.pem  
/opt/sc/support/conf/SecurityCenter.key
```

5. Select yes to overwrite the existing file.

**Caution:** Ensure that the newly copied files have permissions of 0640 and ownership of `tns:tns`.



6. Modify the servername parameter in `/opt/sc/support/conf/servername` to match the Common Name (CN) of the SSL certificate.

**Tip:** To obtain the CN, run the following command and note the CN= portion of the result.

```
# /opt/sc/support/bin/openssl verify /opt/sc/support/conf/SecurityCenter.crt
```

7. In the CLI in Tenable Security Center, run one of the following commands to restart the Apache server:

```
# /opt/sc/support/bin/apachectl restart
```

-or-

```
# service SecurityCenter restart
```

The Apache server restarts.



# Uninstall Tenable Security Center

**Required User Role:** Root user

To uninstall Tenable Security Center:

1. On the host where you want to uninstall Tenable Security Center, open the command line interface (CLI).
2. In the CLI, run the following command to stop Tenable Security Center:

```
service SecurityCenter stop
```

3. Run the following command to remove Tenable Security Center:

```
dnf remove SecurityCenter
```

4. Run the following command to remove user-created and user-modified files:

```
rm -rf /opt/sc
```

Tenable Security Center is removed.



---

## User Access

---

The **Users** page provides the ability to add, edit, delete, or view the details of Tenable Security Center user accounts. When you view the **Users** page, you see a list of users and actions, limited by your account privileges. Your *user role*, *organization* membership, and/or *group* membership determine your account privileges. For more information, see [User Roles](#) and [Organizations and Groups](#).

There are two categories of user accounts:

- *Administrator* users have the system-provided administrator role and do not belong to organizations.
- *Organizational* users have the system-provided security manager, auditor, credential manager, executive, security analyst, security manager, or vulnerability analyst role, or a custom role, and belong to an organization.

Tenable Security Center supports three types of user account authentication: TNS, LDAP, and SAML. For more information, see [User Accounts](#).

To log in to the Tenable Security Center web interface with a user account, see [Log In to the Web Interface](#) or [Log in to the Web Interface via SSL Client Certificate](#).



# Log In to the Web Interface

**Required User Role:** Any

To log in to the Tenable Security Center configuration interface:

1. Open a supported web browser on a system that has access to the system's network address space.

**Note:** You must access the Tenable Security Center web interface using a secure web connection (HTTPS) with SSL/TLS 1.2 enabled. Tenable Security Center recommends configuring the strongest encryption supported by your browser.

For more information, see [Encryption Strength](#).

2. Clear your web browser's cache.
3. Navigate to the URL for your Tenable Security Center: `https://<SERVER ADDRESS OR NAME>/`.

Where `<SERVER ADDRESS OR NAME>` is the IPv4 or IPv6 address or hostname for your Tenable Security Center.

The Tenable Security Center web interface appears.

4. Log in using the supported method for your account configuration.

**Note:** If you are the first administrator user logging in to Tenable Security Center, see [Initial Login Considerations](#).

- To log in via a username and password, type your Tenable Security Center credentials and click **Log In**.
- To log in via SAML authentication, click **Sign In Using Identity Provider**. When presented with your identity provider login page, type your identity provider credentials.

For more information about SAML authentication, see [Configure SAML Authentication Manually via the User Interface](#).

- To log in via certificate, see [Log in to the Web Interface via SSL Client Certificate](#).



Tenable Security Center logs you in and displays the dashboard with different elements depending on your user role.

## Initial Login Considerations

When you log in to Tenable Security Center for the first time, Tenable Security Center displays the Quick Setup Guide welcome page to begin a multi-step setup process for initial configuration. For more information about quick setup, see [Quick Setup](#).

If you prefer to configure the system manually, click **Exit Quick Setup Guide**. For more information about getting started with Tenable Security Center, see [Get Started With Tenable Security Center](#).





## Log in to the Web Interface via SSL Client Certificate

**Required User Role:** Any

Before you begin:


- Confirm your Tenable Security Center administrator fully configured Tenable Security Center for certificate authentication, as described in [Certificate Authentication](#).

To perform a certificate-based Tenable Security Center login:

**Note:** The following information is provided with the understanding that your browser is configured for SSL certificate authentication. Please refer to your browser's help files or other documentation to configure this feature.

1. Open a browser window and navigate to Tenable Security Center.

The browser presents a list of available certificate identities.




For information about Tenable Security Center-browser communications encryption, see [Encryption Strength](#).

2. Select a certificate.



3. Click **OK**.

An authentication prompt appears (if required to access your certificate).



4. (Optional) If prompted, type a PIN or password.

5. Click **OK**.

The Tenable Security Center login page appears.

6. Log in using the username to be associated with the selected certificate.

**Caution:** Only one Tenable Security Center user may be associated with a single certificate. If one user holds multiple user names and roles, a unique certificate must be provided for each login name.

The **Certificate Authentication** window appears.

7. When prompted, specify whether the current certificate is to be used to authenticate the current user.
  - Click **Yes** to always use the certificate for authentication.
  - Click **No** to ignore the certificate and log in via TNS authentication.

Tenable Security Center logs you in.

## Subsequent Logins

After you log out of Tenable Security Center, the login page appears. If you want to log in again with the same certificate, refresh your browser window. If you want to use a different certificate, you must start a new browser session.



After you perform your second certificate login, edit your account from the **Profile** page to view your certificate details. If your certificate changes or you need to revoke it, click the **Clear Certification Details** button to disassociate the certificate from your account.



## User Roles

Roles determine what a user can or cannot access from their account. Tenable Security Center comes with eight system-provided roles, but you can also create custom roles to satisfy complex security policy needs. You can customize the permissions on some, but not all, system-provided user roles.

If you configure *linked user accounts*, an Administrator can switch to one or more Security Manager user accounts without logging out and logging back in to Tenable Security Center. For more information, see [Linked User Accounts](#).

For more information about user roles in Tenable Security Center, see [Create a User Role](#), [Edit a User Role](#), [View User Role Details](#), and [Delete a User Role](#).

## Roles

User Role	Customizable Permissions?	Description
Administrator	No	<p>An account that manages Tenable Security Center as a whole. The primary task of the Administrator is to install and configure each organization. In addition, the Administrator adds components to Tenable Security Center such as Tenable Nessus Network Monitor, Tenable Log Correlation Engine, and Tenable Nessus to extend its capabilities. The Administrator is automatically assigned the “Manage Application” role.</p> <p>Because administrators do not belong to an organization, they do not have access to the data collected by Tenable Security Center.</p>
Organizational User Roles		
Security Manager	No	<p>An account that manages an individual organization. This is the role assigned to the initial user that is assigned when a new organization is created. They can launch scans, configure users (except for admin-</p>



		<p>istrator user roles), vulnerability policies, and other objects belonging to their organization.</p> <p>A Security Manager is the account within an organization that has a broad range of security roles within the defined organization. This is the initial user that is created when a new organization is created, and the user can launch scans, configure users (except for the Administrator user), vulnerability policies, and other objects that belong to their organization. This initial Security Manager account cannot be deleted without deleting the entire organization.</p> <p>Security Managers have complete access to all data collected by their organization.</p>
Auditor	Yes	<p>An account that can access summary information to perform third-party audits. An Auditor can view dashboards, reports, and logs, but cannot perform scans or create tickets.</p>
Credential Manager	Yes	<p>An account that can be used specifically for handling credentials. A Credential Manager can create and share credentials without revealing the contents of the credential. This can be used by someone outside the security team to keep scanning credentials up to date.</p>
Executive	Yes	<p>An account intended for users who are interested in a high-level overview of their security posture and risk profile. Executives would most likely browse dashboards and review reports, but would not be concerned with monitoring running scans or managing users. Executives would also be able to assign tasks to other users using the ticketing interface.</p>
Security Analyst	Yes	<p>An account that has permissions to perform all</p>



		actions at the Organizational level except managing groups and users. A Security Analyst is most likely an advanced user who can be trusted with some system-related tasks such as setting freeze windows or updating plugins.
Vulnerability Analyst	Yes	An account that can perform basic tasks within the application. A Vulnerability Analyst is allowed to view security data, perform scans, share objects, view logs, and work with tickets.
No Role	No	An account with virtually no permissions. No Role is assigned to a user if their designated role is deleted.
Custom Role	Yes	A custom role that you create by enabling or disabling individual permissions.

## Role Options

Permissions Option	Description
General	
Name	Custom role name
Description	Custom role description
Scan Permissions	
Create Scans	Allows the user to create policy-based scans. Disabling <b>Create Policies</b> while enabling this permission allows you to lock user into specific set of policies for scanning.
Create Plugin Scans	Allows the user to create single plugin remediation scans.
Create Agent Synchronization Jobs	Allows the user to add agent synchronization jobs that fetch agent scan results from Tenable Vulnerability Management or Tenable Nessus Manager.



Permissions Option	Description
Create Agent Scans	Allows the user to add agent scans that create and launch parallel scans in Tenable Nessus Manager, then import the scan results to Tenable Security Center.
Create Audit Files	Allows the user to upload audit files, which can be used for configuration audit scans.
Create Policies	Allows the user to set scan parameters and select plugins for scanning.
Upload Nessus Scan Results	Allows the user to import results from an external Nessus scanner. Result upload will be limited to user's repositories and restricted by user's IP address ranges.
Manage Freeze Windows	Allows the user to add, edit, and delete organization-wide freeze windows. Freeze windows prevent scans from launching and stop any scans in progress.
<b>Asset Permissions</b>	
Create LDAP Query Assets	Allows the user to create LDAP Query Assets, which update a list of hosts based on a user-defined LDAP query.
<b>Analysis Permissions</b>	
Accept Risks	Allows the user to accept risks for vulnerabilities, which removes them from the default view for analysis, dashboards, and reports.
Recast Risks	Allows the user to change the severity for vulnerabilities.
<b>Organizational Permissions</b>	
Share Objects Between Groups	Allows the user to share assets, audit files, credentials, queries, and policies with any group. Users in groups to which these objects have been shared can use the objects for filtering and scan creation.
View Organization Logs	Allows the user to view logs for entire organization.
<b>User Permissions</b>	



Permissions Option	Description
Manage Roles	Allows the user to create new roles and edit and delete organizational roles. Any roles added must have permissions equal to or lesser than the user's role.
Manage Groups	Allows the user to add, edit, and delete groups. Users with this permission are allowed to create groups with access to any vulnerability and event data available to the organization.
Manage Group Relationships	Allows the user to set other user's relationship with any other groups. Group relationships allow for a user to view and manage objects and users in other groups.
<b>Report Permissions</b>	
Manage Images	Allows the user to upload images, so anyone in the organization can use the images in reports.
Manage Attribute Sets	Allows the user to add, edit, and delete attribute sets.
<b>System Permissions</b>	
Update Feeds	Allows the user to request a plugin update or a Tenable Security Center feed update.
<b>Workflow Permissions</b>	
Create Alerts	Allows the user to create alerts which are used to trigger actions (e.g., launch scans, run reports, send emails) when specified vulnerability or event conditions occur.
Create Tickets	Allows the user to create tickets, which are typically used to delegate work to other users.
<b>Attack Surface Discovery Permissions</b>	
Manage Attack Surface Discovery Domains	Allows the user to manage Attack Surface Discovery Domains.





Permissions Option	Description
View Domain Inventory Assets	Allows the user to view domain inventory assets.
Host Assets Permissions	
View Host Assets	Allows the user to view host assets.



## Create a User Role

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information about user role options, see [User Roles](#).

To create a custom user role:

1. Log in to Tenable Security Center via the user interface.
2. Click **Users > Roles**.  
The **Roles** page appears.
3. Click **Add**.  
The **Add Role** page appears.
4. In the **Name** box, type a name for the role.
5. (Optional) In the **Description** box, type a description for the role.
6. Set the following permissions, as described in [User Roles](#):
  - **Scanning Permissions**
  - **Asset Permissions**
  - **Analysis Permissions**
  - **Domain Permissions**
  - **Organization Permissions**
  - **User Permissions**
  - **Reporting Permissions**
  - **System Permissions**
  - **Workflow Permissions**
7. Click **Submit**.

Tenable Security Center saves your configuration.



## Edit a User Role

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information about user role options, see [User Roles](#).

To edit the permissions of a custom or system-provided role:

1. Log in to Tenable Security Center via the user interface.
2. Click **Users > Roles**.

The **Roles** page appears.

3. Right-click the row for the user role you want to edit.

The actions menu appears.

-or-

Select the check box for the user role you want to edit.

The available actions appear at the top of the table.

4. Click **More > Edit**.

The **Edit Role** page appears.

5. (Optional) Modify the **Name**
6. (Optional) Modify the **Description**.
7. (Optional) Modify the following permissions, as described in [User Roles](#):
  - **Scanning Permissions**
  - **Asset Permissions**
  - **Analysis Permissions**
  - **Domain Permissions**
  - **Organization Permissions**
  - **User Permissions**



- **Reporting Permissions**
- **System Permissions**
- **Workflow Permissions**

8. Click **Submit**.

Tenable Security Center saves your configuration.



## View User Role Details

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

You can view details for any user role. For more information, see [User Roles](#).

To view role details:

1. Log in to Tenable Security Center via the user interface.
2. Click **Users > Roles**.

The **Roles** page appears.

3. Right-click the row for the user role you want to view.

The actions menu appears.

-or-

Select the check box for the user role you want to view.

The available actions appear at the top of the table.

4. Click **View**.

The **View Role** page appears.

Section	Action
<b>General</b>	<p>View general information for the user role.</p> <ul style="list-style-type: none"><li>• <b>Name</b> —The user role name.</li><li>• <b>Description</b> —The user role description.</li><li>• <b>User Count</b> —The number of users with this role.</li><li>• <b>Created</b> —The date the user role was created.</li><li>• <b>Last Modified</b> —The date the user role was last modified.</li><li>• <b>ID</b> —The user role ID.</li></ul>



Section	Action
<b>Scanning Per- missions</b>	View a summary of permissions for the role. For more information, see <a href="#">User Roles</a> .
<b>Asset Permissions</b>	
<b>Analysis Per- missions</b>	
<b>Organization Per- missions</b>	
<b>User Permissions</b>	
<b>Reporting Per- missions</b>	
<b>System Per- missions</b>	
<b>Workflow Per- missions</b>	



## Delete a User Role

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information, see [User Roles](#).

To delete a custom or system-provided user role:

**Note:** Deleting a role will cause all users with that role to lose all assigned permissions.

1. Log in to Tenable Security Center via the user interface.
2. Click **Users > Roles**.

The **Roles** page appears.

3. Select the role you want to delete:

To delete a single user role:

- a. In the table, right-click the row for the role you want to delete.

The actions menu appears.

- b. Click **Delete**.

To delete multiple user roles:

- a. In the table, select the check box for each role you want to delete.

The available actions appear at the top of the table.

- b. At the top of the table, click **More > Delete**.

A confirmation window appears.

4. Click **Delete**.

Tenable Security Center deletes the role.



---

## Organizations and Groups

---

An *organization* is a set of distinct users and groups and the resources they have available to them. These users are assigned repositories and zones within one or more specified IP address networks. *Users* refers to any non-administrator user account on Tenable Security Center. *Groups* refers to collections of users with the same permissions within an organization.

For more information, see [Organizations](#) and [Groups](#).





## Organizations

An *organization* is a set of distinct users and groups and the resources (for example, scanners, repositories, and LDAP servers) they have available to them.

The organization is managed primarily by the administrator users and security manager users. The administrator user creates the organization and creates, assigns, and maintains the security manager user account. The security manager user (or any organizational user with appropriate permissions) creates other users within the organization. Groups allow you to manage users and share permissions to resources and objects among the group. For more information, see [User Access](#).

Multiple organizations can share the same repositories, and the vulnerability data associated with the overlapping ranges is shared between each organization. Conversely, organizations can be configured with their own discrete repositories to facilitate situations where data must be kept confidential between different organizational units.

Creation of an organization is a multi-step process. After you create an organization, Tenable Security Center prompts you to create the initial security manager user. For more information, see [Add an Organization](#) and [Delete an Organization](#).

To view details for any organization, see [View Organization Details](#).

To view the users in an organization, filter by the organization on the [Users](#) page. For more information about filters, see [Apply a Filter](#).

## Organization Options

Option	Description
<b>General</b>	
<b>Name</b>	(Required) The organization name.
<b>Description</b>	A description for the organization.
<b>Contact Information</b>	The relevant contact information for the organization including address, city, state, country, and phone number.
<b>Password Expiration</b>	
<b>Enable Password Expiration</b>	When enabled, passwords for users in the organization will



Option	Description
	expire after the number of days specified in the <b>Expiration Days</b> box.
<b>Expiration Days</b>	<p>The number of days before the user's password expires. You can enter a number between 1 and 365.</p> <p>The user will receive daily password expiration notifications at login, starting 14 days before the password expires. After the password expires, the user must change their password at the next login. For more information about Tenable Security Center notifications, see <a href="#">Notifications</a>.</p>
<b>Scanning</b>	
<b>Distribution Method</b>	<p>The scan distribution mode you want to use for this organization:</p> <ul style="list-style-type: none"><li>• <b>Automatic Distribution Only:</b> Tenable Security Center chooses one or more scan zones to run the scan. Organizational users cannot choose a scan zone when configuring a scan.</li></ul> <p>Tenable Security Center distributes targets for scans based on your configured scan zone ranges. This facilitates optimal scanning and is useful if an organization has devices placed behind a firewall or NAT device or has conflicting <a href="#">RFC 1918</a> non-internet-routable address spaces.</p> <ul style="list-style-type: none"><li>• <b>Locked Zone:</b> Tenable Security Center uses the one <b>Available Zone</b> you specify to run the scan. Organizational users cannot modify the scan zone when configuring a scan.</li><li>• <b>Selectable Zones:</b> Tenable Security Center allows organizational users to select a scan zone when configuring a scan.</li></ul>



Option	Description
	<p>This mode allows organizational users to use scanners to run internal and external vulnerability scans and analyze the vulnerability stance from a new perspective. For example, an organizational user can choose an external scanner to see the attack surface from an external attacker's perspective.</p> <p>For more information about scan zones, see <a href="#">Scan Zones</a>.</p>
<b>Available Zones</b>	One or more scan zones that you want organizational users to have access to when configuring scans.
<b>Allow for Automatic Distribution</b>	<p>Enable or disable this option to specify whether you want Tenable Security Center to select one or more scan zones automatically if an organizational user does not specify a scan zone when configuring a scan.</p> <ul style="list-style-type: none"><li>• When enabled, Tenable Security Center chooses one or more scan zones as specified by your <b>Restrict to Selected Zones</b> setting.</li><li>• When disabled, Tenable Security Center requires the organizational user to specify a scan zone when configuring a scan.</li></ul>
<b>Restrict to Selected Zones</b>	<p>If <b>Allow for Automatic Distribution</b> is enabled, enable or disable this option to specify the zones you want Tenable Security Center to choose from when automatically distributing zones.</p> <ul style="list-style-type: none"><li>• When enabled, Tenable Security Center chooses from the <b>Available Zones</b> shared with the organization.</li><li>• When disabled, Tenable Security Center chooses from all zones on Tenable Security Center.</li></ul>
<b>Restricted Scan Ranges</b>	The IP address ranges you do not want users in this organization to scan.



Option	Description
<b>Analysis</b>	
<b>Accessible LCEs</b>	The Log Correlation Engines that you want this organization to have access to. You can search for the Log Correlation Engines by name or scroll through the list.
<b>Accessible Repositories</b>	The repositories that you want this organization to have access to. You can search for the repositories by name or scroll through the list.
<b>Accessible Agent Capable Scanners</b>	The Tenable Nessus scanners (with Tenable Nessus Agents enabled) that you want this organization to have access to. Select one or more of the available scanners to allow the organization to import Tenable Nessus Agent results from the selected scanner.
<b>Accessible LDAP Servers</b>	The LDAP servers that you want this organization to have access to. An organization must have access to an LDAP server to perform LDAP authentication on user accounts within that organization, and to configure LDAP query assets. <div data-bbox="602 1150 1479 1268" style="border: 1px solid blue; padding: 5px;"><b>Note:</b> If you revoke access to an LDAP server, users in the organization cannot authenticate and LDAP query assets cannot run.</div>
<b>Custom Analysis Links</b>	
A list of custom analysis links provided to users within the host vulnerability details when analyzing data outside of Tenable Security Center is desired. Click <b>Add Custom Link</b> to create a new option to type the link name and URL to look up additional data external to Tenable Security Center.  For example: <i>http://example.com/index.htm?ip=%ip%</i>  The <i>%ip%</i> reference is a variable that inserts the IP address of the current host into the specified URI.	
<b>Vulnerability Weights</b>	



Option	Description
<b>Low</b>	The vulnerability weighting to apply to <b>Low</b> criticality vulnerabilities for scoring purposes. (Default: 1)
<b>Medium</b>	The vulnerability weighting to apply to <b>Medium</b> criticality vulnerabilities for scoring purposes. (Default: 3)
<b>High</b>	The vulnerability weighting to apply to <b>High</b> criticality vulnerabilities for scoring purposes. (Default: 10)
<b>Critical</b>	The vulnerability weighting to apply to <b>Critical</b> criticality vulnerabilities for scoring purposes. (Default: 40)
<b>Vulnerability Scoring System</b>	
<b>Scoring System</b>	<p>The scoring system Tenable Security Center uses to assess the severity of vulnerabilities: <b>CVSS v2</b> or <b>CVSS v3</b>.</p> <div data-bbox="602 926 1479 1121" style="border: 1px solid #0070C0; padding: 5px;"><p><b>Note:</b> Changing the <b>Scoring System</b> while Tenable Security Center is running certain operations, such as preparing reports or dashboard data, results in data using mixed CVSS v2 and CVSS v3 scores.</p></div> <div data-bbox="602 1142 1479 1377" style="border: 1px solid #0070C0; padding: 5px;"><p><b>Note:</b> Changing the <b>Scoring System</b> does not impact historical dashboard trend data. For example, if you change the <b>Scoring System</b> from <b>CVSS v2</b> to <b>CVSS v3</b>, dashboard trend data before the change displays CVSS v2 scores while dashboard trend data after the change displays CVSS v3 scores.</p></div>



## Add an Organization

**Required User Role:** Administrator

For more information about organization options, see [Organizations](#).

To add an organization:

1. Log in to Tenable Security Center via the user interface.

2. Click **Organizations**.

The **Organizations** page appears.

3. Click **Add**.

The **Add Organization** page appears.

4. Configure the following settings:

- **General**
- **Password Expiration**
- **Scanning**
- **Analysis**
- **Custom Analysis Links**
- **Vulnerability Weights**
- **Vulnerability Scoring System**

5. Click **Submit**.

Tenable Security Center saves your configuration.



## View Organization Details

**Required User Role:** Administrator

You can view details for any organization. For more information, see [Organizations](#).

To view organization details:

1. Log in to Tenable Security Center via the user interface.

2. Click **Organizations**.

The **Organizations** page appears.

3. Right-click the row for the organization you want to view.

The actions menu appears.

-or-

Select the check box for the organization you want to view.

The available actions appear at the top of the table.

4. Click **View**.

The **View Organization** page appears.

Section	Action
<b>General</b>	<p>View general information for the organization.</p> <ul style="list-style-type: none"><li>• <b>Name</b> —The organization name.</li><li>• <b>Description</b> —The organization description.</li><li>• <b>Address / City / State / Country / Phone</b> —The contact information for the organization.</li><li>• <b>Created</b> —The date the organization was created.</li><li>• <b>Last Modified</b> —The date the organization was last modified.</li><li>• <b>ID</b> —The organization ID.</li></ul>



Section	Action
<b>Password Expiration</b>	View a summary of your password expiration settings for the organization. For more information about a setting, see <a href="#">Organizations</a> .
<b>Scanning</b>	View a summary of your scanning settings for the organization. For more information about a setting, see <a href="#">Organizations</a> .
<b>Analysis</b>	View a summary of your analysis settings for the organization. For more information about a setting, see <a href="#">Organizations</a> .
<b>Custom Analysis Links</b>	View a summary of your custom analysis link settings for the organization. For more information about a setting, see <a href="#">Organizations</a> .
<b>Vulnerability Weights</b>	View a summary of your vulnerability weights settings for the organization. For more information about a setting, see <a href="#">Organizations</a> .
<b>Vulnerability Scoring System</b>	View the vulnerability scoring system selected for the organization. For more information, see <a href="#">Organizations</a> .





# Delete an Organization

**Required User Role:** Administrator

For more information, see [Organizations](#).

To delete an organization:

**Note:** Deleting an organization deletes all of the users in that organization.

1. Log in to Tenable Security Center via the user interface.
2. Click **Organizations**.

The **Organizations** page appears.

3. Select the organization you want to delete:

To delete a single organization:

- a. In the table, right-click the row for the organization you want to delete.

The actions menu appears.

- b. Click **Delete**.

To delete multiple organizations:

- a. In the table, select the check box for each organization you want to delete.

The available actions appear at the top of the table.

- b. At the top of the table, click **Delete**.

A confirmation window appears.

4. Click **Delete**.

A confirmation window appears.

5. Click **Delete**.

Tenable Security Center deletes the organization.



## Groups

User groups are a way to group rights to objects within an organization, and then quickly assign these rights to one or more users. A user's group membership determines their access to security data. When a user creates various objects such as reports, scan policies, dashboards, and other similar items, these objects are automatically shared among the group members if the group permissions allow view and control.

For more information, see [Add a Group](#), [View Group Details](#), and [Delete a Group](#).

### Group Options

Option	Description
<b>General tab</b>	
<b>Name</b>	The name for the group.
<b>Description</b>	A description for the group (e.g., <b>security team at the central office</b> or <b>executives on the east coast</b> ).
<b>Viewable Hosts</b>	The IP addresses and agent IDs that are viewable by the group. The selection is made by all defined assets or the selection of one or more asset lists.
<b>Repositories</b>	The repositories you want to share with the group.
<b>Log Correlation Engines</b>	The Log Correlation Engines you want to assign to the group.
<b>Sample Content</b>	When enabled, Tenable provides sample content objects to users in the group: <ul style="list-style-type: none"><li>• sample dashboards (<b>Executive 7 Day</b>, <b>Executive Summary</b>, and <b>Vulnerability Overview</b>)</li><li>• sample reports (<b>Critical and Exploitable Vulnerabilities</b>, <b>Monthly Executive</b>, and <b>Remediation Instructions by Host</b>)</li><li>• sample ARCs (<b>CCC 1: Maintain an Inventory of Software and Hardware</b>, <b>CCC 2: Remove Vulnerabilities and Misconfigurations</b>, <b>CCC 3: Deploy a</b></li></ul>



Option	Description
	<p data-bbox="501 247 1455 327"><b>Secure Network, CCC 4: Authorize Users, and CCC 5: Search for Malware and Intruders)</b></p> <ul data-bbox="469 369 1118 401" style="list-style-type: none"><li>• sample assets required for the sample ARCs</li></ul> <p data-bbox="420 443 1390 525">After enabling <b>Sample Content</b>, you must add a new user to the group before all users in the group can access the sample content.</p> <div data-bbox="423 556 1479 669"><p data-bbox="451 579 1450 648"><b>Note:</b> If a user in a group deletes a sample content object, the object is deleted for all other users in that group.</p></div> <div data-bbox="423 695 1479 1066"><p data-bbox="451 720 1419 795"><b>Note:</b> If you move a sample content object owner (e.g., move the first user in group A to group B), Tenable Security Center:</p><ol data-bbox="495 829 1430 1050" style="list-style-type: none"><li>1. Assigns their dashboards and ARCs to a new sample content object owner in group A. Tenable Security Center does not reassign reports or assets.</li><li>2. Recreates their dashboards, ARCs, and assets required for ARCs in group B. Tenable Security Center does not recreate reports.</li></ol></div>
<b>Share to Group</b> tab	
<b>Available Objects</b>	The list of available objects to be shared with the group on creation or edit in a bulk operation.



## Add a Group

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information about group options, see [Groups](#).

To add a group:

1. Log in to Tenable Security Center via the user interface.
2. Click **Users > Groups**.

The **Groups** page appears.

3. Click **Add**.

The **Add Group** page appears.

4. Configure the **General** options.
5. Configure the **Share to Group** options.
6. Click **Submit**.

Tenable Security Center saves your configuration.



## View Group Details

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can view details for any group. For more information, see [Groups](#).

To view group details:

1. Log in to Tenable Security Center via the user interface.
2. Click **Users > Groups**.

The **Groups** page appears.

3. Right-click the row for the group you want to view.

The actions menu appears.

-or-

Select the check box for the group you want to view.

The available actions appear at the top of the table.

4. Click **View**.

The **View Group** page appears.

Section	Action
<b>General</b>	<p>View general information for the group.</p> <ul style="list-style-type: none"><li>• <b>Name</b> —The group name.</li><li>• <b>Description</b> —The group description.</li><li>• <b>Created</b> —The date the group was created.</li><li>• <b>Last Modified</b> —The date the group options were last modified.</li><li>• <b>ID</b> —The group ID.</li></ul>
<b>Access</b>	<p>View the lists of <b>Viewable Hosts</b>, <b>Repositories</b>, and <b>LCES</b> users in the</p>



Section	Action
	group can access. For more information, see <a href="#">Group Options</a> .
<b>Preferences</b>	View whether you enabled <b>Sample Content</b> for the group. For more information, see <a href="#">Group Options</a> .
<b>Users</b>	View the list of users associated with the group.



## Delete a Group

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

To delete a group:

1. Log in to Tenable Security Center via the user interface.
2. Click **Users > Groups**.

The **Groups** page appears.

3. Select the group you want to delete:

To delete a single group:

- a. In the table, right-click the row for the group you want to delete.

The actions menu appears.

- b. Click **Delete**.

To delete multiple groups:

- a. In the table, select the check box for each group you want to delete.

The available actions appear at the top of the table.

- b. At the top of the table, click **Delete**.

A confirmation window appears.

4. Click **Delete**.

Tenable Security Center deletes the group.



---

## User Accounts

---

The **Users** page displays the user accounts on Tenable Security Center, limited by your account privileges. You can sort the columns or apply filters to locate specific user accounts. You can also add a user ([Add a TNS-Authenticated User](#), [Add an LDAP-Authenticated User](#), or [Add a SAML-Authenticated User](#)) or [Delete a User](#).

You can create one or more administrator accounts on Tenable Security Center. You can create one or more organizational users (security managers and custom roles) per organization. Tenable recommends you make at least one TNS-authenticated administrator and security manager user per organization so that you can still log in if the LDAP or SAML service becomes unavailable. For more information about user account types, see [User Access](#).

For more information about options available when configuring user accounts, see [User Account Options](#).

## Linked User Accounts

You can create linked user accounts to allow an Administrator user to switch to one or more Security Manager accounts without logging out and logging back in to Tenable Security Center. For more information, see [Linked User Accounts](#).

## API Keys

You can generate API keys to authenticate as a specific user for Tenable Security Center API requests. For more information, see [API Key Authentication](#).





## Add a TNS-Authenticated User

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information about user account configuration options, see [TNS User Account Options](#).

To add a TNS-authenticated user account as an administrator user:

1. Log in to Tenable Security Center via the user interface.
2. Click **Users > Users**.  
The **Users** page appears.
3. Click **Add**.  
The **Add User** page appears.
4. Select a **Role**.
5. If you selected **Security Manager** as the **Role**, select an **Organization**.
6. (Optional) Type a **First Name** and **Last Name**.
7. Type a **Username** and **Password** for the user.
8. If the **Type** drop-down box is visible, select **TNS**.
9. (Optional) Enable **User Must Change Password**.
10. Select a **Time Zone**.
11. (Optional) Select a **Scan Result Default Timeframe**.
12. (Optional) Enable **Cached Fetching**.
13. (Optional) Enable **Password Expiration** for the user.
14. (Optional) Enable **Dark Mode** for the user.
15. (Optional) Type **Contact Information** for the user.
16. Click **Submit**.

Tenable Security Center saves your configuration.



To add a TNS-authenticated user account as an organizational user:

1. Log in to Tenable Security Center via the user interface. You must log in with a user account belonging to the organization where you want to create a new user.
2. Click **Users > Users**.  
The **Users** page appears.
3. Click **Add**.  
The **Add User** page appears.
4. (Optional) Type a **First Name** and **Last Name** for the user.
5. If the **Type** drop-down box is visible, select **TNS**.
6. Type a **Username** and **Password** for the user.
7. (Optional) Enable **User Must Change Password**.
8. Select a **Time Zone**.
9. (Optional) Select a **Scan Result Default Timeframe**.
10. (Optional) Enable **Cached Fetching**
11. (Optional) Enable **Password Expiration** for the user.
12. Select a **Role**. For more information, see [User Roles](#).
13. Select a **Group**. For more information, see [Organizations and Groups](#).
14. (Optional) If you want to customize the group-related permissions for the user, modify the **Group Permissions** as described in [Custom Group Permissions](#).
15. (Optional) If you want to share an asset list with the user, select an **Asset**. For more information, see [Assets](#).
16. (Optional) Enable **Dark Mode** for the user.
17. (Optional) Type **Contact Information** for the user.
18. Click **Submit**.

Tenable Security Center saves your configuration.



## Add an LDAP-Authenticated User

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information about user account configuration options, see [User Accounts](#). To automatically add LDAP-authenticated users by importing users from your LDAP identity provider, see [Configure LDAP User Provisioning](#).

To add an LDAP-authenticated user account as an administrator user:

1. Log in to Tenable Security Center via the user interface.
2. Configure an LDAP server, as described in [LDAP Authentication](#). If you want the new user to be a member of an organization, associate the LDAP server with an organization.
3. Click **Users > Users**.

The **Users** page appears.

4. Click **Add**.

The **Add User** page appears.

5. Select a **Role** for the user account.
6. If you selected **Security Manager** as the **Role**, select an **Organization** for the user account. You must select an organization with an associated LDAP server.
7. (Optional) Type a **First Name** and **Last Name** for the user.
8. In the **Type** drop-down list, select **LDAP**. If **LDAP** does not appear in the drop-down list, add an LDAP server as described in [Add an LDAP Server](#).
9. Select the **LDAP Server** where you want to authenticate the user.
10. Type a **Search String** to find existing users on the LDAP server.
11. Click **Search**.

The page displays the **LDAP Users Found** by the LDAP search string.

12. Select an LDAP user from the **LDAP Users Found** drop-down box.



The page populates the **Username** option with your selection.

13. View the **Username**. Tenable does not recommend modifying the **Username** since it must match the username on the LDAP server.
14. Select a **Time Zone**.
15. (Optional) Select a **Scan Result Default Timeframe**.
16. (Optional) Enable **Cached Fetching**.
17. (Optional) Enable **Dark Mode** for the user.
18. (Optional) Type **Contact Information** for the user.
19. Click **Submit**.

Tenable Security Center saves your configuration.

To add an LDAP-authenticated user account as an organizational user:

1. Log in to Tenable Security Center via the user interface. You must log in with a user account belonging to the organization where you want to create a new user.
2. Confirm that an administrator user configured an LDAP server, and that the LDAP server was associated with the organization where you want to create a user account.
3. Click **Users > Users**.

The **Users** page appears.

4. Click **Add**.

The **Add User** page appears.

5. (Optional) Type a **First Name** and **Last Name** for the user.
6. In the **Type** drop-down list, select **LDAP**. If **LDAP** does not appear in the drop-down list, add an LDAP server as described in [Add an LDAP Server](#).
7. Select the **LDAP Server** where you want to authenticate the user.
8. Select an LDAP user from the **LDAP Users Found** drop-down box.

The page populates the **Username** option with your selection.



9. View the **Username**. Tenable does not recommend modifying the **Username** since it must match the username on the LDAP server.
10. Select a **Time Zone**.
11. (Optional) Select a **Scan Result Default Timeframe**.
12. (Optional) Enable **Cached Fetching**.
13. Select a **Role**. For more information, see [User Roles](#).
14. Select a **Group**. For more information, see [Organizations and Groups](#).
15. (Optional) If you want to customize the group-related permissions for the user, modify the **Group Permissions** as described in [Custom Group Permissions](#).
16. (Optional) If you want to share an asset list with the user, select an **Asset**. For more information, see [Assets](#).
17. (Optional) Enable **Dark Mode** for the user.
18. (Optional) Type **Contact Information** for the user.
19. Click **Submit**.

Tenable Security Center saves your configuration.



## Add a SAML-Authenticated User

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information about user account configuration options, see [SAML User Account Options](#). To automatically add SAML-authenticated users by importing users from your SAML identity provider, see [Configure SAML User Provisioning](#).

Before you begin:

- Configure SAML authentication, as described in [Configure SAML Authentication Manually via the User Interface](#).

To add a SAML-authenticated user account as an administrator user:

1. Log in to Tenable Security Center via the user interface.
2. Click **Users > Users**.  
The **Users** page appears.
3. Click **Add**.  
The **Add User** page appears.
4. (Optional) Type a **First Name** and **Last Name** for the user.
5. In the **Type** drop-down box, select **SAML**. If **SAML** does not appear in the drop-down box, configure SAML authentication as described in [Configure SAML Authentication Manually via the User Interface](#).
6. In the **Username** box, type the user's SAML username exactly as it appears in your identity provider SAML configuration for this user.
7. Select a **Time Zone**.
8. (Optional) Select a **Scan Result Default Timeframe**.
9. (Optional) Enable **Cached Fetching**.
10. (Optional) Enable **Dark Mode** for the user.



11. (Optional) Type **Contact Information** for the user.
12. Click **Submit**.

Tenable Security Center saves your configuration.

To add a SAML-authenticated user account as an organizational user:

1. Log in to Tenable Security Center via the user interface. You must log in with a user account belonging to the organization where you want to create a new user.
2. Click **Users > Users**.  
The **Users** page appears.
3. Click **Add**.  
The **Add User** page appears.
4. (Optional) Type a **First Name** and **Last Name** for the user.
5. In the **Type** drop-down list, select **SAML**. If **SAML** does not appear in the drop-down list, configure SAML authentication as described in [Configure SAML Authentication Manually via the User Interface](#).
6. In the **Username** box, type the user's SAML username exactly as it appears in your identity provider SAML configuration for this user.
7. Select a **Time Zone**.
8. (Optional) Select a **Scan Result Default Timeframe**.
9. (Optional) Enable **Cached Fetching**.
10. Select a **Role**. For more information, see [User Roles](#).
11. Select a **Group**. For more information, see [Organizations and Groups](#).
12. (Optional) To customize the user's object and user account management permissions, modify the **Group Permissions** as described in [Custom Group Permissions](#).
13. (Optional) To share an asset list with the user, select an **Asset**. For more information, see [Assets](#).
14. (Optional) Enable **Dark Mode** for the user.



15. (Optional) Type **Contact Information** for the user.
16. Click **Submit**.

Tenable Security Center saves your configuration.





# Manage User Accounts

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information about user accounts, see [User Accounts](#).

To view or edit a user account:

1. Log in to Tenable Security Center via the user interface.
2. In the left navigation, click **Users > Users**.

The **Users** page appears.

3. To filter the users that appear on the page, apply a filter as described in [Apply a Filter](#).

**Note:** If you are logged in with an administrator account, the **Organization** filter is set to **System** by default. To view users from other organizations, select a different organization for the **Organization** filter.

4. To view details for a user, see [View User Details](#).

5. To edit a user:

- a. Right-click the row for the user you want to edit.

The actions menu appears.

-or-

Select the check box for the user you want to edit.

The available actions appear at the top of the table.

- b. Click **Edit**.

The **Edit User** page appears.

- c. Modify the user details.

**Note:** If you want to edit a Tenable Security Center user that was created via user provisioning and you enabled **User Data Sync**, edit the user in your SAML or LDAP identity provider.



Otherwise, the Tenable Security Center user data synchronization overwrites your changes the next time the user logs in to Tenable Security Center using your SAML or LDAP identity provider. For more information about **User Data Sync**, see [SAML Authentication Options](#) or [LDAP Authentication Options](#).

d. Click **Submit**.

Tenable Security Center saves your configuration.

6. To delete a user, see [Delete a User](#).



## Edit Your User Account

**Required User Role:** Any

You can edit your user account to update your password, contact information, display preferences, and other settings depending on your user role.

To edit your user account as an administrator:

1. Log in to Tenable Security Center via the user interface.
2. Click **Users > Users**.

The **Users** page appears.

3. Right-click the row for your user account.

The actions menu appears.

-or-

Select the check box for your user account.

The available actions appear at the top of the table.

4. Click **More > Edit**.

The **Edit User** page appears.

5. Modify your user account settings. For more information, see [User Account Options](#).

6. Click **Submit**.

Tenable Security Center saves your configuration.

To edit your user account as an organizational user:

1. Log in to Tenable Security Center via the user interface.
2. Click **Username > Profile**.

The **Edit User Profile** page appears.

3. Modify your user account settings. For more information, see [User Account Options](#).



4. Click **Submit**.

Tenable Security Center saves your configuration.



## View User Details

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information about user accounts, see [User Accounts](#).

To view details for a user:

1. Log in to Tenable Security Center via the user interface.
2. Click **Users > Users**.

The **Users** page appears.

3. Right-click the row for the user you want to view.

The actions menu appears.

-or-

Select the check box for the user you want to view.

The available actions appear at the top of the table.

4. Click **View**.

The **View User** page appears.

5. View the following information for the user:

Section	Action
General	View general information for the user. <ul style="list-style-type: none"><li>• <b>Created</b> —The date the user was created.</li><li>• <b>Last Modified</b> —The date the user was last modified.</li><li>• <b>ID</b> —The user ID.</li></ul>
Membership	View role and organization information for the user. For more information, see <a href="#">User Account Options</a> .



<b>Password Expiration</b>	View password expiration settings for the user. For more information, see <a href="#">User Account Options</a> .
<b>Display Options</b>	View dark mode settings for the user. For more information, see <a href="#">User Account Options</a> .
<b>Contact Information</b>	View contact information for the user. For more information, see <a href="#">User Account Options</a> .
<b>API Key</b>	If the user has API keys, view the access key for the user. For more information, see <a href="#">Enable API Key Authentication</a> .
<b>Linked User Details</b>	<div style="border: 1px solid orange; padding: 5px; margin-bottom: 10px;"><b>Required User Role:</b> Administrator</div> View linked user accounts associated with the user: <ul style="list-style-type: none"><li>• <b>Linked Users</b> —If the user is an Administrator, view the linked Security Manager users.</li><li>• <b>Primary User</b> —If the user is a linked Security Manager, view the associated Administrator user.</li></ul> For more information, see <a href="#">Linked User Accounts</a> .



## Delete a User

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

If you want to migrate a user's objects, you must use a Security Manager account in the user's organization to delete the user. Other roles cannot migrate user objects.

**Note:** You cannot delete the first user created in any of your organizations. For more information, contact Tenable Support.

**Note:** If you want to delete an Administrator with linked user accounts, you must delete the linked accounts associated with the Administrator before deleting the Administrator, as described in [Delete a Linked User Account](#). For more information about linked user accounts, see [Linked User Accounts](#).

**Note:** If you want to delete a Tenable Security Center user that was created via user provisioning, delete the user from your SAML or LDAP identity provider. If you delete a user in Tenable Security Center that was created via user provisioning without deleting the user in your SAML or LDAP identity provider, Tenable Security Center automatically re-creates the user in Tenable Security Center the next time they log in using your SAML or LDAP identity provider. For more information, see [SAML User Provisioning](#) or [LDAP User Provisioning](#).

To delete a user:

1. Log in to Tenable Security Center via the user interface.
2. Click **Users > Users**.

The **Users** page appears.

3. Select the user you want to delete:

To delete a single user:

- a. In the table, right-click the row for the user you want to delete.

The actions menu appears.

- b. Click **Delete**.

To delete multiple users:



- a. In the table, select the check box for each user you want to delete.

The available actions appear at the top of the table.

- b. At the top of the table, click **More > Delete**.

A confirmation window appears.

4. (Optional) If you want to migrate the user's objects, click the toggle to migrate the user's objects to another user. Tenable Security Center supports migrating:

- Active scans, agent scans, and scan results
- Custom assets, credentials, audit files, and scan policies
- Freeze windows
- Queries
- Tickets and alerts
- ARCs
- Dashboards
- Reports, report images, report attributes, and report results

If you do not migrate the user's objects, Tenable Security Center deletes the user's objects.

**Note:** You cannot migrate objects when deleting an Administrator user because all Administrator-created objects are shared across Tenable Security Center and remain accessible after user deletion.

5. Click **Delete**.

Tenable Security Center deletes the user.





---

## Linked User Accounts

---

If a user needs to perform administrator and non-administrator tasks in Tenable Security Center, you can configure *linked user accounts* to allow an Administrator user to switch to one or more Security Manager users without logging out and logging back in to Tenable Security Center.

Users with linked user accounts can use a single set of login credentials to log in to Tenable Security Center as an Administrator, then switch to a linked Security Manager, from one linked Security Manager to another, or from a linked Security Manager to the linked Administrator. You do not need to re-authenticate to switch between linked user accounts after logging in as the linked Administrator.

The following restrictions apply to linked user accounts:

- Each Administrator can have one linked Security Manager per organization.
- Each linked Security Manager can be associated with only one Administrator user account.
- Linked Security Managers cannot log in to Tenable Security Center directly. You must log in to the Administrator account associated with the linked Security Manager, then switch users.
- You cannot convert a standalone user account to a linked user account.
- You cannot convert a linked user account to a standalone user account. To unlink a Security Manager user from an Administrator user, delete the linked Security Manager, then create a standalone Security Manager.

For more information about user accounts in Tenable Security Center, see [User Access](#) and [User Roles](#).

For more information about linked user accounts, see:

- [Add a Linked User](#)
- [Switch to a Linked User Account](#)
- [Edit a Linked User Account](#)
- [Delete a Linked User Account](#)



## Add a Linked User

**Required User Role:** Administrator

To allow an Administrator user to switch to one or more Security Manager users without logging out and logging back in to Tenable Security Center, add a linked user account to the Administrator. The following restrictions apply to linked user accounts:

- You cannot convert a standalone user account to a linked user account.
- Each Administrator can have one linked Security Manager per organization.
- Each linked Security Manager user can be associated with only one Administrator user account.

For more information about linked user accounts, see [Linked User Accounts](#). For more information about user account configuration options, see [User Account Options](#).

To add a linked Security Manager to an Administrator:

1. Log in to Tenable Security Center via the user interface.
2. Click **Users > Users**.

The **Users** page appears.

3. Right-click the row for the Administrator to which you want to add a linked user.

The actions menu appears.

-or-

Select the check box for the Administrator to which you want to add a linked user.

The available actions appear at the top of the table.

4. Click **Add Linked User**.

The **Add User** page appears. Tenable Security Center pre-populates the **First Name**, **Last Name**, and **Contact Information** fields with values from the Administrator user account.

5. Select an **Organization**.
6. (Optional) Modify the **First Name** and **Last Name** for the user.



7. Type a **Username** for the user.
8. Select a **Time Zone**.
9. (Optional) Select a **Scan Result Default Timeframe**.
10. (Optional) Enable **Cached Fetching**.
11. (Optional) Enable or disable **Dark Mode** for the user.
12. (Optional) Modify the **Contact Information** for the user.
13. Click **Submit**.

Tenable Security Center saves your configuration.

What to do next:

- Switch between linked Administrator and Security Manager user accounts, as described in [Switch to a Linked User Account](#).



## Switch to a Linked User Account

**Required User Role:** Administrator with linked user accounts or a Security Manager linked to an Administrator. For more information, see [User Roles](#) and [Linked User Accounts](#).

Linked users can switch from the linked Administrator to a linked Security Manager, from one linked Security Manager to another, or from a linked Security Manager to the linked Administrator user. For more information about linked user accounts, see [Linked User Accounts](#).


Before you begin:

- Configure one or more linked user accounts, as described in [Add a Linked User](#).

To switch to a linked user account:

1. Log in to Tenable Security Center via the user interface.

**Note:** You must log in to the Administrator account associated with the linked Security Manager, then switch between linked users. Linked Security Managers cannot log in to Tenable Security Center directly.

2. Click your user profile  icon > **Switch User**. This option appears only if the current logged-in user already has a linked user account.

The **Switch To Linked Account** window appears.

3. Click the name of the linked user you want to switch to.
4. Click **Switch**.

Tenable Security Center logs you in as the selected user.

The username menu updates to show the linked user account name and associated organization.



## Edit a Linked User Account

**Required User Role:** Administrator or a Security Manager linked to an Administrator. For more information, see [User Roles](#) and [Linked User Accounts](#).

You can edit a linked user account as an administrator or while logged in as the linked user. For more information, see [Linked User Accounts](#).

To edit a linked user account as an Administrator:

1. Log in to Tenable Security Center via the user interface.

2. Click **Users > Users**.

The **Users** page appears.

3. Filter the **Users** page to show user accounts for the linked user's organization, as described in [Apply a Filter](#).

4. Right-click the row for the linked user account you want to edit.

The actions menu appears.

-or-

Select the check box for the linked user account you want to edit.

The available actions appear at the top of the table.

5. Click **More > Edit**.

The **Edit User** page appears.

6. Modify the user account settings. For more information, see [User Account Options](#).

7. Click **Submit**.

Tenable Security Center saves your configuration.

To edit your linked user account as a linked user:

1. Log in to Tenable Security Center via the user interface.

2. Switch to a linked user account, as described in [Switch to a Linked User Account](#).



3. Click **Username > Profile**.

The **Edit User Profile** page appears.

4. Modify the user account settings. For more information, see [User Account Options](#).

5. Click **Submit**.

Tenable Security Center saves your configuration.



## Delete a Linked User Account

**Required User Role:** Administrator

If you want to remove a linked user account, you must delete the linked account. You cannot convert a linked user account into a standalone user account. For more information about linked user accounts, see [Linked User Accounts](#).

**Note:** If you want to delete an Administrator with linked user accounts, you must delete the linked accounts associated with the Administrator before deleting the Administrator.

To delete a linked user account:

1. Log in to Tenable Security Center via the user interface.
2. Click **Users > Users**.

The **Users** page appears.

3. Apply a filter to view the organization for the user you want to delete, as described in [Apply a Filter](#).
4. Select the linked user account you want to delete:

To delete a single linked user account:

- a. In the table, right-click the row for the linked user account you want to delete.

The actions menu appears.

- b. Click **Delete**.

To delete multiple linked user accounts:

- a. In the table, select the check box for each linked user account you want to delete.

The available actions appear at the top of the table.

- b. At the top of the table, click **Delete**.

A confirmation window appears.



5. (Optional) If you want to migrate the user's objects, click the toggle to migrate the user's objects to another user. Tenable Security Center supports migrating:

- Active scans, agent scans, and scan results
- Custom assets, credentials, audit files, and scan policies
- Freeze windows
- Queries
- Tickets and alerts
- ARCs
- Dashboards
- Reports, report images, report attributes, and report results

If you do not migrate the user's objects, Tenable Security Center deletes the user's objects.

**Note:** You cannot migrate objects when deleting an Administrator user because all Administrator-created objects are shared across Tenable Security Center and remain accessible after user deletion.

6. Click **Delete**.

Tenable Security Center deletes the user.





## Custom Group Permissions

When creating or editing a user account, you can customize a user's group permissions.

- Your selection in the **Group** field assigns the user to a group.
- Your selections in the **Group Permissions** section grant the user resource (user and object) permissions in their assigned group and other groups.

For more information about organizations and groups, see [Organizations and Groups](#).

In the **Group Permissions** section, the **Manage All Users** and **Manage All Objects** sliders enable or disable all of the settings in the **User Permission** and **Object Permission** columns, respectively. By default, the system enables all permissions for all groups. You can clear the check boxes in each group row to restrict the user's ability to perform the following actions on the resources within a group.

Resources Controlled by Manage Users/ User Permissions	Resources Controlled by Manage Objects/ Object Permissions
<ul style="list-style-type: none"><li>• Users (edit and delete)</li><li>• Groups (edit and delete)</li></ul>	<ul style="list-style-type: none"><li>• Reports (launch, stop, copy, delete, and sometimes edit)</li></ul> <div data-bbox="703 1121 1479 1276" style="border: 1px solid #0070C0; padding: 5px;"><p><b>Note:</b> A user can only edit reports within their assigned group, even if you grant them <b>Object Permissions</b> for another group.</p></div> <ul style="list-style-type: none"><li>• Report results (publish, email, copy, and delete)</li><li>• Report images (delete)</li><li>• Report attributes (delete)</li><li>• Scan results (launch, import, copy, send to report, stop, pause, and delete)</li><li>• Policies (edit, copy, and delete)</li><li>• Assets (edit, share, and delete)</li><li>• Alerts (edit and delete)</li><li>• Audit files (edit, share, and delete)</li></ul>



Resources Controlled by Manage Users/ User Permissions	Resources Controlled by Manage Objects/ Object Permissions
	<ul style="list-style-type: none"><li>• Credentials (edit, share, and delete)</li><li>• Tickets (edit, resolve, and close)</li><li>• Risk rules (delete)</li><li>• Queries (edit, share, and delete)</li><li>• ARCs (edit, share, copy, and delete)</li><li>• Dashboards (edit, share, copy, and delete)</li></ul>

## Examples

Consider the following examples for a user assigned to *Group1*.

### Control Permissions to Resources in the User's Assigned Group

- If you select the **User Permissions** and/or **Object Permissions** check boxes in the *Group1* row, the user can perform actions for all resources in *Group1*, including the resources owned by other users.
- If you clear the **User Permissions** and/or **Object Permissions** check boxes in the *Group1* row, the user cannot perform actions on resources owned by other users in *Group1*.

### Control Permissions to Resources in Other Groups

- If you select the **User Permissions** and/or **Object Permissions** check boxes in the *Group2* row, the user can perform actions for all resources in *Group2*, including the resources owned by other users.

**Note:** Although the user receives many permissions for resources in *Group2*, the user cannot edit reports owned by *Group2* users. Users must be assigned to *Group2* and have **Object Permissions** selected in order to edit reports, active scans, and agent scans.

- If you clear the **User Permissions** and/or **Object Permissions** check boxes in the *Group2* row, the user cannot perform actions on resources owned by other users in *Group2*.



## Generate API Keys

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

API keys allow you to authenticate as a specific user for Tenable Security Center API requests. Administrators can generate API keys for any user account. Other roles can generate API keys for user accounts with the same role. For more information, see [API Key Authentication](#).

**Note:** If you generate API keys for a user that already has API keys, the old keys will be replaced. If you delete existing keys or generate new API keys for a user, Tenable Security Center deauthorizes API requests attempted with the old keys.

Before you begin:

- Enable API keys to allow users to perform API key authentication, as described in [Enable API Key Authentication](#).

To generate API keys:

1. Log in to Tenable Security Center via the user interface.

2. Click **Users > Users**.

The **Users** page appears.

3. Right-click the row for the user for which you want to generate an API key.

The actions menu appears.

-or-

Select the check box for the user for which you want to generate an API key.

The available actions appear at the top of the table.

4. Click **API Keys > Generate API Key**.

A confirmation window appears.

5. Click **Generate**.

The **Your API Key** window appears, displaying the access key and secret key for the user.



6. Save the API keys in a safe location.

**Note:** You cannot view API secret keys in the Tenable Security Center interface after initial generation. If you lose your existing secret key, you must generate new API keys.

What to do next:

- Use the API keys to perform API requests, as described in [API Key Authorization](#) in the *Tenable Security Center API Best Practices Guide*.



## Delete API Keys

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

After you delete a user's API keys, the deleted keys cannot be used for authentication in Tenable Security Center API requests. To generate new API keys for a user, see [Generate API Keys](#). For more information, see [API Key Authentication](#).

To delete API keys:

1. Log in to Tenable Security Center via the user interface.

2. Click **Users > Users**.

The **Users** page appears.

3. Right-click the row for the user for which you want to delete API keys.

The actions menu appears.

-or-

Select the check box for the user for which you want to delete API keys.

The available actions appear at the top of the table.

4. Click **API Keys > Delete API Key**.

A confirmation window appears.

5. Click **Delete**.

The system deletes the API keys.



## User Account Options

You can configure the following options for Tenable Security Center user accounts. The available options depend on the user type, the user's role, and the role of the user adding or editing the user.

- [TNS User Account Options](#)
- [LDAP User Account Options](#)
- [SAML User Account Options](#)

For more information about user accounts in Tenable Security Center, see [User Accounts](#).

### TNS User Account Options

To add a TNS-authenticated user, see [Add a TNS-Authenticated User](#).

Option	Description
<b>First Name</b>	The user's first name.
<b>Last Name</b>	The user's last name.
<b>Type</b>	<p>(If LDAP or SAML are configured) The type of authentication you want to perform on the user:</p> <ul style="list-style-type: none"><li>• Tenable (<b>TNS</b>)</li><li>• Lightweight Directory Access Protocol (<b>LDAP</b>)</li><li>• Security Assertion Markup Language (<b>SAML</b>)</li></ul> <p>You must configure an LDAP server or SAML authentication in order to select <b>LDAP</b> or <b>SAML</b> from the <b>Type</b> drop-down box.</p>
<b>Username</b>	<p>(Required) The username for the user account.</p> <div style="border: 1px solid #0070C0; padding: 5px;"><p><b>Note:</b> The username value is case-sensitive.</p></div>
<b>Password</b>	<p>(Required) The password for the user account.</p> <div style="border: 1px solid #008000; padding: 5px;"><p><b>Tip:</b> Tenable recommends using passwords that meet stringent length and complexity requirements.</p></div>



	<p>For information about Tenable Security Center password data encryption, see <a href="#">Encryption Strength</a>.</p> <p>When editing a user, type a new password to change the password for the user account.</p>
<b>Confirm Password</b>	(Required) When creating a user or changing a user's password, re-type the password for the user account.
<b>Password Change</b>	<p>Click <b>Change Password</b> to change the password for the user account.</p> <p>To change a user password:</p> <ol style="list-style-type: none"><li>1. Begin editing a user account, as described in <a href="#">Manage User Accounts</a> or <a href="#">Edit Your User Account</a>.</li><li>2. Click <b>Change Password</b>.</li><li>3. In the <b>Current Password</b> box, type your password. If you do not have a password (for example, you have a SAML-authenticated or LDAP-authenticated user account), type any string of characters in this field.</li><li>4. In the <b>Password</b> box, type a new password.</li><li>5. In the <b>Confirm Password</b> box, type the new password again.</li><li>6. Click <b>Submit</b>.</li></ol> <p>Tenable Security Center saves your configuration.</p>
<b>Current Password</b>	(If you click <b>Change Password</b> ) Type your password. If you do not have a password (for example, you have a SAML-authenticated or LDAP-authenticated user account), type any string of characters in this field.
<b>User Must Change Password</b>	When enabled, the user must change their password upon initial login.
<b>Account Locked</b>	When enabled, the user cannot log in to Tenable Security Center. An administrator must unlock the user's account to allow them to log in.



<b>Time Zone</b>	(Required) The time zone for the user.
<b>Scan Result Default Time-frame</b>	The default <b>Completion Time</b> filter applied when the user accesses or refreshes the scan results page.
<b>Cached Fetching</b>	When enabled, Tenable Security Center caches plugin policy information and performs plugin policy downloads once per page load.
<b>Password Expiration</b>	
<b>Password Never Expires</b>	When enabled, the user's password will never expire. Any password expiration settings at the user or organization level will not apply to this user.
<b>Enable Password Expiration or Custom Password Expiration</b>	<p>When enabled, the user's password will expire after the number of days specified in the <b>Expiration Days</b> box.</p> <p>When disabled, the user's password expiration settings will default to the organization settings. For more information about organization options, see <a href="#">Organizations</a>.</p> <p>The user will receive daily password expiration notifications at login, starting 14 days before the password expires. After the password expires, the user must change their password at the next login. For more information about Tenable Security Center notifications, see <a href="#">Notifications</a>.</p>
<b>Expiration Days</b>	The number of days before the user's password expires. You can enter a number between 1 and 365.
<b>Membership</b>	
<b>Role</b>	<p>(Required) The role assigned to the user. For more information, see <a href="#">User Roles</a>.</p> <p>Administrator users can create <b>Administrator</b> or <b>Security Manager</b> user accounts. Organizational users can create <b>Auditor</b>, <b>Credential Manager</b>, <b>Executive</b>, <b>No Role</b>, <b>Security Analyst</b>, <b>Security Manager</b>, or <b>Vulnerability Analyst</b> accounts at their own privilege level or lower. For example:</p> <ul style="list-style-type: none"><li>• If a user is an Auditor, they can create new Auditors or lesser roles.</li></ul>





	<ul style="list-style-type: none"><li>If a custom user has the Create Policies privilege but not the Update Feeds privilege, that user can create users with the Create Policies privilege, but not the Update Feeds privilege.</li></ul>
<b>Organization</b>	(Required) The organization where you want to assign the user account.
<b>Group</b>	(Required) The group where you want to assign the user account. A user's group determines their access to Tenable Security Center resources. For more information about groups, see <a href="#">Groups</a> .  To grant a user limited privileges to other groups' resources, see <a href="#">Custom Group Permissions</a> .
<b>Group Permissions</b>	
<b>Manage All Users</b>	When enabled, allows the user to manage users in all of the user's assigned groups. For more information, see <a href="#">Custom Group Permissions</a> .
<b>Manage All Objects</b>	When enabled, allows the user to manage objects in all of the user's assigned groups. For more information, see <a href="#">Custom Group Permissions</a> .
<b>Responsibility</b>	
<b>Asset</b>	Assigns a user to an asset list for which the user is responsible. Assigning a user to an asset list makes it easier to determine who in a group or organization should be assigned tickets, notifications, and other tasks to resolve particular issues. Selecting an asset updates the User Responsibility Summary in the <a href="#">Vulnerability Analysis</a> section.
<b>Display Options</b>	
<b>Dark Mode</b>	When enabled, sets the Tenable Security Center user interface to dark mode for the user.
<b>Contact Information</b>	



<b>Title</b>	The contact information for the user.
<b>Address</b>	
<b>City</b>	
<b>State</b>	
<b>Country</b>	
<b>Email</b>	
<b>Phone</b>	

## LDAP User Account Options

You must configure an LDAP server to add LDAP-authenticated users. For more information, see [LDAP Authentication](#).

To add an LDAP-authenticated user, see [Add an LDAP-Authenticated User](#).

Option	Description
<b>First Name</b>	The user's first name.
<b>Last Name</b>	The user's last name.
<b>Type</b>	<p>(If LDAP or SAML are configured) The type of authentication you want to perform on the user:</p> <ul style="list-style-type: none"><li>• Tenable (<b>TNS</b>)</li><li>• Lightweight Directory Access Protocol (<b>LDAP</b>)</li><li>• Security Assertion Markup Language (<b>SAML</b>)</li></ul> <p>You must configure an LDAP server or SAML authentication in order to select <b>LDAP</b> or <b>SAML</b> from the <b>Type</b> drop-down box.</p>
<b>LDAP Server</b>	The LDAP server you want to use to authenticate the user.
<b>Search String</b>	The LDAP search string you want to use to filter your user search. Use the format: <i>attribute=&lt;filter text&gt;</i> . You can use wildcards, and the option



	<p>accepts up to 1024 characters.</p> <p><b>Examples</b></p> <p>sAMAccountName=*</p> <p>mail=a*</p> <p>displayName=C*</p>
<b>LDAP Users Found</b>	<p>A filtered list of LDAP user accounts retrieved by the <b>Search String</b>. Your selection in this option populates the <b>Username</b> option.</p>
<b>The Username for this account must match a user on the LDAP server in order to authenticate.</b>	<p>If the user was created via LDAP user provisioning, the username on the LDAP server associated with the Tenable Security Center user account. If you select a username in the drop-down, Tenable Security Center overwrites the Tenable Security Center user account using information from the new LDAP user you selected. By default, this option is blank.</p> <p>You do not need to configure this option to enable user provisioning or automatic synchronization of user data between your LDAP server and Tenable Security Center.</p> <p>For more information, see <a href="#">LDAP User Provisioning</a>.</p>
<b>Username</b>	<p>(Required) The username, populated by your <b>LDAP Users Found</b> selection. This username must match a user on the LDAP server in order to authenticate successfully.</p>
<b>Time Zone</b>	<p>(Required) The time zone for the user.</p>
<b>Scan Result Default Time-frame</b>	<p>The default <b>Completion Time</b> filter applied when the user accesses or refreshes the scan results page.</p>
<b>Cached Fetching</b>	<p>When enabled, Tenable Security Center caches plugin policy information and performs plugin policy downloads once per page load.</p>
<b>Membership</b>	
<b>Role</b>	<p>(Required) The role assigned to the user. For more information, see <a href="#">User Roles</a>.</p>



	<p>Administrator users can create <b>Administrator</b> or <b>Security Manager</b> user accounts. Organizational users can create <b>Auditor</b>, <b>Credential Manager</b>, <b>Executive</b>, <b>No Role</b>, <b>Security Analyst</b>, <b>Security Manager</b>, or <b>Vulnerability Analyst</b> accounts at their own privilege level or lower. For example:</p> <ul style="list-style-type: none"><li>• If a user is an Auditor, they can create new Auditors or lesser roles.</li><li>• If a custom user has the Create Policies privilege but not the Update Feeds privilege, that user can create users with the Create Policies privilege, but not the Update Feeds privilege.</li></ul>
<b>Organization</b>	(Required) The organization where you want to assign the user account.
<b>Group</b>	<p>(Required) The group where you want to assign the user account. A user's group determines their access to Tenable Security Center resources. For more information about groups, see <a href="#">Groups</a>.</p> <p>To grant a user limited privileges to other groups' resources, see <a href="#">Custom Group Permissions</a>.</p>
<b>Group Permissions</b>	
<b>Manage All Users</b>	When enabled, allows the user to manage users in all of the user's assigned groups. For more information, see <a href="#">Custom Group Permissions</a> .
<b>Manage All Objects</b>	When enabled, allows the user to manage objects in all of the user's assigned groups. For more information, see <a href="#">Custom Group Permissions</a> .
<b>Responsibility</b>	
<b>Asset</b>	Assigns a user to an asset list for which the user is responsible. Assigning a user to an asset list makes it easier to determine who in a group or organization should be assigned tickets, notifications, and other tasks to resolve particular issues. Selecting an asset updates the User Responsibility Summary in the <a href="#">Vulnerability Analysis</a> section.
<b>Display Options</b>	
<b>Dark Mode</b>	When enabled, sets the Tenable Security Center user interface to dark mode for the user.



Contact Information	
Title	The contact information for the user.
Address	
City	
State	
Country	
Email	
Phone	

## SAML User Account Options

You must configure SAML authentication to add SAML-authenticated users. For more information, see [SAML Authentication](#).

To add a SAML-authenticated user, see [Add a SAML-Authenticated User](#).

Option	Description
First Name	The user's first name.
Last Name	The user's last name.
Type	<p>(If LDAP or SAML are configured) The type of authentication you want to perform on the user:</p> <ul style="list-style-type: none"><li>• Tenable (<b>TNS</b>)</li><li>• Lightweight Directory Access Protocol (<b>LDAP</b>)</li><li>• Security Assertion Markup Language (<b>SAML</b>)</li></ul> <p>You must configure an LDAP server or SAML authentication in order to select <b>LDAP</b> or <b>SAML</b> from the <b>Type</b> drop-down box.</p>
Username	(Required) The user's SAML username. Type the username exactly as it appears in your identity provider SAML configuration for this user.



<b>Time Zone</b>	(Required) The time zone for the user.
<b>Scan Result Default Time-frame</b>	The default <b>Completion Time</b> filter applied when the user accesses or refreshes the scan results page.
<b>Cached Fetching</b>	When enabled, Tenable Security Center caches plugin policy information and performs plugin policy downloads once per page load.
<b>Membership</b>	
<b>Role</b>	<p>(Required) The role assigned to the user. For more information, see <a href="#">User Roles</a>.</p> <p>Administrator users can create <b>Administrator</b> or <b>Security Manager</b> user accounts. Organizational users can create <b>Auditor</b>, <b>Credential Manager</b>, <b>Executive</b>, <b>No Role</b>, <b>Security Analyst</b>, <b>Security Manager</b>, or <b>Vulnerability Analyst</b> accounts at their own privilege level or lower. For example:</p> <ul style="list-style-type: none"><li>• If a user is an Auditor, they can create new Auditors or lesser roles.</li><li>• If a custom user has the Create Policies privilege but not the Update Feeds privilege, that user can create users with the Create Policies privilege, but not the Update Feeds privilege.</li></ul>
<b>Organization</b>	(Required) The organization where you want to assign the user account.
<b>Group</b>	<p>(Required) The group where you want to assign the user account. A user's group determines their access to Tenable Security Center resources. For more information about groups, see <a href="#">Groups</a>.</p> <p>To grant a user limited privileges to other groups' resources, see <a href="#">Custom Group Permissions</a>.</p>
<b>Group Permissions</b>	
<b>Manage All Users</b>	When enabled, allows the user to manage users in all of the user's assigned groups. For more information, see <a href="#">Custom Group Permissions</a> .
<b>Manage All Objects</b>	When enabled, allows the user to manage objects in all of the user's assigned groups. For more information, see <a href="#">Custom Group Permissions</a> .



<b>Responsibility</b>	
<b>Asset</b>	Assigns a user to an asset list for which the user is responsible. Assigning a user to an asset list makes it easier to determine who in a group or organization should be assigned tickets, notifications, and other tasks to resolve particular issues. Selecting an asset updates the User Responsibility Summary in the <a href="#">Vulnerability Analysis</a> section.
<b>Display Options</b>	
<b>Dark Mode</b>	When enabled, sets the Tenable Security Center user interface to dark mode for the user.
<b>Contact Information</b>	
<b>Title</b>	The contact information for the user.
<b>Address</b>	
<b>City</b>	
<b>State</b>	
<b>Country</b>	
<b>Email</b>	
<b>Phone</b>	



## LDAP Authentication

Adding LDAP servers allows you to use one or more external LDAP servers for Tenable Security Center user account authentication. LDAP authentication enhances the security of Tenable Security Center by inheriting password complexity requirements from environments mandated by security policy.

After you configure an LDAP server, create Tenable Security Center user accounts for each LDAP user you want to grant access.

- To manually add LDAP-authenticated users in Tenable Security Center, see [Add an LDAP-Authenticated User](#).
- To automatically add LDAP-authenticated users by importing users from your LDAP identity provider, see [LDAP User Provisioning](#).

Then, users with LDAP-authenticated accounts can log in to Tenable Security Center using the **Sign In Using Identity Provider** button, as described in [Log In to the Web Interface](#).

You can also use configured LDAP servers as LDAP query assets. For more information, see [Assets](#).

**Note:** Tenable Security Center does not support Microsoft Active Directory Lightweight Directory Services (AD LDS) servers for LDAP authentication.

**Note:** Tenable Security Center cannot retrieve more than one page of LDAP results. If Tenable Security Center asset list or user authentication queries are not retrieving all expected results, consider modifying your LDAP pagination control settings to increase the results per page.

For more information, see [Add an LDAP Server](#) and [Delete an LDAP Server](#).

### LDAP Authentication Options

Configure the LDAP settings as directed by your LDAP server administrator. Click **Test LDAP Settings** to validate the connection.

Option	Description
Server Settings	
Name	(Required) A unique name for the LDAP server.





Option	Description
Description	A description for the LDAP server.
Hostname	(Required) The IP address or DNS name of the LDAP server.
Port	(Required) The remote LDAP port. Confirm the selection with your LDAP server administrators. <ul style="list-style-type: none"><li>• When <b>Encryption</b> is <b>None</b>, <b>Port</b> is typically <b>389</b>.</li><li>• When <b>Encryption</b> is <b>TLS</b> or <b>LDAPS</b>, <b>Port</b> is typically <b>636</b>.</li></ul>
Encryption	If the LDAP server encrypts communications, the encryption method: Transport Layer Security (STARTTLS) or LDAP over SSL (LDAPS).
Username / Password	(Required) The username and password for an account on the LDAP server with credentials to search for user data. For example, Active Directory servers require an authenticated search.  Format the username as provided by the LDAP server.  <b>Tip:</b> It is recommended to use passwords that meet stringent length and complexity requirements.
User Provisioning	You can enable user provisioning to automatically create LDAP-authenticated users in Tenable Security Center by importing user accounts from your LDAP identity provider. When user provisioning is enabled, users who log in to your LDAP identity provider are automatically created in Tenable Security Center.  Tenable Security Center supports the following LDAP authentication systems for user provisioning: <ul style="list-style-type: none"><li>• Active Directory on Microsoft Server 2016 (on-premises)</li><li>• Active Directory on Microsoft Server 2019 (on-premises)</li></ul> For more information, see <a href="#">LDAP User Provisioning</a> .  <b>Note:</b> If you want to delete a Tenable Security Center user that was created via



Option	Description
	<p>LDAP user provisioning, delete the user from your LDAP identity provider. If you delete a user in Tenable Security Center that was created via LDAP user provisioning without deleting the user in your LDAP identity provider, Tenable Security Center automatically re-creates the user in Tenable Security Center the next time they log in using your LDAP identity provider.</p>
User Data Sync	<p>If you enable <b>User Provisioning</b>, you can enable <b>User Data Sync</b> to allow Tenable Security Center to automatically synchronize contact information (first name, last name, email address, and phone number) from your LDAP identity provider for Tenable Security Center users created via LDAP user provisioning. For more information, see <a href="#">LDAP User Provisioning</a>.</p> <p><b>Note:</b> If you want to edit a Tenable Security Center user that was created via LDAP user provisioning and you enabled <b>User Data Sync</b>, edit the user in your LDAP identity provider. Otherwise, the Tenable Security Center user data synchronization overwrites your changes the next time the user logs in to Tenable Security Center using your LDAP identity provider.</p>
<b>LDAP Schema Settings</b>	
Base DN	(Required) The LDAP search base used as the starting point to search for the user data.
User Object Filter	The string you want to use to create a search based on a location or filter other than the default search base or attribute.
<b>User Schema Settings (Optional, if you plan to use the LDAP server only as an LDAP query asset.)</b>	
Username Attribute	The attribute name on the LDAP server that contains the username for the account. This is often specified by the string <b>sAMAccountName</b> in Active Directory servers that may be used by LDAP. Contact your LDAP server administrator for the correct value.
E-mail Attribute	The attribute name on the LDAP server that contains the email address for the account. This is often specified by the string <b>mail</b> in Active Directory servers that may be used by LDAP. Contact your LDAP server admin-



Option	Description
	istrator for the correct value.
Phone Attribute	The attribute name on the LDAP server that contains the telephone number for the account. This is often specified by the string <b>telephoneNumber</b> in Active Directory servers that may be used by LDAP. Contact your LDAP server administrator for the correct value.
Name Attribute	The attribute name on the LDAP server that contains the name associated with the account. This is often specified by the string <b>CN</b> in Active Directory servers that may be used by LDAP. Contact your LDAP administrator for the correct value.
<b>Access Settings</b>	
Organizations	The Tenable Security Center organizations you want to authenticate using this LDAP server.
<b>Advanced Settings</b>	
Lowercase	When enabled, Tenable Security Center modifies the usernames sent by the LDAP server to use only lowercase characters.  Tenable recommends keeping this option disabled.
DNS Field	The LDAP server parameter used in LDAP server requests to filter the returned asset data.  Tenable recommends using the default value provided by Tenable Security Center.
Time Limit	The number of seconds you want Tenable Security Center to wait for search results from the LDAP server.  Tenable recommends using the default value provided by Tenable Security Center.

**Note:** Access to Active Directory is performed via AD's LDAP mode. When using multiple AD domains, LDAP access may be configured to go through the Global Catalog. Port 3268 is the default non-SSL/TLS setting, while port 3269 is used for SSL/TLS connections by default. More general information about LDAP



earches via the Global Catalog may be found at: [http://technet.microsoft.com/en-us/library/cc728188-7e3d-4100-8000-000000000000/=ws.10\).aspx](http://technet.microsoft.com/en-us/library/cc728188-7e3d-4100-8000-000000000000/=ws.10).aspx).



## Add an LDAP Server

**Required User Role:** Administrator

For more information about LDAP server options, see [LDAP Authentication](#).

To add an LDAP server connection:

1. Log in to Tenable Security Center via the user interface.
2. Click **Resources > LDAP Servers**.
3. Click **Add**.
4. Configure the following settings as described in the [Options](#) table:
  - **Server Settings**
  - **LDAP Schema Settings**
  - **User Schema Settings**
  - **Access Settings**
5. If necessary, modify the default **Advanced Settings**.
6. Click **Test LDAP Settings** to validate the LDAP server connection.
7. Click **Submit**.

What to do next:

- Add LDAP-authenticated user accounts.
  - To manually add LDAP-authenticated users in Tenable Security Center, see [Add an LDAP-Authenticated User](#).
  - To automatically add LDAP-authenticated users by importing users from your LDAP identity provider, see [Configure LDAP User Provisioning](#).



## LDAP User Provisioning

You can enable user provisioning to automatically create LDAP-authenticated users in Tenable Security Center by importing user accounts from your LDAP identity provider. When user provisioning is enabled, users who log in to your LDAP identity provider are automatically created in Tenable Security Center.

Tenable Security Center supports the following LDAP authentication systems for user provisioning:

- Active Directory on Microsoft Server 2016 (on-premises)
- Active Directory on Microsoft Server 2019 (on-premises)

For more information about LDAP authentication in Tenable Security Center, see [LDAP Authentication](#).

If you enable user provisioning and a user who does not have a Tenable Security Center user account logs in using your LDAP identity provider, Tenable Security Center automatically creates a user account for them in Tenable Security Center.

Tenable Security Center creates users using data from attribute fields you map to the corresponding fields in your LDAP identity provider. If you enable **User Data Sync** for an LDAP server, each time a user logs into Tenable Security Center using your LDAP identity provider, Tenable Security Center updates any mapped attribute fields in Tenable Security Center with values from the fields in your LDAP identity provider. For more information about **User Data Sync**, see [LDAP Authentication Options](#).

**Note:** If you want to edit a Tenable Security Center user that was created via LDAP user provisioning and you enabled **User Data Sync**, edit the user in your LDAP identity provider. Otherwise, the Tenable Security Center user data synchronization overwrites your changes the next time the user logs in to Tenable Security Center using your LDAP identity provider.

**Note:** If you want to delete a Tenable Security Center user that was created via LDAP user provisioning, delete the user from your LDAP identity provider. If you delete a user in Tenable Security Center that was created via LDAP user provisioning without deleting the user in your LDAP identity provider, Tenable Security Center automatically re-creates the user in Tenable Security Center the next time they log in using your LDAP identity provider.

For more information, see [Configure LDAP User Provisioning](#).



# Configure LDAP User Provisioning

**Required User Role:** Administrator

You can enable user provisioning to automatically create LDAP-authenticated users in Tenable Security Center by importing user accounts from your LDAP identity provider. When user provisioning is enabled, users who log in to your LDAP identity provider are automatically created in Tenable Security Center.

Tenable Security Center supports the following LDAP authentication systems for user provisioning:

- Active Directory on Microsoft Server 2016 (on-premises)
- Active Directory on Microsoft Server 2019 (on-premises)

For more information, see [LDAP User Provisioning](#).

To manually create LDAP-authenticated users in Tenable Security Center, see [Add an LDAP-Authenticated User](#).

For more information about user account configuration options, see [LDAP User Account Options](#).

Before you begin:

1. (Recommended) Create a backup of your user directory in your LDAP identity provider.
2. In Tenable Security Center, add an LDAP server, as described in [Add an LDAP Server](#).
3. In your LDAP identity provider, create the following custom user attributes: `tenableRoleID`, `tenableGroupID`, and `tenableOrgID`.
4. In your LDAP identity provider, specify the role, group, and organization you want to assign the user in Tenable Security Center:
  - a. In the `tenableRoleID` attribute field, type the ID for the Tenable Security Center role you want to assign to the user. To locate the ID for a role, see [View User Role Details](#).
  - b. In the `tenableGroupID` attribute field, type the ID for the Tenable Security Center group you want to assign to the user. To locate the ID for a group, see [View Group Details](#).



- c. In the `tenableOrgID` attribute field, type the ID for the Tenable Security Center organization you want to assign to the user. To locate the ID for an organization, see [View Organization Details](#).

To enable LDAP user provisioning for an LDAP server:

1. Log in to Tenable Security Center via the user interface.
2. In the left navigation, click **Resources > LDAP Servers**.

The **LDAP Servers** page appears.

3. Right-click the row for the LDAP server where you want to enable user provisioning.

The actions menu appears.

-or-

Select the check box for the LDAP server where you want to enable user provisioning.

The available actions appear at the top of the table.

4. Click **Edit**.

The **Edit LDAP Server** page appears.

5. In the **Server Settings** section, click the toggle to enable **User Provisioning**.
6. (Optional) To automatically update contact information (first name, last name, email address, and phone number) for users created via LDAP user provisioning, click the **User Data Sync** toggle. For more information about **User Data Sync**, see [LDAP Authentication Options](#).
7. (Optional) In the **User Schema Settings** section, type the names of the attributes in your LDAP identity provider you want to use to populate the **Username**, **Email**, **Phone**, **First Name**, and **Last Name** for users created via LDAP user provisioning. For more information about user account options, see [LDAP User Account Options](#).

**Note:** If you enable **User Data Sync** and configure the options in the **User Schema Settings** section, Tenable Security Center automatically updates the attributes in the **User Schema Settings** section with values from your LDAP identity provider. For more information, see [LDAP Authentication Options](#).





8. Click **Submit**.

Tenable Security Center saves your configuration.



## Delete an LDAP Server

**Required User Role:** Administrator

For more information, see [LDAP Authentication](#).

To delete an LDAP server connection:

**Note:** If you delete a connection to an LDAP server, the users associated with that server cannot log in to Tenable Security Center. Tenable recommends reconfiguring associated user accounts before deleting LDAP server connections.

1. Log in to Tenable Security Center via the user interface.
2. Click **Resources > LDAP Servers**.
3. Select the server connection you want to delete:

To delete a single server connection:

- a. In the table, right-click the row for the server connection you want to delete.  
The actions menu appears.
- b. Click **Delete**.

To delete multiple server connections:

- a. In the table, select the check box for each server connection you want to delete.  
The available actions appear at the top of the table.
- b. At the top of the table, click **Delete**.

A confirmation window appears.

4. Click **Delete**.

Tenable Security Center deletes the LDAP server.



## LDAP Servers with Multiple OUs

Tenable's Tenable Security Center LDAP configuration does not support the direct addition of multiple Organizational Units (OUs) in the LDAP configuration page. Two deployment options are possible for those with multiple OUs.

For general information about LDAP Servers, see [LDAP Authentication](#).

### Option 1 (Recommended)

When you complete these changes, new users who are members of this group can log in immediately. No restart is required.

Before you begin:

- In LDAP, add a new group for Tenable Security Center users.
- In LDAP, allow existing Active Directory users to become members of the new group.

To configure LDAP with multiple OUs (Option 1):

1. Log in to Tenable Security Center via the user interface.
2. Click **Resources > LDAP Servers**.
3. Add the LDAP server, as described in [Add an LDAP Server](#).

**Note:** Use the Distinguished Name (DN) of the new group as the **Search Base** (e.g., *CN=Tenablesec,DC=target,DC=example,DC=com*).

4. Log out of Tenable Security Center.
5. Log in to Tenable Security Center as the organizational user you want to manage the users.
6. Create a user account for each Active Directory user in the new group, as described in [Add an LDAP-Authenticated User](#).

In the **Search String** box, type `=*`.

### Option 2



Use a high level **Search Base** in the LDAP configuration. For example: **DC=target,DC=example,DC=com**.

The example above could be used along with a **Search String** for global usage. As another example, you might use this search string, when used in the configuration, applies to all LDAP searches:

*memberOf=CN=nested1,OU=cftest1,DC=target,DC=example,DC=com*

**Note:** This option is limited to 128 characters.

To configure LDAP with multiple OUs (Option 2):

1. Log in to Tenable Security Center via the user interface.
2. Click **Resources > LDAP Servers**.
3. Begin configuring the LDAP server, as described in [Add an LDAP Server](#).

LDAP Configuration

← Back

Test LDAP Settings

### Server Settings

Hostname: 192.168.55.33

Port: 636

Encryption: LDAPS

Username: TARGET\Administrator

Password: Password Set

### LDAP Schema

Base DN: DC=target,DC=example,DC=com

User Object Filter: memberOf=CN=nested1,OU=ctest1,DC=t

### User Schema Settings

Username Attribute: sAMAccountName

E-mail Attribute: mail

Phone Attribute: telephoneNumber

Name Attribute: CN

Submit Cancel

4. Click **Test LDAP Settings** to test configurations.
5. Log out of Tenable Security Center.
6. Log in to Tenable Security Center as the organizational user you want to manage the users.
7. Create a user account for each Active Directory user, as described in [Add an LDAP-Authenticated User](#).

In the **Search String** box, type =\*.



## SAML Authentication

You can configure SAML authentication so that Tenable Security Center users can use identity provider-initiated single sign-on (SSO) when logging in to Tenable Security Center. Tenable Security Center supports SAML 2.0-based authentication (for example, Okta, OneLogin, Microsoft ADFS, or Shibboleth 2.0).

For more information, see:

- [Configure SAML Authentication Automatically via the User Interface](#)
- [Configure SAML Authentication Manually via the User Interface](#)
- [Configure SAML Authentication via the SimpleSAML Module](#)

After you configure SAML authentication, create Tenable Security Center user accounts for each SAML user you want to grant access.

- To manually add SAML-authenticated users in Tenable Security Center, see [Add a SAML-Authenticated User](#).
- To automatically add SAML-authenticated users by importing users from your SAML identity provider, see [SAML User Provisioning](#).

Then, users with SAML-authenticated accounts can log in to Tenable Security Center using the **Sign In Using Identity Provider** button, as described in [Log In to the Web Interface](#).

### Considerations for Advanced SAML Features

Because Tenable Security Center cannot accept private keys to decrypt SAML assertions, Tenable Security Center does not support SAML assertion encryption. If you want to configure SAML authentication in Tenable Security Center, choose an identity provider that does not require assertion encryption and confirm that assertion encryption is not enabled.

For information about Tenable Security Center communications encryption, see [Encryption Strength](#).

**Note:** Tenable Support does not assist with configuring or troubleshooting advanced SAML features.

### SAML Authentication Options



Option	Description
<b>SAML</b>	<p>Specifies whether SAML authentication is enabled or disabled.</p> <p>If you disable SAML, the system clears your SAML configuration settings and prevents SAML-authenticated user accounts from accessing Tenable Security Center.</p>
<b>Source</b>	<p>Specifies your SAML configuration method:</p> <ul style="list-style-type: none"><li>• <b>Import</b> —Configure SAML authentication by uploading the metadata file provided by your identity provider, as described in <a href="#">Configure SAML Authentication Automatically via the User Interface</a>.</li><li>• <b>Entry</b> —Configure SAML authentication by manually configuring SAML options using data from the metadata file provided by your identity provider, as described in <a href="#">Configure SAML Authentication Manually via the User Interface</a>.</li></ul>
<b>Type</b>	<p>Specifies the identity provider you are using: <b>SAML 2.0</b> (e.g., Okta, OneLogin, Shibboleth 2.0, etc.).</p>
<b>Entity ID</b>	<p>The name of the Entity ID attribute. Type the attribute exactly as it appears in your identity provider SAML configuration.</p> <div style="border: 1px solid green; padding: 5px;"><p><b>Tip:</b> This is the <b>Federation Service Identifier</b> value in Microsoft ADFS.</p></div>
<b>Identity Provider (IdP)</b>	<p>The identity provider identifier string.</p> <p>For example:</p> <ul style="list-style-type: none"><li>• The <b>Identity Provider Issuer</b> value in Okta.</li><li>• The <b>Federation Service Identifier</b> value in Microsoft ADFS.</li></ul>
<b>Username Attribute</b>	<p>The name of the SAML username attribute. Type the attribute exactly as it appears in your identity provider SAML configuration.</p> <p>For example, if your SAML username attribute is <b>NameID</b>, specify <b>NameID</b> to instruct Tenable Security Center to recognize users who match the format <code>NameID=username</code>.</p>



Option	Description
<b>Single Sign-on Service</b>	The identity provider URL where users log in via single sign-on. Type the URL exactly as it appears in your identity provider SAML metadata.
<b>Single Logout Service</b>	The identity provider URL where users log out. Type the URL exactly as it appears in your identity provider SAML metadata.
<b>Certificate Data</b>	The text of the identity provider's X.509 SSL certificate, without the <code>===BEGIN CERT===</code> and the <code>===END CERT===</code> strings.
<b>User Provisioning</b>	<p>You can enable user provisioning to automatically create SAML-authenticated users in Tenable Security Center by importing user accounts from your SAML identity provider. When user provisioning is enabled, users who log into your SAML identity provider are automatically created in Tenable Security Center. For more information, see <a href="#">SAML User Provisioning</a>.</p> <div data-bbox="418 877 1479 1157" style="border: 1px solid #0070C0; padding: 10px;"><p><b>Note:</b> If you want to delete a Tenable Security Center user that was created via SAML user provisioning, delete the user from your SAML identity provider. If you delete a user in Tenable Security Center that was created via SAML user provisioning without deleting the user in your SAML identity provider, Tenable Security Center automatically re-creates the user in Tenable Security Center the next time they log in using your SAML identity provider.</p></div>
<b>User Data Sync</b>	<p>If you enabled <b>User Provisioning</b>, you can enable <b>User Data Sync</b> to allow Tenable Security Center to automatically synchronize contact information from your SAML identity provider for Tenable Security Center users created via SAML user provisioning. For more information, see <a href="#">SAML User Provisioning</a>.</p> <div data-bbox="418 1451 1479 1688" style="border: 1px solid #0070C0; padding: 10px;"><p><b>Note:</b> If you want to edit a Tenable Security Center user that was created via SAML user provisioning and you enabled <b>User Data Sync</b>, edit the user in your SAML identity provider. Otherwise, the Tenable Security Center user data sync overwrites your changes the next time the user logs in to Tenable Security Center using your SAML identity provider.</p></div> <div data-bbox="418 1709 1479 1864" style="border: 1px solid #0070C0; padding: 10px;"><p><b>Note:</b> Tenable Security Center does not update required fields (<b>Organization ID</b>, <b>Group ID</b>, and <b>Role ID</b>). To change the organization, group, or role for a user created via SAML user provisioning, see <a href="#">Manage User Accounts</a>.</p></div>





# Configure SAML Authentication Automatically via the User Interface

**Required User Role:** Administrator

You can use this method to configure most types of SAML authentication via the Tenable Security Center user interface. If you encounter issues with this method (for example, when configuring Microsoft ADFS), try the module method described in [Configure SAML Authentication via the SimpleSAML Module](#).

For more information about SAML authentication and SAML authentication options, see [SAML Authentication](#).

Before you begin:

- Save your identity provider SAML metadata file to a directory on your local computer.

To automatically configure SAML authentication for Tenable Security Center users:

1. Log in to Tenable Security Center via the user interface.
2. In the left navigation, click **System > Configuration**.

The **Configuration** page appears.

3. Click the **SAML** button.

The **SAML Configuration** page appears.

4. In the **General** section, confirm the **SAML** toggle is enabled.

If you want to disable SAML authentication for Tenable Security Center users, click the toggle.

5. In the **Source** drop-down box, select **Import**.

The page updates to display additional options.

6. In the **Type** drop-down box, select **SAML 2.0** (e.g., Okta, OneLogin, Shibboleth 2.0, etc.).
7. Click **Choose File** and browse to the SAML metadata file from your identity provider.



**Note:** The metadata file must match the **Type** you selected. If Tenable Security Center rejects the file, contact your identity provider for assistance.

8. Click **Submit**.

Tenable Security Center saves your configuration.

What to do next:

- Click **Download SAML Configuration XML**, save the .xml file locally, and use it to configure your identity provider SAML configuration. For more information, see [SAML Authentication XML Configuration Examples](#).
- Add SAML-authenticated user accounts.
  - To manually add SAML-authenticated users in Tenable Security Center, see [Add a SAML-Authenticated User](#).
  - To automatically add SAML-authenticated users by importing users from your SAML identity provider, see [Configure SAML User Provisioning](#).
- Instruct users to log in to Tenable Security Center using the **Sign In Using Identity Provider** button, as described in [Log In to the Web Interface](#).



# Configure SAML Authentication Manually via the User Interface

**Required User Role:** Administrator

You can use this method to configure most types of SAML authentication via the Tenable Security Center interface. However, you may prefer a more streamlined method:

- To configure SAML Authentication automatically, use the method described in [Configure SAML Authentication Automatically via the User Interface](#).
- If you encounter issues with either method (for example, when configuring Microsoft ADFS), try the module method described in [Configure SAML Authentication via the SimpleSAML Module](#).

For more information about SAML authentication and SAML authentication options, see [SAML Authentication](#).

Before you begin:

- Save your identity provider SAML metadata file to a directory on your local computer.

To configure SAML authentication for Tenable Security Center users:

1. Log in to Tenable Security Center via the user interface.
2. In the left navigation, click **System > Configuration**.

The **Configuration** page appears.

3. Click the **SAML** button.

The **SAML Configuration** page appears.

4. In the **General** section, confirm the **SAML** toggle is enabled.

If you want to disable SAML authentication for Tenable Security Center users, click the toggle.

5. In the **Source** drop-down box, select **Entry**.

The page updates to display additional options.

6. In the **SAML Settings** section, configure the options:



- a. In the **Type** drop-down box, select **SAML 2.0** (e.g., Okta, OneLogin, Shibboleth 2.0, etc.).
- b. In the **Entity ID** box, type the name of the Entity ID attribute exactly as it appears in your identity provider SAML configuration.
- c. In the **Identity Provider (IdP)** box, type identity provider identifier string.
- d. In the **Username Attribute** box, type the SAML username attribute exactly as it appears in your identity provider SAML configuration.
- e. In the **Single Sign-on Service** box, type the identity provider URL where users log in via single sign-on exactly as it appears in your identity provider SAML metadata.
- f. In the **Single Logout Service** box, type the identity provider URL where users log out exactly as it appears in your identity provider SAML metadata.
- g. In the **Certificate Data** box, paste the text of the identity provider's X.509 SSL certificate, without the `====BEGIN CERT====` and the `====END CERT====` strings.

7. Click **Submit**.

Tenable Security Center saves your configuration.

What to do next:

- Click **Download SAML Configuration XML**, save the .xml file locally, and use it to configure your identity provider SAML configuration. For more information, see [SAML Authentication XML Configuration Examples](#).
- Add SAML-authenticated user accounts.
  - To manually add SAML-authenticated users in Tenable Security Center, see [Add a SAML-Authenticated User](#).
  - To automatically add SAML-authenticated users by importing users from your SAML identity provider, see [Configure SAML User Provisioning](#).
- Instruct users to log in to Tenable Security Center using the **Sign In Using Identity Provider** button, as described in [Log In to the Web Interface](#).



## Configure SAML Authentication via the SimpleSAML Module

**Tip:** The recommended method for configuring SAML authentication is via the Tenable Security Center interface:

- [Configure SAML Authentication Automatically via the User Interface](#)
- [Configure SAML Authentication Manually via the User Interface](#)

**Required User Role:** Administrator

If you encounter issues [configuring SAML via the Tenable Security Center interface](#), you can use a hidden SimpleSAML module to automatically configure SAML authentication.

For general information, see [SAML Authentication](#).

Before you begin:

- Save your identity provider SAML metadata file to a directory on your local computer.

To configure SAML authentication via the SimpleSAML module:

1. Log in to Tenable Security Center via the user interface.
2. In the left navigation, click **System > Configuration**.

The **Configuration** page appears.

3. Click the **SAML** button.

The **SAML Configuration** page appears.

4. Type placeholder values into all SAML configuration options. You do not need to configure valid values.
5. Click **Submit**.

Tenable Security Center saves your configuration.

6. Log in to Tenable Security Center via the command line interface (CLI).
7. Navigate to and open the `/opt/sc/support/etc/SimpleSAML/config/authsources.php` file.



- Copy and paste the following text into the file, between the `)`, line and the `);` line:

```
// This is a authentication source which handles admin authentication.
'admin' => array(
// The default is to use core:AdminPassword, but it can be replaced with
// any authentication source.

'core:AdminPassword',
),
```

- Save the file.
- In a browser, navigate to **`https://<Tenable Security Center IP address or hostname>/saml/module.php/core/frontpage_config.php`**.

The **SimpleSAML.php installation** page appears.

- On the **Configuration** tab, click **Login as administrator**.

The **Enter your username and password** page appears.

- In the **Username** box, type *admin*.
- In the **Password** box, type *admin*.
- Click **Login**.

- On the **Federation** tab, in the **Tools** section, click **XML to SimpleSAML.php metadata converter**.

The **Metadata parser** page appears.

- Click **Choose File** and select your identity provider SAML metadata file.
- Click **Parse**.

Tenable Security Center validates the identity provider SAML metadata file. If the metadata file is supported, Tenable Security Center populates the XML metadata box with content from your metadata file. If the metadata file is not supported, you cannot use it for SAML authentication in Tenable Security Center.

- In the **saml20-idp-remote** section, copy the text in the box.



19. Log in to Tenable Security Center via the command line interface (CLI).
20. Navigate to and open the `/opt/sc/support/etc/SimpleSAML/metadata/saml20-idp-remote.php` file (for SAML 2.0 or Shibboleth 2.0).
21. Paste the text into the file, after the `<?php` line.
22. Save the file.
23. Navigate to and open the `/opt/sc/support/etc/SimpleSAML/config/authsources.php` file again.
24. Confirm the **idp** URL in the `authsources.php` file matches the **\$metadata** URL in the `saml20-idp-remote.php` or `shib13-idp-remote.php` file:

Valid `authsources.php` syntax example:

```
'idp' => 'http://www.okta.com/abcdefghijklmnopqr0s1'
```

Valid `saml20-idp-remote.php` or `shib13-idp-remote.php` syntax example:

```
$metadata['http://www.okta.com/abcdefghijklmnopqr0s1']
```

25. In a browser, navigate to **`https://<Tenable Security Center IP address or hostname>/sam-  
I/module.php/core/frontpage_config.php`**.

The **SimpleSAML.php installation** page appears.

26. On the **Authentication** tab, click **Test configured authentication sources**.

The **Test authentication sources** page appears.

27. Click **1**.

Your identity provider login page appears.

28. Log in to your identity provider.

The **SAML 2.0 SP Demo Example** page appears. If this page does not appear, the configuration did not succeed.

What to do next:



- In the Tenable Security Center interface, on the **SAML Configuration** page, click **Download SAML Configuration XML**, save the .xml file locally, and use it to configure your identity provider SAML configuration. For more information, see [SAML Authentication XML Configuration Examples](#).
- Add SAML-authenticated user accounts.
  - To manually add SAML-authenticated users in Tenable Security Center, see [Add a SAML-Authenticated User](#).
  - To automatically add SAML-authenticated users by importing users from your SAML identity provider, see [Configure SAML User Provisioning](#).
- Instruct users to log in to Tenable Security Center using the **Sign In Using Identity Provider** button, as described in [Log In to the Web Interface](#).





## SAML User Provisioning

You can enable user provisioning to automatically create SAML-authenticated users in Tenable Security Center by importing user accounts from your SAML identity provider. When user provisioning is enabled, users who log into your SAML identity provider are automatically created in Tenable Security Center. For more information about SAML authentication in Tenable Security Center, see [SAML Authentication](#).

If you enable user provisioning and a user who does not have a Tenable Security Center user account logs in using your SAML identity provider, Tenable Security Center automatically creates a user account for them in Tenable Security Center.

Tenable Security Center creates users using data from attribute fields you map to the corresponding fields in your SAML identity provider. If you enable **User Data Sync**, each time a user logs into Tenable Security Center using your SAML identity provider, Tenable Security Center updates any mapped attribute fields in Tenable Security Center with values from the fields in your SAML identity provider. For more information about **User Data Sync**, see [SAML Authentication Options](#).

**Note:** If you want to edit a Tenable Security Center user that was created via SAML user provisioning and you enabled **User Data Sync**, edit the user in your SAML identity provider. Otherwise, the Tenable Security Center user data sync overwrites your changes the next time the user logs in to Tenable Security Center using your SAML identity provider.

**Note:** If you want to delete a Tenable Security Center user that was created via SAML user provisioning, delete the user from your SAML identity provider. If you delete a user in Tenable Security Center that was created via SAML user provisioning without deleting the user in your SAML identity provider, Tenable Security Center automatically re-creates the user in Tenable Security Center the next time they log in using your SAML identity provider.

For more information, [Configure SAML User Provisioning](#).



# Configure SAML User Provisioning

**Required User Role:** Administrator

You can enable user provisioning to automatically create SAML-authenticated users in Tenable Security Center by importing user accounts from your SAML identity provider. When user provisioning is enabled, users who log into your SAML identity provider are automatically created in Tenable Security Center. For more information, see [SAML User Provisioning](#).

To manually create SAML-authenticated users in Tenable Security Center, see [Add a SAML-Authenticated User](#).

For more information about user account configuration options, see [SAML User Account Options](#).

Before you begin:

- Configure SAML authentication, as described in [Configure SAML Authentication Manually via the User Interface](#).

To import SAML-authenticated user accounts from your SAML identity provider:

1. Log in to Tenable Security Center via the user interface.
2. In the left navigation, click **System > Configuration**.

The **Configuration** page appears.

3. Click the **SAML** button.

The **SAML Configuration** page appears.

4. In the **SAML Settings** section, click the toggle to enable **User Provisioning**.
5. (Optional) To automatically update contact information for imported SAML-authenticated users, click the **User Data Sync** toggle. For more information about **User Data Sync**, see [SAML Authentication Options](#).
6. Click **Submit**.

Tenable Security Center saves your configuration.

What to do next:



- In your SAML identity provider, map the required Tenable Security Center user attribute fields to the corresponding fields for users in your identity provider: **Organization ID**, **Group ID**, and **Role ID**.

**Note:** Tenable Security Center uses the fields listed in the **Attribute Mapping** section to create and update users in Tenable Security Center. Any Tenable fields that you map to corresponding fields in your SAML identity provider populate when Tenable Security Center imports SAML users into Tenable Security Center. If you enable **User Data Sync**, each time a user logs into Tenable Security Center using your SAML identity provider, Tenable Security Center updates any mapped attribute fields in Tenable Security Center with values from the corresponding fields in your SAML identity provider.



## SAML Authentication XML Configuration Examples

Identity provider SAML configurations vary widely, but you can use the following examples to guide your SAML-side configurations.

- [OneLogin Example](#)
- [Okta Example](#)
- [Microsoft ADFS Example](#)

### OneLogin Example

In the OneLogin SAML configuration, paste data from your .xml download file.

OneLogin Field	Description
Relay State	Leave this field blank.
Audience	Type <code>tenable.sc</code> .
Recipient	Type <code>https://&lt;Tenable Security Center host&gt;/saml/module.php/saml/sp/saml2-acs.php/1</code> , where <i>&lt;Tenable Security Center host&gt;</i> is the IP address or hostname for Tenable Security Center.
ACS (Consumer) URL Validator	Type <code>-*</code> .
ACS (Consumer) URL	Type <code>https://&lt;Tenable Security Center host&gt;/saml/module.php/saml/sp/saml2-acs.php/1</code> , where <i>&lt;Tenable Security Center host&gt;</i> is the IP address or hostname for Tenable Security Center.
Single Logout URL	Type <code>https://&lt;Tenable Security Center host&gt;/saml/module.php/saml/index.php?sls</code> , where <i>&lt;Tenable Security Center host&gt;</i> is the IP address or hostname for Tenable Security Center.

### Okta Example

In the Okta SAML configuration, paste data from your .xml download file.



Okta Field	Description
General	
Single Sign On URL	Type <code>https://&lt;Tenable Security Center host&gt;/saml/module.php/saml/sp/saml2-acis.php/1</code> , where <i>&lt;Tenable Security Center host&gt;</i> is the IP address or hostname for Tenable Security Center.
Recipient URL	Type <code>https://&lt;Tenable Security Center host&gt;/saml/module.php/saml/sp/saml2-acis.php/1</code> , where <i>&lt;Tenable Security Center host&gt;</i> is the IP address or hostname for Tenable Security Center.
Destination URL	Type <code>https://&lt;Tenable Security Center host&gt;/saml/module.php/saml/sp/saml2-acis.php/1</code> , where <i>&lt;Tenable Security Center host&gt;</i> is the IP address or hostname for Tenable Security Center.
Audience Restriction	Type <code>tenable.sc</code> .
Default Relay State	Leave this field blank.
Name ID Format	Set to Unspecified.
Response	Set to Signed.
Assertion Signature	Set to Signed.
Signature Algorithm	Set to RSA_SHA256.
Digest Algorithm	Set to SHA256.
Assertion Encryption	Set to Unencrypted.
SAML Single Logout	Set to Disabled.
authnContextClassRef	Set to PasswordProtectedTransport.
Honor Force Authentication	Set to Yes.



Okta Field	Description
SAML Issuer ID	Type <code>http://www.okta.com/\${org.externalKey}</code> .
Attribute Statements	
FirstName	Set to <b>Name Format:</b> Unspecified and <b>Value:</b> <code>user.firstName</code> .
LastName	Set to <b>Name Format:</b> Unspecified and <b>Value:</b> <code>user.lastName</code> .
Email	Set to <b>Name Format:</b> Unspecified and <b>Value:</b> <code>user.email</code> .
username	Set to <b>Name Format:</b> Unspecified and one of the following: <ul style="list-style-type: none"><li>• <b>Value:</b> <code>user.displayName</code>, if your Tenable Security Center user account usernames are full names (e.g., Jill Smith).</li><li>• <b>Value:</b> <code>user.email</code>, if your Tenable Security Center user account usernames are email addresses (e.g., <code>jsmith@website.com</code>).</li><li>• <b>Value:</b> <code>user.login</code>, if your Tenable Security Center user account usernames are name-based text strings (e.g., <code>jsmith</code>).</li></ul>

## Microsoft ADFS Example

In the Microsoft ADFS configuration, paste data from your `.xml` download file.

Microsoft ADFS Configuration	Description
Edit Authentication Methods window	
Extranet	Select, at minimum, the <b>Forms Authentication</b> check box.
Intranet	Select, at minimum, the <b>Forms Authentication</b> check box.
Add Relying Party Trust wizard	
Welcome section	<ul style="list-style-type: none"><li>• Select <b>Claims aware</b>.</li></ul>



Microsoft ADFS Configuration	Description
	<ul style="list-style-type: none"><li>• Select <b>Import data about the relying party from a file</b>.</li><li>• Browse to and select the SAML configuration .xml file you downloaded from Tenable Security Center.</li></ul> <div data-bbox="529 480 1479 598" style="border: 1px solid #0070C0; padding: 5px;"><b>Note:</b> If you see a warning that some content was skipped, click <b>Ok</b> to continue.</div>
Specify Display Name section	In the <b>Display Name</b> box, type your Tenable Security Center FQDN.
Configure Certificate section	Browse to and select the encryption certificate you want to use.
Choose Access Control Policy section	Select the <b>Permit everyone</b> policy.
Ready to Add Trust section	<ul style="list-style-type: none"><li>• On the <b>Advanced</b> tab, select <b>SHA256</b> or the value dictated by your security policy.</li><li>• On the <b>Identifiers</b> tab, confirm the information is accurate.</li><li>• On the <b>Endpoints</b> tab, confirm the information is accurate.</li></ul>
Finish section	Select the <b>Configure claims issuance policy for this application</b> check box.
Edit Claim Issuance Policy window	Add one or more claim rules to specify the ADFS value you want Tenable Security Center to use when authenticating SAML users. For example: <b>To transform an incoming claim:</b> <ol style="list-style-type: none"><li>1. In <b>Incoming claim type</b>, select <b>Email address</b> or <b>UPN</b>.</li><li>2. In <b>Outgoing claim type</b>, select <b>Name ID</b>.</li><li>3. In <b>Outgoing name ID format</b>, select <b>Transient Identifier</b>.</li><li>4. Select the <b>Pass through all claim values</b> check box.</li></ol>



Microsoft ADFS Configuration	Description
	<p data-bbox="448 300 922 331"><b>To send LDAP attributes as claim:</b></p> <ol data-bbox="483 373 1206 552" style="list-style-type: none"><li data-bbox="483 373 1109 405">1. In <b>Attribute store</b>, select <b>Active Directory</b>.</li><li data-bbox="483 443 1130 474">2. In <b>LDAP Attribute</b>, select <b>E-Mail Addresses</b>.</li><li data-bbox="483 512 1206 543">3. In <b>Outgoing Claim Type</b>, select <b>E-Mail Addresses</b>.</li></ol> <div data-bbox="448 579 1479 657" style="border: 1px solid #0070C0; padding: 5px;"><p data-bbox="475 604 1167 636"><b>Note:</b> Tenable Support does not assist with claim rules.</p></div>





---

## Certificate Authentication

---

You can use configure SSL client certificate authentication for Tenable Security Center user account authentication. Tenable Security Center supports:

- SSL client certificates
- smart cards
- personal identity verification (PIV) cards
- Common Access Cards (CAC)

Configuring certificate authentication is a multi-step process.

To fully configure SSL client certificate authentication for Tenable Security Center user accounts:

1. Configure Tenable Security Center to allow SSL client certificate authentication, as described in [Configure Tenable Security Center to Allow SSL Client Certificate Authentication](#).
2. Configure Tenable Security Center to trust certificates from your CA, as described in [Trust a Custom CA](#).
3. Add TNS-authenticated user accounts for the users you want to authenticate via certificate, as described in [Add a TNS-Authenticated User](#).
4. (Optional) If you want to validate client certificates against a certificate revocation list (CRL), configure CRLs or OCSP in Tenable Security Center, as described in [Configure a CRL in Tenable Security Center](#) or [Configure OCSP Validation in Tenable Security Center](#).

What to do next:

- Instruct users to log in to Tenable Security Center via certificate, as described in [Log in to the Web Interface via SSL Client Certificate](#).



# Configure Tenable Security Center to Allow SSL Client Certificate Authentication

You must configure the Tenable Security Center server to allow SSL client certificate connections. For complete information about certificate authentication, see [Certificate Authentication](#).

To allow SSL client certificate authentication:

1. Open the `/opt/sc/support/conf/sslverify.conf` file in a text editor.
2. Edit the **SSLVerifyClient** setting:

Value	Description
none (default)	Tenable Security Center does not accept SSL certificates for user authentication.
require	Tenable Security Center requires a valid SSL certificate for user authentication.
optional	<p>Tenable Security Center accepts but does not require a valid SSL certificate for user authentication.</p> <p>If a user does not present a certificate, they can log in via username and password.</p> <div style="border: 1px solid blue; padding: 5px;"><p><b>Note:</b> Some browsers may not connect to Tenable Security Center when you use the <b>optional</b> setting.</p></div>
optional_no_ca	<p>Tenable Security Center accepts valid and invalid SSL certificates for user authentication.</p> <div style="border: 1px solid green; padding: 5px;"><p><b>Tip:</b> This setting does not configure reliable user authentication, but you can use it to troubleshoot issues with your SSL connection and determine whether there is an issue with the key or the CA.</p></div>

3. Edit the **SSLVerifyDepth** setting to specify the length of the certificate chain you want Tenable Security Center to accept for user authentication. For example:



- When set to **0**, Tenable Security Center accepts self-signed certificates.
- When set to **1**, Tenable Security Center does not accept intermediate certificates. Tenable Security Center accepts self-signed certificates or certificates signed by known CAs.
- When set to **2**, Tenable Security Center accepts up to 1 intermediate certificate. Tenable Security Center accepts self-signed certificates, certificates signed by known CAs, or certificates signed by unknown CAs whose certificate was signed by a known CA.

4. Save the file.

Tenable Security Center saves your configuration.



## Configure a CRL in Tenable Security Center

**Required User Role:** Root user

You can enable a certificate revocation list (CRL) in Tenable Security Center to prevent users from authenticating to Tenable Security Center if their certificate matches a revocation in the CRL.

**Note:** Tenable Support does not assist with CRL creation or configuration in Tenable Security Center.

Before you begin:

- Confirm that you have the `mod_ssl` Apache module installed on Tenable Security Center.
- Back up the `/opt/sc/data/CA/` directory in case you encounter issues and need to restore the current version.

To configure a CRL in Tenable Security Center:

1. In a text editor, open the `/opt/sc/support/conf/sslverify.conf` file.
  - a. Set the **SSLVerifyClient** setting to **Require** or **Optional**, as described in [SSLVerifyClient](#).
  - b. Set the **SSLVerifyDepth** setting, as described in [SSLVerifyDepth](#).
  - c. Save the file.

Tenable Security Center saves your configuration.

2. Restart Tenable Security Center, as described in [Start, Stop, or Restart Tenable Security Center](#).

Tenable Security Center restarts.

3. Confirm that your CA root configuration file contains the following parameters:
  - `crl_dir`
  - `database`
  - `crl`



- `clr_extensions`
- `default_crl_days`

For example:

```
...
# Directory and file locations.
dir                = /opt/sc/data/CA
crl_dir            = /opt/sc/support/conf/crl
database           = /opt/sc/support/conf/index.txt
# The root key and root certificate.
private_key        = /opt/sc/support/conf/TenableCA.key
certificate         = /opt/sc/data/CA/TenableCA.crt
# For certificate revocation lists.
crl                = /opt/sc/support/conf/crl/ca.crl
crl_extensions     = crl_ext
default_crl_days   = 30
...
```

4. Save your CA root configuration file as `YourCAname.conf` in a subdirectory of `/opt/sc/support/conf/`.
5. Confirm the directories and files referenced in your `YourCAname.conf` file are present on Tenable Security Center in a subdirectory of `/opt/sc/support/conf/`.
6. Configure Tenable Security Center to trust your CA, as described in [Trust a Custom CA](#).

Tenable Security Center processes your CA.

7. In the command line interface (CLI), run the following command to enable the CRL in Tenable Security Center:

```
$ openssl ca -config <CA root configuration file directory> -gencrl -out
<crl parameter value in the YourCAname.conf file>
```

For example:



```
$ openssl ca -config /opt/sc/support/conf/ca-root.conf -gencrl -out /opt/sc/support/conf/crl/ca.crl
```

Tenable Security Center creates the CRL file.

8. In a text editor, open the `/opt/sc/support/conf/vhostssl.conf` file.
  - a. Add the following content at the end of the file:

```
SSLCARevocationCheck <value>  
SSLCARevocationFile "<filepath>"
```

Where `<value>` and `<filepath>` are:

Content	Description
<b>SSLCARevocationCheck &lt;value&gt;</b>	
chain	Tenable Security Center checks all certificates in a chain against the CRL.
leaf	Tenable Security Center checks only the end-entity certificate in a chain against the CRL.
<b>SSLCARevocationFile &lt;filepath&gt;</b>	
Specifies the file path for the CRL file in Tenable Security Center. For example, <code>/opt/sc/support/conf/crl/ca.crl</code> .	

- b. Save the file.

Tenable Security Center saves your configuration.

9. In the CLI, run the following command to create a symbolic link for the CRL file:

```
$ ln -s <crl parameter value in the YourCAname.conf file> `openssl crl -hash -noout -in <crl parameter value in the YourCAname.conf file>`.r0
```

For example:



```
$ ln -s /opt/sc/support/conf/crl/ca.crl `openssl crl -hash -noout -in /opt/sc/support/conf/crl/ca.crl` .r0
```

**Caution:** Do not use a single quote character (') instead of a backtick character (`); this command requires the backtick.

Tenable Security Center creates a symbolic link for the CRL file.

10. Restart Tenable Security Center, as described in [Start, Stop, or Restart Tenable Security Center](#).

Tenable Security Center restarts.



# Configure OCSP Validation in Tenable Security Center

**Required User Role:** Root user

You can configure Online Certificate Status Protocol (OCSP) validation in Tenable Security Center to prevent users from authenticating to Tenable Security Center if their certificate matches a revocation on your OCSP server.

**Note:** Tenable Support does not assist with OCSP configuration in Tenable Security Center.

Before you begin:

- Confirm that you have an OCSP server configured in your environment.

To configure OCSP validation in Tenable Security Center:

1. In a text editor, open the `/opt/sc/support/conf/sslverify.conf` file.
  - a. Set the **SSLVerifyClient** setting to **Require** or **Optional**, as described in [SSLVerifyClient](#).
  - b. Set the **SSLVerifyDepth** setting, as described in [SSLVerifyDepth](#).
  - c. Save the file.

Tenable Security Center saves your configuration.

2. In a text editor, open the `/opt/sc/support/conf/vhostssl.conf` file.
  - a. Add the following content at the end of the file:

```
SSLOCSPEnable on
SSLOCSPDefaultResponder <URI>
SSLOCSPOverrideResponder on
```

Where `<URI>` is the URI for your OCSP server.

- b. Save the file.

Tenable Security Center saves your configuration.

3. Restart Tenable Security Center, as described in [Start, Stop, or Restart Tenable Security](#)





[Center.](#)

Tenable Security Center restarts.



## Search

In Tenable Security Center, you can search for vulnerabilities by CVE ID using the search box in the top navigation bar. A list of suggestions appears after you type at least five characters.

Tenable Security Center saves your search history. To view your search history, click the search box. To delete an item from your search history, click the **X** icon next to the search term.

To view a search result, press **Enter** or click a suggestion in the drop-down box. The search results page appears, which displays widgets with details about the vulnerability:

Widget	Description
<b>Vulnerability Information</b>	<p>A list of solutions for the vulnerability that correspond to the plugins currently visible in the <b>Tenable Coverage</b> widget.</p> <p>The top right corner displays the Vulnerability Priority Rating (VPR) for the vulnerability. For more information about VPRs, see <a href="#">CVSS vs. VPR</a>.</p>
<b>VPR Key Drivers</b>	<p>Details about the history and severity of the vulnerability that contribute to the VPR.</p> <p>For more information about VPRs, see <a href="#">CVSS vs. VPR</a>.</p>
<b>Risk Information</b>	<p>Details about the risk associated with the vulnerability, as determined by the <a href="#">National Vulnerability Database (NVD)</a>.</p>
<b>Hosts Impacted</b>	<p>A list of assets in your system that are affected by the vulnerability. When you scan your network, any discovered assets that are affected by the vulnerability will appear in this list.</p> <p>If you have a Tenable Security Center+ license, this widget also displays the Asset Exposure Score (AES) and Asset Criticality Rating (ACR) for the assets.</p> <p>Click <b>More Details</b> to see the <b>IP Summary</b> page, where you can view the list of hosts filtered by the CVE ID.</p>
<b>CPEs</b>	<p>A list of CPE names that are relevant to the vulnerability.</p> <p>Click <b>More Details</b> to open a dialog box with the full list of CPEs.</p>



Widget	Description
<b>References</b>	<p>A list of links with information relevant to the vulnerability.</p> <p>Click <b>More Details</b> to open a dialog box with the full list of references.</p>
<b>Tenable Coverage</b>	<p>A list of <a href="#">Tenable plugins</a> that address the vulnerability. You can sort this list by plugin ID.</p> <p>When you sort plugins or navigate pages in the widget, the <b>Vulnerability Information</b> and <b>Related Links</b> widgets update to correspond to the visible plugins.</p> <p>Click <b>More Details</b> to see the <b>Vulnerability List</b> page, where you can view the list of plugins filtered by your assets. If none of the assets in your network are affected by the list of plugins, then this page will not display any plugins.</p>
<b>Related Links</b>	<p>A list of links with information relevant to the plugins currently visible in the <b>Tenable Coverage</b> widget.</p> <p>Click <b>More Details</b> to open a dialog box with the full list of related links.</p>



---

# Certificates and Certificate Authorities in Tenable Security Center

---

Tenable Security Center includes the following defaults:

- a default Tenable Security Center server certificate (`SecurityCenter.crt`)
- a Tenable Security Center certificate authority (CA), which signs `SecurityCenter.crt`
- a DigiCert High Assurance EV Root CA

However, you may want to upload your own CAs or certificates for advanced configurations or to resolve scanning issues. For more information, see:

- [Tenable Security Center Server Certificates](#)
- [Trust a Custom CA](#)
- [Certificate Authentication](#)
- [Custom Plugin Packages for NASL and CA Certificate Upload](#)
- [Manual Tenable Nessus SSL Certificate Exchange](#)



## Tenable Security Center Server Certificates

Tenable Security Center ships with a default Tenable Security Center server certificate and key: `SecurityCenter.crt` and `SecurityCenter.key`. In some cases, you must replace it or regenerate it.

If you replace the server certificate with a self-signed certificate, you may need to upload the CA for your server certificate to Tenable Nessus or your browser.

Problem	Solution
The default certificate for Tenable Security Center is untrusted.	Upload a certificate for the Tenable Security Center server, as described in <a href="#">Upload a Server Certificate for Tenable Security Center</a> .  If the new server certificate is self-signed, plugin 51192 may report that the Tenable Security Center server certificate is untrusted. To configure Tenable Nessus to trust the server certificate, upload the CA certificate to Tenable Nessus.
Your browser reports that the Tenable Security Center server certificate is untrusted.	Upload a CA certificate for the Tenable Security Center server certificate to your browser.
Plugin 51192 reports that the Tenable Security Center server certificate expired.	Regenerate the Tenable Security Center server certificate, as described in <a href="#">Regenerate the Tenable Security Center Server Certificate</a> .



# Upload a Server Certificate for Tenable Security Center

**Required User Role:** Root user

For information about Tenable Security Center server certificates, see [Tenable Security Center Server Certificates](#).

**Tip:** The custom certificate email address must not be SecurityCenter@SecurityCenter or subsequent upgrades cannot retain the new certificate.

Before you begin:

- Save your new server certificate and key files as `host.crt` and `host.key`.

To upload a server certificate for Tenable Security Center:

1. Log in to Tenable Security Center via the user interface.
2. Back up the existing `SecurityCenter.crt` and `SecurityCenter.key` files located in the `/opt/sc/support/conf` directory.

For example:

```
# cp /opt/sc/support/conf/SecurityCenter.crt /tmp/SecurityCenter.crt.bak
# cp /opt/sc/support/conf/SecurityCenter.key /tmp/SecurityCenter.key.bak
```

3. To rename the `host.crt` and `host.key` files and copy them to the `/opt/sc/support/conf` directory, run:

```
# cp host.crt /opt/sc/support/conf/SecurityCenter.crt
# cp host.key /opt/sc/support/conf/SecurityCenter.key
```

If prompted, type `y` to overwrite the existing files.

4. To confirm the files have the correct permissions (640) and ownership (tns), run:

```
# ls -l /opt/sc/support/conf/SecurityCenter.crt
-rw-r----- 1 tns tns 4389 May 15 15:12 SecurityCenter.crt
```



```
# ls -l /opt/sc/support/conf/SecurityCenter.key
-rw-r----- 1 tns tns 887 May 15 15:12 SecurityCenter.key
```

**Note:** If an intermediate certificate is required, it must also be copied to the system and given the correct permissions (640) and ownership (tns). Additionally, you must remove the # from the line in /opt/sc/support/conf/vhostssl.conf that begins with #SSLCertificateChainFile to enable the setting. Modify the path and filename to match the uploaded certificate.

If necessary, change the ownership or permissions.

- a. To change the ownership, run:

```
# chown tns:tns /opt/sc/support/conf/SecurityCenter.crt\
```

```
# chown tns:tns /opt/sc/support/conf/SecurityCenter.key
```

- b. To change the permissions, run:

```
# chmod 640 /opt/sc/support/conf/SecurityCenter.crt
# chmod 640 /opt/sc/support/conf/SecurityCenter.key
```

5. Restart the Tenable Security Center service:

```
# service SecurityCenter restart
```

6. In a browser, log in to the Tenable Security Center user interface as a user with administrator permissions.
7. When prompted, verify the new certificate details.

What to do next:

- If you uploaded a self-signed server certificate and plugin 51192 reports that the CA for your self-signed certificate is untrusted, upload the custom CA certificate to Tenable Nessus.



# Regenerate the Tenable Security Center Server Certificate

**Required User Role:** tns user

**Required User Role:** Root user

Tenable Security Center ships with a default server certificate that is valid for two years. After the certificate expires, you must regenerate the SSL certificate.

To regenerate the Tenable Security Center SSL certificate:

1. Log in to Tenable Security Center via the command line interface (CLI).
2. In the CLI in Tenable Security Center, run the following command to switch to the tns user:

```
su - tns
```

3. As the tns user, run the following command:

```
/opt/sc/support/bin/php /opt/sc/src/tools/installSSLCertificate.php
```

(Optional) If you want to suppress the self-signed warning or specify a Common Name, include an optional argument.

Argument	Description
-q	Suppresses the warning: This script generates a self-signed SSL certificate, which is not recommended for production.
-h <IP/host name>	Specifies an IP address or hostname that will be used as the Common Name for the certificate.

Tenable Security Center generates a new certificate.

4. Run the following command to exit the tns user:

```
exit
```





5. As the root user, run the following command to restart the Tenable Security Center service:

```
# service SecurityCenter restart
```

The service restarts and Tenable Security Center applies the new certificate.



## Trust a Custom CA

**Required User Role:** tns user

You can configure Tenable Security Center to trust a custom CA for certificate authentication or other uses.

To configure Tenable Security Center to trust a custom CA:

1. Log in to Tenable Security Center via the user interface.
2. Copy the required PEM-encoded CA certificate (and intermediate CA certificate, if needed) to the Tenable Security Center server's /tmp directory.

In this example, the file is named ROOTCA2.cer.

3. Run the installCA.php script to create the required files for each CA in /opt/sc/data/CA:

```
# /opt/sc/support/bin/php /opt/sc/src/tools/installCA.php /tmp/ROOTCA2.cer
```

Tenable Security Center processes all the CAs in the file.

4. Restart Tenable Security Center, as described in [Start, Stop, or Restart Tenable Security Center](#).



---

## System Settings

---

The **System** menu in the left navigation and the **Username** menus in the top navigation bar contain several options to configure Tenable Security Center system settings. Administrator users can configure more options than organizational users.

- [Configuration Settings](#)
- [Tenable Lumin Data](#)
- [Diagnostics Settings](#)
- [Job Queue Events](#)
- [System Logs](#)
- [Publishing Sites Settings](#)
- [Keys Settings](#)
- [User Profile Menu Settings](#)



# Configuration Settings

The configuration menu includes the following settings:

- [Data Expiration Settings](#)
- [External Schedules Settings](#)
- [Tenable Lumin Settings](#)
- [Mail Settings](#)
- [Miscellaneous Settings](#)
- [License Settings](#)
- [Plugins/Feed Settings](#)
- [SAML Settings](#)
- [Security Settings](#)

## Data Expiration Settings

Data expiration determines how long Tenable Security Center retains closed tickets, scan results, and report results.

Option	Description
<b>User Generated Object Lifetime</b>	
<b>Closed Tickets</b>	The number of days you want Tenable Security Center to retain closed tickets. The default value of this option is 365 days.
<b>Scan Results</b>	The number of days you want Tenable Security Center to retain scan results. The default value of this option is 365 days.
<b>Report Results</b>	The number of days you want Tenable Security Center to retain report results. The default value of this option is 365 days.

**Tip:** You can configure vulnerability data expiration for individual IPv4, IPv6, agent, and universal repositories. For more information, see [IPv4/IPv6 Repositories](#), [Agent Repositories](#), and [Universal Repositories](#).



## External Schedules Settings

The Tenable Security Center external schedule settings determine the update schedule for the common tasks of pulling Tenable Nessus Network Monitor data, IDS signature updates, and IDS correlation updates.

Option	Description
<b>Tenable Nessus Network Monitor</b>	
<b>Pull Interval</b>	This option configures the interval that Tenable Security Center uses to pull results from the attached Tenable Nessus Network Monitor instances. The default setting is 1 hour. The timing is based from the start of the Tenable Security Center service on the host system.
<b>Tenable Log Correlation Engine</b>	
<b>IDS Signatures</b>	Specifies the frequency to update Tenable Security Center IDS signatures via third-party sources. The schedule appears along with the specified time zone.
<b>IDS Correlation Databases</b>	Specifies the frequency to push vulnerability information to the Log Correlation Engine for correlation. The schedule appears along with the specified time zone.

You can also configure each of the update schedule times to occur by time in a particular time zone using the **Time Zone** link next to each hour selection.

## Tenable Lumin Settings

If you have a Tenable Vulnerability Management license to use Tenable Lumin with Tenable Security Center, you can configure your Tenable Security Center data to synchronize to Tenable Vulnerability Management for Tenable Lumin analysis.

For more information, see [Tenable Lumin Synchronization](#).

## Mail Settings

The **Mail** option designates SMTP settings for all email-related Tenable Security Center functions. Available options include SMTP host, port, authentication method, encryption, and return address.



In addition, you can use the **Test SMTP Settings** in the upper left corner of the page to validate the settings.

**Note:** The **Return Address** defaults to *noreply@localhost*. Use a valid return email address for this option. If this option is empty or the email server requires emails from valid accounts, the email server cannot send the email.

**Note:** Type the **Username** in a format supported by your SMTP server (for example, *username@domain.com* or *domain\username*).

## Miscellaneous Settings

The **Miscellaneous Configuration** section offers options to configure settings for web proxy, syslog, notifications, and enable or disable some report types.

### Web Proxy

From this configuration page, you can configure a web proxy by entering the host URL (proxy host-name or IP address), port, authentication type, username, and password. The hostname used must resolve properly from the Tenable Security Center host.

### Syslog

In the **Syslog** section, you can configure options to allow Tenable Security Center to send log events to the local syslog service.

Option	Description
<b>Enable Forwarding</b>	Enables log forwarding options.
<b>Facility</b>	Type the facility you want to receive the log messages.
<b>Severity</b>	Specifies which syslog message levels you want to forward: <b>Informational</b> , <b>Warning</b> , or <b>Critical</b> .

### Scanning



The **IP Randomization** option specifies how you want Tenable Security Center to send active scan target lists to Tenable Nessus and Tenable Vulnerability Management scanners.

You enable or disable IP randomization for all configured active scans; you cannot configure IP randomization on a per-scan basis.

- When enabled, Tenable Security Center randomizes the targets in the active scan before sending the target list to the scanners to reduce strain on network devices during large active scans.

Scan	Randomization
1,000 or fewer targets	Tenable Security Center randomizes all the IP addresses in the target list.
1,001 or more targets	Tenable Security Center randomizes all the IP addresses in the target list by: <ol style="list-style-type: none"><li>1. Ordering the IP addresses numerically and splitting them into 100 groups.</li><li>2. Randomly selecting a group and choosing the lowest IP address from that group.</li><li>3. Selecting groups and IP addresses until all IP addresses in all groups are randomized in the target list.</li></ol>

If the active scan includes a Tenable Vulnerability Management scanner, Tenable Security Center breaks the target list into smaller lists (256 IP addresses each) before sending to Tenable Vulnerability Management.

**Note:** Some randomized target lists (such as small target lists) may still contain sequences of increasing IP addresses. This is a possible outcome of randomization, not an indication that randomization failed.

- When disabled, Tenable Security Center organizes the target list by increasing IP address. Then, scanners scan targets, starting with the lowest IP address and finishing with the highest IP address.



**Tip:** The **Max simultaneous hosts per scan** scan policy option specifies how many IP addresses Tenable Security Center sends to each scanner at a time. For more information, see [Scan Policy Options](#).

## Notifications

The **Notifications** section defines the Tenable Security Center web address used when alerts and tickets generate notifications.

## Report Generation

If your organization requires specialized reporting formats, such as DISA or CyberScope, you can enable **Report Generation** options based on your organization's needs.

- Defense Information Systems Agency (DISA) reporting standards include the Assessment Summary Results (ASR), Assessment Results Format (ARF), and Consolidated Assessment Results Format (CARF) styles.
- CyberScope reports utilize Lightweight Asset Summary Results Schema (LASR) style reports, which are used by some segments of governments and industry.

To allow users to choose these reports during report creation, you must enable the corresponding toggles. For more information about reports in Tenable Security Center, see [Reports](#).

Option	Description
<b>Enable DISA ARF</b>	Enable the DISA ARF report format, which meets the standards of the Defense Information Systems Agency Assessment Results Format.
<b>Enable DISA Consolidated ARF</b>	Enable the DISA consolidated ARF report format, which meets the standards of the Defense Information Systems Agency Consolidated Assessment Results Format.
<b>Enable DISA ASR</b>	Enable the DISA ASR report format, which meets the standards of the Defense Information Systems Agency Assessment Summary Results.
<b>Enable CyberScope</b>	Enable the CyberScope report format, which meets CyberScope reporting standards to support FISMA compliance.

## Risk Rule Comments





You can enable the **Recast and Accept Risk Rule Comments** option to display accept risk rule comments and recast risk rule comments in reports and vulnerability analysis views.

For more information about recast risk rules and accept risk rules, see [Recast Risk Rules](#) and [Accept Risk Rules](#).

For more information about vulnerability analysis views, see [View Vulnerability Instance Details](#) and [View Vulnerabilities by Plugin](#).

## Privacy

The **Enable Usage Statistics** option specifies whether Tenable collects anonymous telemetry data about your Tenable Security Center deployment.

When enabled, Tenable collects usage statistics that cannot be attributed to a specific user or customer. Tenable does not collect personal data or personally identifying information (PII).

Usage statistics include, but are not limited to, data about your visited pages, your used reports and dashboards, your Tenable Security Center license, and your configured features. Tenable uses the data to improve your user experience in future Tenable Security Center releases. You can disable this option at any time to stop sharing usage statistics with Tenable.

After you enable or disable this option, all Tenable Security Center users must refresh their browser window for the changes to take effect.

## License Settings

The **License Configuration** section allows you to configure licensing and activation code settings for Tenable Security Center and all attached Tenable products.

For information about the Tenable Security Center license count, see [License Requirements](#). To add or update a license, see [Apply a New License](#) or [Update an Existing License](#).

## Plugins/Feed Settings

The Plugins/Feed Configuration page displays the **Plugin Detail Locale** for Tenable Security Center and the feed and plugin update (scanner update) schedules.

For more information, see [Edit Plugin and Feed Settings and Schedules](#).



Update	Description
<b>Tenable Security Center Feed</b>	Retrieves the latest Tenable Security Center feed from Tenable. This feed includes data for general use, including templates (for example, dashboards, ARCs, reports, policies, assets, and audit files), template-required objects, some general plugin information, and updated VPR values.
<b>Active Plugins</b>	Retrieves the latest active plugins feed (for Tenable Nessus and Tenable Vulnerability Management scanners) from Tenable. Tenable Security Center pushes the feed to Tenable Nessus and Tenable Vulnerability Management scanners.
<b>Passive Plugins</b>	Retrieves the latest passive plugins feed from Tenable. Tenable Security Center pushes the feed to Tenable Nessus Network Monitor instances.
<b>Event Plugins</b>	Retrieves the latest event plugins feed from Tenable. Tenable Security Center uses the feed locally with Log Correlation Engine data but does not push the feed to Log Correlation Engine; Log Correlation Engine retrieves the feed directly from Tenable.

For information about Tenable Security Center-Tenable plugins server communications encryption, see [Encryption Strength](#).

## Plugin Detail Locale

The local language plugin feature allows you to display portions of plugin data in local languages. When available, translated text displays on all pages where plugin details appear.

Select **Default** to display plugin data in English.

**Note:** Tenable Security Center cannot translate text within custom files. Upload a translated **Active Plugins**.xml file to display the file content in a local language.

For more information, see [Configure Plugin Text Translation](#).

## Schedules

Tenable Security Center automatically updates Tenable Security Center feeds, active plugins, passive plugins, and event plugins. If you upload a custom feed or plugin file, the system merges the custom file data with the data contained in the associated automatically updating feed or plugin.

You can upload tar .gz files with a maximum size of 1500 MB.



For more information, see [Edit Plugin and Feed Settings and Schedules](#).

## Tenable Security Center Software Updates

New updates and patches for Tenable Security Center appear in the **Tenable Security Center Software Updates** section of the **Plugins/Feed Configuration** page.

If you enable the **Enable Software Updates Through the Tenable Security Center Feed** option, then Tenable Security Center automatically applies Tenable Security Center patches during feed updates.

**Note:** Some patches cannot be applied through the feed, and must be installed manually.

## SAML Settings


Use the SAML section to configure SAML 2.0-based SAML authentication (for example, Okta, OneLogin, Shibboleth 2.0, etc.) for Tenable Security Center users. For more information, see [SAML Authentication](#).

## Security Settings


Use the Security section to define the Tenable Security Center user interface login parameters and options for account logins. You can also configure banners, headers, and classification headers and footers.

Option	Description
<b>Authentication Settings</b>	
<b>Session Timeout</b>	The web session timeout in minutes (default: 60).
<b>Maximum Login Attempts</b>	The maximum number of user login attempts Tenable Security Center allows before locking out the account (default: 20). To disable this feature, set the value to 0.
<b>Minimum Password Length</b>	This setting defines the minimum number of characters for passwords of accounts created using the local TNS authentication access (default: 3).
<b>Password Com-</b>	When enabled, user passwords must be at least 4 characters long and



Option	Description
<b>plexity</b>	<p>contain at least one of each of the following:</p> <ul style="list-style-type: none"><li>• An uppercase letter</li><li>• A lowercase letter</li><li>• A numerical character</li><li>• A special character</li></ul> <div data-bbox="488 604 1479 758"><p><b>Note:</b> After you enable <b>Password Complexity</b>, Tenable Security Center prompts all users to reset their passwords the next time they log in to Tenable Security Center.</p></div> <div data-bbox="488 779 1479 932"><p><b>Note:</b> If you enable <b>Password Complexity</b> and set the <b>Minimum Password Length</b> to a value greater than 4, Tenable Security Center enforces the longer password requirement.</p></div>
<b>Startup Banner Text</b>	Type the text banner that appears before to the login interface.
<b>User Text</b>	Adds custom text to the bottom of the user profile menu. You can use the text to identify a company, group, or other organizational information (maximum 128 characters).
<b>Classification Type</b>	<p>Adds a header and footer banner to Tenable Security Center to indicate the classification of the data accessible via the software. Current options are <b>None</b>, <b>Unclassified</b>, <b>Confidential</b>, <b>Secret</b>, <b>Top Secret</b>, and <b>Top Secret – No Foreign</b>.</p> <p>Sample header:</p> <div data-bbox="488 1524 1078 1587"></div> <p>Sample footer:</p>



Option	Description
	<div data-bbox="483 264 1078 354"><p>CONFIDENTIAL / FOR OFFICIAL USE ONLY</p></div> <div data-bbox="488 422 1479 575"><p><b>Note:</b> If you set <b>Classification Type</b> to an option other than <b>None</b>, users can only see the plain report styles. The Tenable report styles do not support the classification banners.</p></div>
<b>Allow API Keys</b>	When enabled, allows users to generate API keys as an authentication method for Tenable Security Center API requests. For more information, see <a href="#">Enable API Key Authentication</a> .
<b>Allow Session Management</b>	This setting is disabled by default. When enabled, the <b>Session Limit</b> option appears. This feature displays the option that allows administrators to set a session limit for all users.
<b>Disable Inactive Users</b>	When enabled, Tenable Security Center disables user accounts after a set period of inactivity. You cannot use a disabled user account to log in to Tenable Security Center, but other users can use and manage objects owned by the disabled user account.
<b>Days Users Remain Enabled</b>	When you enable <b>Disable Inactive Users</b> , specify the number of inactive days you want to allow before automatically disabling a user account.
<b>Session Limit</b>	<p>Specifies the maximum number of sessions a user can have open at once.</p> <p>If you log in and the session limit has already been reached, Tenable Security Center notifies you that the oldest session with that username will be logged out automatically. You can cancel the login or proceed with the login and end the oldest session.</p> <div data-bbox="488 1640 1479 1793"><p><b>Note:</b> This behavior is different for Common Access Cards (CAC) logins. Tenable Security Center does not check active sessions for CAC authentication.</p></div>



Option	Description
<b>Login Notifications</b>	Sends notifications for each time a user logs in.
<b>WebSeal</b>	<p>Allows you to enable or disable WebSEAL. WebSEAL supports multiple authentication methods, provides Security Access Authorization service, and single sign-on capabilities.</p> <div data-bbox="488 485 1479 716" style="border: 1px solid red; padding: 5px;"><p><b>Caution:</b> Before the user that enabled WebSEAL logs out of Tenable Security Center, Tenable Security Center strongly recommends confirming, in a separate session, that at least one user (preferably an administrator user) is able to log in successfully via WebSEAL. Otherwise, if there is an issue, no one will be able to access Tenable Security Center to turn off WebSEAL.</p></div> <div data-bbox="488 743 1479 936" style="border: 1px solid red; padding: 5px;"><p><b>Caution:</b> Any user created while WebSEAL is enabled will not have a password. An administrator must update the user account to establish a password. Any user that existed before enabling WebSEAL must revert to their old password.</p></div>
<b>PHP Serialization</b>	
<b>Operational Status</b>	Summarizes your current setting.
<b>PHP Serialization Mode</b>	<p>Specifies whether you want to allow or prevent PHP serialization in Tenable Security Center.</p> <ul style="list-style-type: none"><li>• <b>PHP Serialization ON</b> —Tenable Security Center performs PHP serialization and Tenable Security Center features operate as expected.</li><li>• <b>PHP Serialization OFF</b> —Tenable Security Center does not perform PHP serialization and prevents users from importing or exporting the following objects.<ul style="list-style-type: none"><li>• Assets</li><li>• Scan policies</li><li>• Assurance Report Cards</li><li>• Reports</li></ul></li></ul>



Option	Description
	<ul style="list-style-type: none"><li data-bbox="613 247 786 279">• Audit files</li><li data-bbox="613 317 808 348">• Dashboards</li></ul>
<b>Scanners</b>	
<b>Picture in Picture</b>	<p data-bbox="483 468 1490 600">When enabled, allows administrators to view and manage Tenable Nessus scanner configurations from the Tenable Security Center user interface. For more information, see <a href="#">Enable Picture in Picture</a>.</p> <div data-bbox="488 632 1479 825" style="border: 1px solid blue; padding: 5px;"><p data-bbox="514 653 1437 804"><b>Note:</b> You cannot use <b>Picture in Picture</b> with a Tenable Nessus scanner if you enabled <b>Use Proxy</b> for the scanner or if the scanner's <b>Authentication Type</b> is <b>SSL Certificate</b>. For more information, see <a href="#">Tenable Nessus Scanner Settings</a>.</p></div>
<b>FIPS 140-2 Configuration</b>	
<b>Operational Status</b>	Summarizes whether FIPS 140-2 mode is currently enabled or disabled.
<b>FIPS 140-2 Mode</b>	Specifies whether you want to enable or disable FIPS mode for communication. Switching from one mode to the other requires a restart. For more information, see <a href="#">Start, Stop, or Restart Tenable Security Center</a> .



## Edit Plugin and Feed Settings and Schedules

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information, see [Configuration Settings](#).

To view and edit plugin and feed settings and schedules as an administrator user:

1. Log in to Tenable Security Center via the user interface.
2. In the left navigation, click **System > Configuration**.

The **Configuration** page appears.


3. Click the **Plugins/Feed** tile.

The **Plugins/Feed Configuration** page appears.

4. View the **Plugin Detail Locale** section to see the local language configured for Tenable Security Center.
5. Expand the **Schedules** section to show the settings for the **Tenable.sc Feed**, **Active Plugins**, **Passive Plugins**, or **Event Plugins** schedule.
6. If you want to update a plugin or feed on demand, click **Update**. You cannot update feeds with invalid activation codes.
7. If you want to upload a custom feed file, click **Choose File**.
8. Click **Submit**.

Tenable Security Center saves your configuration.

To view and edit plugin and feed settings and schedules as an organizational user:

1. Log in to Tenable Security Center via the user interface.
2. In the top navigation bar, click your user profile  icon > **Feeds**.

The **Plugins/Feed Configuration** page appears.





3. View the **Plugin Detail Locale** section to see the local language configured for Tenable Security Center.
4. Expand the **Schedules** section to show the settings for the **Tenable.sc Feed**, **Active Plugins**, **Passive Plugins**, or **Event Plugins** schedule.
5. If you want to update a plugin or feed on demand, click **Update**. You cannot update feeds with invalid activation codes.
6. If you want to upload a custom feed file, click **Choose File**.
7. Click **Submit**.

Tenable Security Center saves your configuration.



# Configure Plugin Text Translation

**Required User Role:** Administrator

For more information, see [Configuration Settings](#).

To configure plugin text translation:

1. Log in to Tenable Security Center via the user interface.

2. In the left navigation, click **System > Configuration**.

The **Configuration** page appears.

3. Click the **Plugins/Feed** tile.

The **Plugins/Feed Configuration** page appears.

4. If you want plugin text to display in a local language, select a language from the **Locale List** box.

5. Click **Apply**.

Tenable Security Center saves your configuration.

6. In the **Schedules** section, in the **Active Plugins** row, click **Update**.

Tenable Security Center updates active plugins to obtain available translations.



---

## API Key Authentication

---

You can enable API key authentication to allow users to use API keys as an authentication method for Tenable Security Center API requests. Without API keys, users must use the /token endpoint to log in to the Tenable Security Center API and establish a token for subsequent requests, as described in [Token](#) in the *Tenable Security Center API Guide*.

Tenable Security Center attributes actions performed with API keys to the user account associated with the API keys. You can only perform actions allowed by the privileges granted to the user account associated with the API keys.

You can enable the **Allow API Keys** toggle in your Security Settings to allow users to perform API key authentication. Then, users can generate API keys for themselves or for other users. API keys include an access key and secret key that must be used together for API key authentication. For more information, see [Enable API Key Authentication](#) and [Generate API Keys](#).

A user can use API keys for Tenable Security Center API request authentication by including the **x-apikey** header element in your HTTP request messages, as described in [API Key Authorization](#) in the *Tenable Security Center API Best Practices Guide*.

Deleting API keys prevents users from authenticating Tenable Security Center API requests with the deleted keys. For more information, see [Delete API Keys](#).

For more information about the Tenable Security Center API, see the [Tenable Security Center API Guide](#) and the [Tenable Security Center API Best Practices Guide](#).



## Enable API Key Authentication

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

You can enable API key authentication to allow users to use API keys as an authentication method for Tenable Security Center API requests. For more information, see [API Key Authentication](#).

To allow users to authenticate to the Tenable Security Center API using API keys:

1. Log in to Tenable Security Center via the user interface.
2. In the left navigation, click **System > Configuration**.

The **Configuration** page appears.

3. Click the **Security** tile.

The **Security Configuration** page appears.

4. In the **Authentication Settings** section, click **Allow API Keys** to enable the toggle.
5. Click **Submit**.

Tenable Security Center saves your configuration.

What to do next:

- Generate API keys for a user, as described in [Generate API Keys](#).



## Disable API Key Authentication

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

**Caution:** Disabling API keys prevents users from authenticating API requests with API keys. Disabling API keys does not delete existing API keys. If you re-enable API keys, Tenable Security Center reauthorizes any API keys they were active before you disabled API key authentication.

For more information, see [API Key Authentication](#).

To disable API key authentication:

1. Log in to Tenable Security Center via the user interface.
2. In the left navigation, click **System > Configuration**.

The **Configuration** page appears.

3. Click the **Security** tile.

The **Security Configuration** page appears.

4. In the **Authentication Settings** section, click **Allow API Keys** to disable the toggle.
5. Click **Submit**.

Tenable Security Center saves your configuration.



## Enable Picture in Picture

**Required User Role:** Administrator

You can enable **Picture in Picture** to allow administrators to view and manage Tenable Nessus scanner configurations from the Tenable Security Center user interface.

**Note:** You cannot use **Picture in Picture** with a Tenable Nessus scanner if you enabled **Use Proxy** for the scanner or if the scanner's **Authentication Type** is **SSL Certificate**. For more information, see [Tenable Nessus Scanner Settings](#).

To enable **Picture in Picture**:

1. Log in to Tenable Security Center via the user interface.
2. Click **System > Configuration**.

The **Configuration** page appears.

3. Click the **Security** tile.

The **Security Configuration** page appears.

4. In the **Scanners** section, click **Picture in Picture** to enable the toggle.
5. Click **Submit**.

Tenable Security Center saves your configuration.

What to do next:

- View and manage your Tenable Nessus instances in Tenable Security Center, as described in [View Tenable Nessus Instances in Tenable Security Center](#).



---

## Disable Picture in Picture

---

**Required User Role:** Administrator

For more information, see [Tenable Nessus Scanners](#).

To disable **Picture in Picture**:

1. Log in to Tenable Security Center via the user interface.
2. Click **System > Configuration**.  
The **Configuration** page appears.
3. Click the **Security** tile.  
The **Security Configuration** page appears.
4. In the **Scanners** section, click **Picture in Picture** to disable the toggle.
5. Click **Submit**.

Tenable Security Center saves your configuration.



---

## Tenable Lumin Data

---

After you configure Tenable Security Center data synchronization to Tenable Lumin in Tenable Vulnerability Management, you can monitor information about your Tenable Lumin metrics and past synchronizations. For general information about Tenable Lumin synchronization, see [Configure Tenable Lumin Synchronization](#).

Tenable Security Center retrieves your latest Cyber Exposure Score (CES), Assessment Maturity grade, and Remediation Maturity grade daily from Tenable Lumin in Tenable Vulnerability Management. For more information about the metrics and timing, see [View Tenable Lumin Metrics](#).

Tenable Security Center logs all Tenable Lumin synchronization activity. For more information about the log contents, see [View Tenable Lumin Data Synchronization Logs](#).





## View Tenable Lumin Metrics

**Required Additional License:** Tenable Lumin

**Required User Role:** Administrator

After you configure Tenable Security Center data synchronization to Tenable Lumin in Tenable Vulnerability Management, you can view information about your Tenable Lumin metrics.

Every day at 11:00 PM UTC, Tenable Security Center retrieves data from Tenable Lumin in Tenable Vulnerability Management.

**Note:** Newly transferred data does not immediately impact your Tenable Lumin metrics (for example, your CES). Tenable requires up to 48 hours to recalculate your metrics. Recalculated metrics appear in Tenable Security Center after the next daily retrieval.

For more information, see [How long does synchronization take to complete?](#)

**Tip:** To view all Tenable Lumin data and take advantage of full Tenable Lumin functionality, see [Get Started with Tenable Lumin](#) in the *Tenable Vulnerability Management User Guide*.

To view Tenable Lumin metrics in Tenable Security Center:

1. Log in to Tenable Security Center via the user interface.
2. To view your Cyber Exposure Score, Assessment Maturity grade, and Remediation Maturity grade, do the following:

- a. In the left navigation, click **System > Tenable Lumin Data**.

The **Tenable Lumin Data** page appears.

- b. In the **Metrics** section, view data about your Tenable Lumin metrics.
  - An updated [Cyber Exposure Score](#) (CES) for the data you synchronized to Tenable Lumin. High CES values indicate higher risk.
  - An updated [Assessment Maturity](#) grade for the data you synchronized to Tenable Lumin. A high grade indicates you are assessing your assets frequently and



thoroughly.

- An updated [Remediation Maturity](#) grade for the data you synchronized to Tenable Lumin. A high grade indicates you are remediating the vulnerabilities on your assets quickly and thoroughly.

If a metric changed since the last retrieval, Tenable Security Center identifies if the value increased (⬆️) or decreased (⬇️).

**Tip:** If you performed an initial synchronization, Tenable requires up to 48 hours to calculate your Tenable Lumin metrics. Then, metrics appear in Tenable Security Center after the next daily retrieval.

For more information, see [How long does synchronization take to complete?](#)

3. (Requires Tenable Security Center+ license) To view the Asset Criticality Rating for a host, view details for the host, as described in [View Hosts](#). For more information, see [Asset Criticality Rating](#) in the *Tenable Vulnerability Management User Guide*.
4. (Requires Tenable Security Center+ license) To view the Asset Exposure Score for a host, view details for the host, as described in [View Hosts](#). For more information, see [Asset Exposure Score](#) in the *Tenable Vulnerability Management User Guide*.



## View Tenable Lumin Data Synchronization Logs

**Required Additional License:** Tenable Lumin

**Required User Role:** Administrator

After you configure Tenable Security Center data synchronization to Tenable Lumin in Tenable Vulnerability Management, you can view the logs for past synchronizations.

For information about monitoring Tenable Lumin synchronization status, see [View Tenable Lumin Synchronization Status](#).

To view Tenable Lumin synchronization logs:

1. Log in to Tenable Security Center via the user interface.
2. In the left navigation, click **System > Tenable Lumin Data**.

The **Tenable Lumin Data** page appears.



3. In the **History** section, view data about your logged activity.

Column	Description
Timestamp	The date and time of the logged activity.
Object Type	The synchronization data type: <b>asset</b> or <b>repository</b> .
Sync Type	The repository or asset synchronization type: <ul style="list-style-type: none"><li>• <b>Cumulative</b> repository synchronization —The initial synchronization of this repository, which included all cumulative database data from the repository.</li><li>• <b>Active</b> repository synchronization —A subsequent synchronization of this repository, which included only the new or modified scan result data imported to the repository.</li><li>• <b>Static</b> asset —A synchronization of <a href="#">Static Assets</a>.</li><li>• <b>Dynamic</b> asset —A synchronization of <a href="#">Dynamic Assets</a>.</li><li>• <b>Unknown</b> —Indicates an error occurred.</li></ul>
Object ID	The repository ID or asset ID. To locate the ID for an object, see <a href="#">View Repository Details</a> or <a href="#">View Asset Details</a> .
Transfer Duration	For repository or asset synchronizations, the length of time it took Tenable Security Center to transfer your repository or asset data to Tenable Vulnerability Management. <div style="border: 1px solid #0070C0; padding: 5px;"><b>Note:</b> The transfer duration does not include the time required for all data and recalculated metrics to appear in Tenable Lumin. For more information, see <a href="#">How long does synchronization take to complete?</a></div>
Status	The status of the repository or asset synchronization: <ul style="list-style-type: none"><li>• <b>Error</b> —Tenable Security Center failed to transfer your data to Tenable Vulnerability Management.</li></ul>



Column	Description
	<ul style="list-style-type: none"><li>• <b>Synchronized</b> —Tenable Security Center successfully transferred your data to Tenable Vulnerability Management, but all data and recalculated metrics are not yet visible in Tenable Lumin.</li><li>• <b>Visible in Tenable Lumin</b> —Tenable Security Center successfully transferred your data to Tenable Vulnerability Management and all data and recalculated metrics are visible in Tenable Lumin.</li></ul> <p>For more information about the time required for all data and recalculated metrics to appear in Tenable Lumin, see <a href="#">How long does synchronization take to complete?</a></p>

4. To view additional details about your logged activity, click a row in the table.

Column	Description
Repository or asset <b>Message</b>	A message explaining the reason for the synchronization <b>Error</b> status.
Repository or asset <b>Organization ID</b>	The organization ID. To locate the ID for an organization, see <a href="#">View Organization Details</a> .
Repository <b>Scan Result ID</b>	The scan result ID. To locate the ID for a scan result, see <a href="#">View Scan Result Details</a> .



## Edit an ACR Manually

**Required License:** Tenable Security Center+

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can customize an individual host's Asset Criticality Rating (ACR) value to reflect the unique infrastructure or needs of your organization.

For more information about ACR values, see [Asset Criticality Rating](#) in the *Tenable Vulnerability Management User Guide*.

**Tip:** If you want to edit the ACR for a host you imported using a remote repository or by connecting a managed Tenable Security Center instance to Tenable Security Center Director, log in to the Tenable Security Center instance that contains the host's data.

**Tip:** Changes to an ACR value (and recalculations for your ACR values) take effect within 24 hours.

To edit the ACR for a host:

1. Log in to Tenable Security Center via the user interface.
2. Click **Assets > Host Assets**.

The **Host Assets** page appears.

3. Click the row for the host.

The **Host Asset Details** page appears.

4. In the **Asset Criticality Rating** section, click the  button.

The **Edit Asset Criticality Rating** plane appears.

5. Do one of the following:

- To modify the ACR value, click the Asset Criticality Rating slider to increase or decrease the ACR.



- To reset an existing ACR value to the Tenable-provided ACR value, click **Reset to Tenable ACR**.
6. In the **Overwrite Reasoning** section, select one or more options to include a justification for your ACR change. For example, if a host in your development lab environment received a Tenable-assigned ACR appropriate for a public host but not the development host, you can select **Dev Only**. If you modify the ACR from the Tenable-provided value, this option is required.
  7. In the **Notes** box, type a note about your ACR change. If you select **Other** in the **Overwrite Reasoning** section, you must type a note for the change.
  8. Click **Submit**.

Tenable Security Center saves the ACR.

What to do next:

- View the ACR for each host, as described in [View Hosts](#).



## Diagnostics Settings

This page displays and creates information that assists in troubleshooting issues that may arise while using Tenable Security Center.

### System Status

You can use this section to view the current status of system functions.

System Function	Description
Correct Java Version	Indicates whether the minimum version of Java required to support Tenable Security Center functionality is installed.  For more information, see <a href="#">Before You Upgrade</a> .
Sufficient Disk Space	Indicates whether you have enough disk space to support Tenable Security Center functionality. A red X indicates the disk is at 95% capacity or higher.  For more information, see <a href="#">Hardware Requirements</a> .
Correct RPM Package Installed	Indicates whether you have the correct Tenable Security Center RPM installed for your operating system.  For more information, see <a href="#">System Requirements</a> .
Debugging	Indicates whether debugging is enabled. You may experience performance and storage issues if you leave debugging enabled for extended periods of time.  For more information, see <a href="#">Debugging Logs</a> .
Migration Errors	Indicates whether an error occurred during a recent Tenable Security Center update.
PHP Integrity Errors	Indicates whether any PHP files have been modified from the original version included in the Tenable Security Center RPM.

### Diagnostics File





You can use this section to generate a diagnostics file for troubleshooting with Tenable Support. For more information, see [Generate a Diagnostics File](#).

## Debugging Logs

You can use this section to enable or disable debugging logs for troubleshooting with Tenable Support. For more information, see [Enable Debugging Logs](#) and [Disable Debugging Logs](#).

**Note:** Tenable does not recommend leaving debugging enabled on Tenable Security Center after you send the log files to Tenable Support. You may experience performance and storage issues if you leave debugging enabled for extended periods of time.



## Generate a Diagnostics File

**Required User Role:** Administrator

Tenable Support may ask you to generate a diagnostics file to assist with troubleshooting. The `debug.zip` diagnostics file contains files related to the selected chapters. For more information about diagnostics file options, see [Diagnostics File Options](#).

For more information about Tenable Security Center diagnostics, see [Diagnostics Settings](#).

To generate a diagnostics file for Tenable Support:

1. Log in to Tenable Security Center via the user interface.
2. In the left navigation, click **System > Diagnostics**.

The **Diagnostics** page appears.

3. In the **Diagnostics File** section, click **Create Diagnostics File**.

The page updates with options to configure the diagnostics file.

4. In the **General** section, if you want to omit IP addresses from the diagnostics file, click to enable the **Strip IPs from Chapters** toggle.
5. In the **Chapters** section, click the toggles to enable or disable the chapters you want to include in the diagnostics file.
6. Click **Generate File**.

Tenable Security Center generates the diagnostics file.

7. Click **Download Diagnostics File**.

The `debug.zip` file downloads.

What to do next:

- Share the `debug.zip` file with Tenable Support for troubleshooting.



## Diagnostics File Options

For more information, see [Diagnostics Settings](#) and [Generate a Diagnostics File](#).

Option	Description	Default
<b>General</b>		
<b>Strip IPs from Chapters</b>	<p>When enabled, Tenable Security Center omits IP addresses from the following files:</p> <ul style="list-style-type: none"><li>• <code>sc-configuration.txt</code></li><li>• <code>sc-scans.txt</code></li><li>• <code>sc-setup.txt</code></li><li>• <code>sc-logs.txt</code></li><li>• <code>sc-error.log</code></li><li>• <code>cert.log</code></li><li>• <code>install.log</code></li><li>• <code>upgrade.log</code></li><li>• <code>schemaUpdates*.log</code></li><li>• <code>sc-environment.txt</code></li><li>• <code>sc-telemetry.txt</code></li><li>• <code>/opt/sc/support/error_Log</code></li><li>• <code>/opt/sc/support/*.conf</code></li></ul>	Disabled
<b>Chapters</b>		
<b>System Information</b>	Include information about the Tenable Security Center host system in the diagnostic file ( <code>sc-systeminfo.txt</code> ).	Enabled
<b>Scan Information</b>	Include information about scans, scan results, and freeze windows in the diagnostic file ( <code>sc-sscaninfo.txt</code> ).	Enabled



Option	Description	Default
	For more information, see <a href="#">Active Scans</a> , <a href="#">Agent Scanning</a> , and <a href="#">Freeze Windows</a> .	
<b>Setup</b>	Include information about the following Tenable Security Center resources in the diagnostic file (sc-setup.txt): <ul style="list-style-type: none"><li>• Active users</li><li>• <a href="#">Tenable Nessus Scanners</a></li><li>• <a href="#">Tenable Nessus Network Monitor Instances</a></li><li>• <a href="#">Tenable Log Correlation Engines</a></li><li>• <a href="#">Scan Zones</a></li><li>• Schedules</li><li>• <a href="#">Job Queue Events</a></li><li>• <a href="#">Assets</a></li><li>• <a href="#">Repositories</a></li><li>• <a href="#">Organizations</a></li><li>• <a href="#">User Roles</a></li><li>• <a href="#">Reports</a></li><li>• Report results</li><li>• <a href="#">Audit Files</a></li></ul>	Enabled
<b>Logs</b>	Include administrator logs, organization logs, Tenable Security Center error logs, and the certificate log in the diagnostic file (sc-logs.txt, sc-error.log, and cert.log).	Enabled
<b>Environment</b>	Include information about the tns user environment in the diagnostic file (sc-environment.txt).	Enabled
<b>Directory List-</b>	Include a directory listing in the diagnostic file (sc-dir1-	Enabled



Option	Description	Default
<b>ing</b>	isting.txt).  For more information, see <a href="#">Tenable Security Center Communications and Directories</a> .	
<b>Dependency</b>	Include information about Tenable Security Center dependencies in the diagnostic file (sc-depsinfo.txt).  For more information, see <a href="#">Dependencies</a> .	Enabled
<b>Upgrade Log</b>	Include a log of Tenable Security Center upgrade events in the diagnostic file (upgrade.log).	Enabled
<b>Install Log</b>	Include a log of Tenable Security Center installation events in the diagnostic file (install.log).	Enabled
<b>Apache Log</b>	Include a log of web server requests in the diagnostic file (/opt/sc/support/error_Log).	Enabled
<b>Application Conf</b>	Include Tenable Security Center configuration details in the diagnostic file (sc-configuration.txt).	Enabled
<b>Server Conf</b>	Include server configuration details in the diagnostic file (/opt/sc/support/*.conf).	Enabled
<b>User Information</b>	Include a list of users in the diagnostic file (sc-users.txt). The list includes the following details: <ul style="list-style-type: none"><li>• For administrators, the user ID and role ID</li><li>• For organizational users, the user ID, role ID, and group ID</li></ul> For more information about ID values, see <a href="#">View User Details</a> , <a href="#">View User Role Details</a> , and <a href="#">View Group Details</a> .	Enabled
<b>Include Names</b>	(If <b>User Information</b> is enabled) Include usernames and user display names for each user in the diagnostic file.  For more information, see <a href="#">User Account Options</a> .	Disabled



Option	Description	Default
	<p><b>Tip:</b> The display name combine's the user's <b>First Name</b> and <b>Last Name</b>.</p>	



## Enable Debugging Logs

**Required User Role:** Administrator

You can enable debugging to generate logs for troubleshooting with Tenable Support.

To enable debugging:

1. Log in to Tenable Security Center via the user interface.
2. In the left navigation, click **System > Diagnostics**.

The **Diagnostics** page appears.

3. In the **Debugging Logs** section, select one or more debugging logs Tenable Support asked you to enable.
4. Click **Save Debug Settings**.

Tenable Security Center enables the debugging logs you selected and saves the corresponding log files to `/opt/sc/admin/logs`.

What to do next:

- Download the debugging logs, as described in [Download Debugging Logs](#).
- Share the debugging log files with Tenable Support.
- Disable any unneeded debugging logs, as described in [Disable Debugging Logs](#).

**Note:** Tenable does not recommend leaving debugging enabled on Tenable Security Center after you send the log files to Tenable Support. You may experience performance and storage issues if you leave debugging enabled for extended periods of time.

**Note:** Collected debug logs contained in the debug archive are automatically deleted during the scheduled nightly cleanup.



# Download Debugging Logs

**Required User Role:** Administrator

You can download debugging logs for troubleshooting with Tenable Support.

Before you begin:

- Enable debugging logs, as described in [Enable Debugging Logs](#).

To download debugging logs:

1. Log in to Tenable Security Center via the user interface.
2. In the left navigation, click **System > Diagnostics**.

The **Diagnostics** page appears.

3. In the **Download Debugging Logs** section, click **Collect Log Files**.

Tenable Security Center generates the debugging log files you selected.

4. Click **Download Debug File**.

The debugging logs download.

What to do next:

- Share the files with Tenable Support.
- Disable any debugging logs as needed, as described in [Disable Debugging Logs](#).

**Note:** Tenable does not recommend leaving debugging enabled on Tenable Security Center after you send the log files to Tenable Support. You may experience performance and storage issues if you leave debugging enabled for extended periods of time.

**Note:** Collected debug logs contained in the debug archive are automatically deleted during the scheduled nightly cleanup.





## Disable Debugging Logs

**Required User Role:** Administrator

Tenable does not recommend leaving debugging enabled on Tenable Security Center after you send the log files to Tenable Support. You may experience performance and storage issues if you leave debugging enabled for extended periods of time.

For more information about debugging logs, see [Debugging Logs](#).

To disable debugging:

1. Log in to Tenable Security Center via the user interface.
2. In the left navigation, click **System > Diagnostics**.

The **Diagnostics** page appears.

3. In the **Debugging Logs** section:
  - To disable individual debugging logs, deselect the logs.
  - To disable all debugging logs, click **Deselect All**.
4. Click **Save Debug Settings**.

Tenable Security Center disables the debugging logs you deselected.

What to do next:

- Follow Tenable Support's instructions to manually remove old debugging log files from `/opt/sc/admin/logs`.




---

## Job Queue Events

---

Path: **System** > **Job Queue**

Job Queue is a Tenable Security Center feature that displays specified events in a list for review.

You can view and sort Job Queue notifications in several ways by clicking on the desired sort column. Using the  menu next to an item, that item may be viewed for more detail or, if the job is running, the process may be killed. Killing a process should be done only as a last resort, as killing a process may have undesirable effects on other Tenable Security Center processes.



---

## System Logs

---

Tenable Security Center logs contain detailed information about functionality to troubleshoot unusual system or user activity. You can use the system logs for debugging and for maintaining an audit trail of users who access Tenable Security Center or perform basic functions (for example, changing passwords, recasting risks, or running Nessus scans).

To view system logs:

1. Log in to Tenable Security Center via the user interface.
2. Click **System > System Logs** (Administrator users) or **Username > System Logs** (Organizational users).

The **System Logs** page appears.

3. To filter the logs, see [Apply a Filter](#).

The page updates to reflect the filter you applied.



## View System Logs

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information, see [System Logs](#).

To view system logs:

1. Log in to Tenable Security Center via the user interface.
2. Click **System > System Logs** (Administrator users) or **Username > System Logs** (Organizational users).

The **System Logs** page appears.

3. To filter the logs, see [Apply a Filter](#).

The page updates to reflect the filter you applied.



## Publishing Sites Settings

Path: **System > Publishing Sites**

Organizations may configure publishing sites as targets to send report results to a properly configured web server or a Defense Information Systems Agency (DISA) Continuous Monitoring and Risk Scoring (CMRS) site.

Option	Description
<b>Name</b>	Type a name for the publishing site.
<b>Description</b>	Type a description of the publishing site.
<b>Type</b>	The method Tenable Security Center uses to publish to the site. Available options are <b>HTTP Post</b> or <b>CMRS</b> . Use the selection appropriate for the configuration of the publishing site.
<b>Max Chunk Size (MB)</b>	If the target is a CMRS site, Tenable sends the report in chunks sized according to this value.
<b>URI</b>	The target address to send the report to when completed.
<b>Authentication</b>	There are two methods of authentication available: <b>SSL Certificate</b> and <b>Password</b> .
<b>Username / Password</b>	If you select <b>Password</b> as the <b>Authentication</b> method, the credentials to authenticate to the target publishing server.
<b>Certificate</b>	If you selected <b>SSL Certificate</b> as the <b>Authentication</b> method, the certificate you want to use for authentication.
<b>Organizations</b>	Select the organization(s) that are allowed to publish to the configured site.
<b>Verify Host</b>	When enabled, Tenable Security Center verifies that the target address specified in the <b>URI</b> option matches the CommonName (CN) in the SSL certificate from the target publishing server.



---

## Keys Settings

---

Keys allow administrator users to use key-based authentication with a remote Tenable Security Center (remote repository) or between a Tenable Security Center and a Tenable Log Correlation Engine server. This also removes the need for Tenable Security Center administrators to know the administrator login or password of the remote system.

**Note:** The public key from the local Tenable Security Center must be added to the **Keys** section of the Tenable Security Center from which you wish to retrieve a repository. If the keys are not added properly, the remote repository add process prompts for the root username and password of the remote host to perform a key exchange before the repository add/sync occurs.

For more information, see [Add a Key](#), [Delete a Key](#), and [Download the Tenable Security Center SSH Key](#).

### Remote Tenable Log Correlation Engine Key Exchange

A manual key exchange between the Tenable Security Center and the Tenable Log Correlation Engine is normally not required; however, in some cases where remote root login is prohibited or key exchange debugging is required, you must manually exchange the keys.

For the remote Tenable Log Correlation Engine to recognize the Tenable Security Center, you need to copy the SSH public key of the Tenable Security Center and append it to the `/opt/lce/.ssh/authorized_keys` file. The `/opt/lce/daemons/lce-install-key.sh` script performs this function. For more information, see [Manual Log Correlation Engine Key Exchange](#).



## Add a Key

**Required User Role:** Administrator

For more information, see [Keys Settings](#).

To add a new key:

1. Log in to Tenable Security Center via the user interface.
2. Click **System > Keys**.  
The **Keys** page appears.
3. At the top of the table, click **Add**.  
The **Add Key** page appears.
4. In the **Type** drop-down, select **DSA** or **RSA**.
5. In the **Comment** box, add a description or note about the key.
6. In the **Public Key** box, type the text of your public key from your remote Tenable Security Center.
7. Click **Submit**.

Tenable Security Center saves your configuration.



---

## Delete a Key

---

**Required User Role:** Administrator

For more information, see [Keys Settings](#).

To delete a key:

1. Log in to Tenable Security Center via the user interface.
2. Click **System > Keys**.
3. Select the key you want to delete:

To delete a single key:

- a. In the table, right-click the row for the key you want to delete.

The actions menu appears.

- b. Click **Delete**.

To delete multiple keys:

- a. In the table, select the check box for each key you want to delete.

The available actions appear at the top of the table.

- b. At the top of the table, click **Delete**.

A confirmation window appears.

4. Click **Delete**.

Tenable Security Center deletes the key.





---

## Download the Tenable Security Center SSH Key

---

**Required User Role:** Administrator

For more information, see [Keys Settings](#).

To download the Tenable Security Center SSH key:

1. Log in to Tenable Security Center via the user interface.
2. Click **System > Keys**.
3. At the top of the table, click **Download Tenable Security Center Key**.

The Tenable Security Center SSH key downloads.




---

## Notifications

---


In Tenable Security Center, certain events can display a pop-up in the lower right-hand corner of the Tenable Security Center user interface. When you click on a notification, the **Notifications** page appears.

The **Notifications** page displays a list of notifications for your Tenable Security Center instance. You can filter these notifications by time frame. For general information about using filters, see [Filters](#).

To view your Tenable Security Center notifications, in the top navigation bar, click your user profile  icon > **Notifications**.



## User Profile Menu Settings

The user profile  icon in the top navigation bar opens a menu with options to manage your user account.

**Note:** Depending on the screen resolution, the username may not appear next to the user icon in the top navigation bar.

### About

Path: Your user profile  icon > **About**

The **About** menu item displays the Tenable Security Center version, Server Build ID, and copyright information.

### System Logs (Organizational Users Only)

Path: Your user profile  icon > **System Logs**

For a complete discussion about system logs, see [System Logs](#).

### Profile (Organizational Users Only)

Path: Your user profile  icon > **Profile**

The **Profile** option launches the **Edit User Profile** page, where you can modify some of your user account information and permissions. For more information about user account options, see [User Account Options](#).

### Feeds (Organizational Users Only)

Path: Your user profile  icon > **Feeds**

The **Feeds** option displays information about the Tenable Security Center feeds and plugin sets and, if permitted, a link to update the plugins either through Tenable Security Center or by manually uploading plugins. The displayed feeds are for Tenable Security Center Feed, Active Plugins, Passive Plugins, and Event Plugins. Only feeds with valid Activation Codes are updatable.



Plugins are scripts used by the Tenable Nessus, Tenable Nessus Network Monitor, and Log Correlation Engine servers to interpret vulnerability data. For ease of operation, Tenable Security Center centrally manages Tenable Nessus and Tenable Nessus Network Monitor plugins and pushes the plugins out to their respective scanners. Log Correlation Engine servers download their own event plugins and Tenable Security Center downloads event plugins for its local reference. Tenable Security Center does not currently push event plugins to Log Correlation Engine servers.

For more information about plugin/feed settings, see [Configuration Settings](#) and [Edit Plugin and Feed Settings and Schedules](#).

## Notifications

Path: Your user profile  icon > **Notifications**

In Tenable Security Center, specified events can display a pop-up in the lower right-hand corner of the Tenable Security Center user interface.

For more information, see [Notifications](#).

## Plugins

Path: Your user profile  icon > **Plugins**

Plugins are scripts used by the Tenable Nessus, Tenable Nessus Network Monitor, and Log Correlation Engine servers to interpret vulnerability data. For ease of operation, Tenable Nessus and Tenable Nessus Network Monitor plugins are managed centrally by Tenable Security Center and pushed out to their respective scanners. Log Correlation Engine servers download their own event plugins and Tenable Security Center downloads event plugins for its local reference. Tenable Security Center does not currently push event plugins to Log Correlation Engine servers.

Within the Plugins interface, click the information icon next to the Plugin ID and search for specific plugins utilizing the filtering tools to view plugin details/source.

For more information about custom plugins, see [Custom Plugin Packages for NASL and CA Certificate Upload](#).


## Help

Path: Your user profile  icon > **Help**



The **Help** option opens the *Tenable Security Center User Guide* section for your page. To access other Tenable documentation, see <https://docs.tenable.com/>.

## Logout

To end your session in Tenable Security Center, click Your user profile  icon > **Logout**. Tenable recommends closing your browser window after logging out.



## Custom Plugin Packages for NASL and CA Certificate Upload

You can upload a custom plugin package as a `.tar.gz` or `.tgz` file. Depending on your needs, you must include a combination of the following files:

- A `custom_feed_info.inc` file. Always include this file to time stamp your upload to Tenable Security Center.
- (Optional) A `custom_nasl_archive.tar.gz` or `custom_nasl_archive.tgz` file. Include this file if you are uploading one or more custom plugins.
- (Optional) A `custom_CA.inc` file. Include this file if you are uploading one or more CA certificates to solve a Tenable Nessus scanning issue.

After you [Create the Custom Plugin Package](#) and [Upload the Custom Plugin Package](#), Tenable Security Center pushes the package to Tenable Nessus for use when scanning.

**Note:** The system untars the files within your custom plugin package and overwrites any identically named files already in Tenable Security Center or Tenable Nessus.

### `custom_feed_info.inc` Guidelines

Always include this file to time stamp your upload to Tenable Security Center. This text file must contain the following lines:

```
PLUGIN_SET = "YYYYMMDDHHMM";  
PLUGIN_FEED = "Custom";
```

The `PLUGIN_SET` variable `YYYYMMDDHHMM` is the date and time 2 minutes in the future from when you plan to upload the file to Tenable Security Center.

### `custom_nasl_archive.tar.gz` or `custom_nasl_archive.tgz` Guidelines

Include this file if you are uploading one or more custom plugins. This package must contain one or more custom plugin NASL files.

All custom plugins must have unique Plugin ID numbers and have family associations based on existing Tenable Security Center families.



**Note:** Tenable Support does not assist with creating custom plugin NASL files.

## custom\_CA.inc Guidelines

Include this file if you are uploading one or more CA certificates to solve a Tenable Nessus scanning issue. This text file must contain PEM-encoded (Base64) CA certificate text.

For troubleshooting information, see [Troubleshooting Issues with the custom\\_CA.inc File](#).

### One CA Certificate

If you need to include a single CA certificate, paste the PEM-encoded (Base64) certificate directly into the file.

```
-----BEGIN CERTIFICATE-----  
certificatetext  
certificatetext  
certificatetext  
certificatetext  
-----END CERTIFICATE-----
```

### Multiple CA Certificates

If you need to include two or more CA certificates, include the PEM-encoded (Base64) certificates back-to-back.

```
-----BEGIN CERTIFICATE-----  
certificate1text  
certificate1text  
certificate1text  
certificate1text  
-----END CERTIFICATE-----  
-----BEGIN CERTIFICATE-----  
certificate2text  
certificate2text  
certificate2text  
certificate2text  
-----END CERTIFICATE-----
```



## Create the Custom Plugin Package

**Required User Role:** Administrator

For complete information, see [Custom Plugin Packages for NASL and CA Certificate Upload](#).

To create the .tar.gz or .tgz custom plugin package:

1. Prepare the individual text files you want to include in the custom plugins package.

- custom\_nasl\_archive.tar.gz or custom\_nasl\_archive.tgz
- custom\_feed\_info.inc
- custom\_CA.inc

Confirm the files meet the requirements described in [Custom Plugin Packages for NASL and CA Certificate Upload](#).

**Note:** After upload, the system untars the files within your custom plugin package and overwrites any identically named files already in Tenable Security Center or Tenable Nessus.

2. In the command line interface (CLI), tar and compress the files together. (7-Zip or running tar on a Mac does not work for this.) For example:

```
# tar -zcvf upload_this.tar.gz custom_feed_info.inc custom_CA.inc
```

The system generates a .tar.gz or .tgz file.

What to do next:

- Upload the .tar.gz or .tgz file, as described in [Upload the Custom Plugin Package](#).





---

## Upload the Custom Plugin Package

---

**Required User Role:** Administrator

For complete information, see [Custom Plugin Packages for NASL and CA Certificate Upload](#).

Before you begin:

- Create the .tar.gz or .tgz custom plugin file, as described in [Create the Custom Plugin Package](#).

Upload the .tar.gz or .tgz file to Tenable Security Center:

1. Log in to Tenable Security Center via the user interface.
2. Click **Username > Plugins**.  
The **Plugins** page appears.
3. Click **Upload Custom Plugins** and select the .tar.gz or .tgz file.
4. Click **Submit**.

Tenable Security Center uploads the package and pushes it to Tenable Nessus.

What to do next:

- To verify the upload succeeded, click **System > System Logs**.
- To verify the upload resolved a validation issue, run another scan that includes plugin 51192. Verify that Nessus has the custom plugin bundle by checking its plugin directory.



---

## Troubleshooting Issues with the `custom_CA.inc` File

---

If uploading a `custom_CA.inc` file does not resolve your issue, confirm your file meets the requirements described in [custom\\_CA.inc Guidelines](#). Then, use these tips to continue troubleshooting.

### The `/opt/sc/data/customNas1/custom_CA.inc` file

If the Tenable Security Center installation is not on the Appliance, check the uploaded `custom_CA.inc` with the following command: `# cat /opt/sc/data/customNas1/custom_CA.inc`.

The output should match the `custom_CA.inc` file that you checked in a text editor in step T1 above. If the file does not exist, the upload was not successful. If the file does not match, the most recent upload may not have been successful. Go over the steps above for creating and uploading `upload_this.tar.gz` and ensure it is done correctly.

### The `/opt/nessus/lib/nessus/plugins/custom_CA.inc` or `\ProgramData\Tenable\Nessus\nessus\plugins\custom_CA.inc` file

If Nessus is not on the Appliance, navigate to the plugins folder and `cat` or type `custom_CA.inc` to verify it exists and matches the `custom_CA.inc` file contents verified in steps 1 and 2 above. If `custom_CA.inc` does not exist in the plugins folder, or does not match the most recent `custom_CA.inc` in Tenable Security Center, it has not propagated to the scanner. Check **Resources > Nessus Scanners** in Tenable Security Center to see if the scanner is still updating plugins. If it is in a Working state, try updating the active plugins in Tenable Security Center to prompt a plugin push. If the plugin feed version has not incremented and the customer must push plugins immediately, see the following article: [Force plugin update on scanner managed by Tenable Security Center \(Comparable to `nessus-update-plugins -f`\)](#).

### The plugin 51192 output details

Adding the custom CA certificate to `custom_CA.inc` does not resolve the issue if the service is missing intermediate certificate(s). If the service has a self-signed or default certificate (if not self-signed with the server name, it may be issued by a vendor name like Nessus Certification Authority) and not a certificate signed by their custom CA at all, the certificate is expired, etc.

Look at the detailed plugin output of 51192 to see exactly why the certificate is untrusted. If `custom_CA.inc` can fix it, the output states that the certificate at the top of the certificate chain is



unrecognized, and the certificate it shows is either issued by the custom CA (matching the name exactly) or the actual custom CA self-signed certificate.



## Backup and Restore

Tenable recommends performing regular backups of the Tenable Security Center data in your `/opt/sc` directory. When you restore a backup, the file overwrites the content in your `/opt/sc` directory.

Data backup requirements:

- You must restore a backup file to a Tenable Security Center running the same version. For example, you cannot restore a backup file created on version 5.20.0 to a Tenable Security Center running Tenable Security Center 5.21.0.
- You must restore a backup file to the same Tenable Security Center where you created the backup file. The hostname associated with the backup file must match the hostname on the receiving Tenable Security Center. For example, you cannot restore a backup file created on a Tenable Security Center with the hostname *Example1* to a Tenable Security Center with the hostname *Example2*.

For more information, see [Perform a Backup](#) and [Restore a Backup](#).

## Configuration Backups

Tenable recommends performing regular backups of your Tenable Security Center configuration in addition to your Tenable Security Center data. You can restore a configuration backup to quickly resume normal Tenable Security Center operation as part of your disaster recovery plan.

Configuration backups do not include data (such as vulnerability data, trend data, licenses, or secure connection settings). When your repositories contain new vulnerability data, you can use your dashboards, reports, and analysis tools to assess your network.

**Note:** After you restore a configuration backup, Tenable recommends performing discovery scans to repopulate your repositories with vulnerability data. For more information, see [Scanning Overview](#).

Configuration backup requirements:

- You must restore a backup file to a Tenable Security Center running the same version. For example, you cannot restore a backup file created on version 5.20.0 to a Tenable Security Center running Tenable Security Center 5.21.0.



**Note:** For best performance, after restoring a configuration backup, ensure the hostname associated with the configuration backup file matches the hostname on the receiving Tenable Security Center.

For more information, see [Perform a Configuration Backup](#) and [Restore a Configuration Backup](#).

## Configurations Included in a Configuration Backup

Category	Configurations
Users	<a href="#">User accounts</a> , <a href="#">user roles</a> , <a href="#">groups</a> , and <a href="#">organizations</a>
Resources	<a href="#">Tenable Nessus scanners</a> , <a href="#">Tenable Nessus Network Monitor instances</a> , <a href="#">Log Correlation Engines</a> , <a href="#">LDAP servers</a> , and <a href="#">scan zones</a>
System	Configuration settings (including <a href="#">data expiration settings</a> , <a href="#">external schedules settings</a> , <a href="#">Tenable Lumin settings</a> , <a href="#">mail settings</a> , <a href="#">miscellaneous settings</a> , <a href="#">license settings</a> , <a href="#">plugins/feed settings</a> , <a href="#">SAML settings</a> , and <a href="#">security settings</a> ), <a href="#">publishing sites settings</a> , <a href="#">keys settings</a> , and schedules
Scanning	<a href="#">Active scans</a> , <a href="#">agent synchronization jobs</a> , <a href="#">agent scans</a> , <a href="#">freeze windows</a> , <a href="#">credentials</a> , <a href="#">scan policies</a> , <a href="#">audit files</a> , <a href="#">assets</a> , <a href="#">repositories</a> , and compliance check plugin entries
Reporting	<a href="#">Dashboards</a> , <a href="#">Assurance Report Cards</a> , <a href="#">report definitions</a> , <a href="#">report images</a> , and <a href="#">CyberScope and DISA report attributes</a>
Workflow	<a href="#">Alerts</a>
Analysis	<a href="#">Queries</a>

## Automatic Backups

Tenable Security Center performs automatic nightly backups of the following databases:

- /opt/sc/application.db
- /opt/sc/hosts.db
- /opt/sc/jobqueue.db
- /opt/sc/plugins.db



- `/opt/sc/remediationHierarchy.db`
- `/opt/sc/orgs/<orgID>/organization.db` (for each organization in your Tenable Security Center)
- `/opt/sc/orgs/<orgID>/assets.db` (for each organization in your Tenable Security Center)

Automatic backups run nightly at 1:20 AM local time. This schedule cannot be changed.

Tenable Security Center stores backups in the same directory as the database.



## Perform a Backup

**Required User Role:** Root user

For more information about the backup and restore process, see [Backup and Restore](#).

To perform a backup of Tenable Security Center data:

1. Log in to Tenable Security Center via the command line interface (CLI).
2. Stop Tenable Security Center, as described in [Start, Stop, or Restart Tenable Security Center](#).

Tenable Security Center stops.

3. In the CLI in Tenable Security Center, run the following command to view all running processes:

```
# ps -fu tns
```

4. If any processes are listed, run the following commands to stop them:

```
# killall -u tns
```

```
# killall httpd
```

**Note:** These commands stop all jobs (including scans) running on Tenable Security Center.

5. If necessary, repeat step 4 to confirm all processes stopped.
6. Run the following command to create a .tar file for your /opt/sc directory:

```
# tar -pzcf sc_backup.tar.gz /opt/sc
```

**Note:** The .tar file switches are case-sensitive.

Tenable Security Center creates the backup file.

7. Run the following command to confirm the backup file is not corrupted:



```
# tar -tvf sc_backup.tar.gz
```

8. Move the backup file to a secure location.
9. Start Tenable Security Center, as described in [Start, Stop, or Restart Tenable Security Center](#).  
Tenable Security Center starts.

What to do next:

- (Optional) Restore the backup file, as described in [Restore a Backup](#).





## Restore a Backup

**Required User Role:** Root user

For more information about the backup and restore process, see [Backup and Restore](#).

Before you begin:

- Perform a backup of your Tenable Security Center, as described in [Perform a Backup](#).
- Confirm your receiving Tenable Security Center meets the requirements described in [Backup and Restore](#).
- Move the backup file to your receiving Tenable Security Center's /tmp directory.

To restore a backup file:

1. Log in to Tenable Security Center via the command line interface (CLI).
2. Stop Tenable Security Center, as described in [Start, Stop, or Restart Tenable Security Center](#).

Tenable Security Center stops.

3. In the CLI in Tenable Security Center, run the following command to view all running processes:

```
# ps -fu tns
```

4. If any processes are listed, run the following commands to stop them:

```
# killall -u tns
```

```
# killall httpd
```

**Note:** These commands stop all jobs (including scans) running on Tenable Security Center.

5. If necessary, repeat step 4 to confirm all processes are stopped.



6. Run the following commands to decompress the .tar file and overwrite the existing /opt/sc directory:

```
# cd /
```

```
# tar -xvf /tmp/sc_backup.tar.gz
```

**Note:** The .tar file switches are case-sensitive.

The restore finishes.

7. Start Tenable Security Center, as described in [Start, Stop, or Restart Tenable Security Center](#).

Tenable Security Center starts.



# Perform a Configuration Backup

**Required User Role:** Root user

For more information about the backup and restore process and the configurations included in a configuration backup, see [Backup and Restore](#).

Before you begin:

- If you uploaded custom plugins, save a copy of your custom plugins in a safe location.

To perform a backup of your Tenable Security Center configuration:

1. Log in to Tenable Security Center via the command line interface (CLI).
2. Stop Tenable Security Center, as described in [Start, Stop, or Restart Tenable Security Center](#).  
Tenable Security Center stops.
3. In the CLI in Tenable Security Center, do one of the following:

- To save the configuration backup file to a local directory, run the following command, where *[local directory path]* is the local directory where you want to save the backup file:

```
/opt/sc/support/bin/php /opt/sc/src/tools/backupSCConfiguration.php -l [local directory path]
```

For example:

```
/opt/sc/support/bin/php /opt/sc/src/tools/backupSCConfiguration.php -l /tmp/
```

- To save the configuration backup file to a remote directory, run the following command, where *[remote directory absolute path]* is the absolute path to the remote directory where you want to save the backup file:



```
/opt/sc/support/bin/php /opt/sc/src/tools/backupSCConfiguration.php -r  
[user]@[host]:[remote absolute path to configuration backups directory]
```

For example:

```
/opt/sc/support/bin/php /opt/sc/src/tools/backupSCConfiguration.php -r  
tns@100.100.100.100:/tmp/
```

Tenable Security Center creates the configuration backup file and saves it to the specified directory.

**Tip:** The configuration backup file name includes the backup date and time, the Tenable Security Center hostname, and the Tenable Security Center version (for example, SC-config-20211101-165111-sc-hostname-5\_20\_0.tar.gz).

4. Start Tenable Security Center, as described in [Start, Stop, or Restart Tenable Security Center](#).

Tenable Security Center starts.

What to do next:

- (Optional) Restore the configuration backup file, as described in [Restore a Configuration Backup](#).



# Restore a Configuration Backup

**Required User Role:** Root user

For more information about the backup and restore process and the configurations included in a configuration backup, see [Backup and Restore](#).

**Note:** For best performance, after restoring a configuration backup, ensure the hostname associated with the configuration backup file matches the hostname on the receiving Tenable Security Center.

Before you begin:

1. Perform a configuration backup of your Tenable Security Center, as described in [Perform a Configuration Backup](#).
2. Confirm your receiving Tenable Security Center meets the requirements described in [Backup and Restore](#).

To restore a configuration backup file:

1. Log in to Tenable Security Center via the command line interface (CLI).
2. Stop Tenable Security Center, as described in [Start, Stop, or Restart Tenable Security Center](#).

Tenable Security Center stops.

3. In the CLI in Tenable Security Center, run the following command to restore the configuration backup, where *[path to backup file]* is the path to the backup file you want to restore:

```
/opt/sc/support/bin/php /opt/sc/src/tools/restoreSCConfiguration.php -l [path to backup file]
```

For example:

```
/opt/sc/support/bin/php /opt/sc/src/tools/restoreSCConfiguration.php -l /tmp/SC-config-20211101-165111-sc-hostname-5_20_0.tar.gz
```

Tenable Security Center restores the configuration backup.



- 
4. Start Tenable Security Center, as described in [Start, Stop, or Restart Tenable Security Center](#).  
Tenable Security Center starts.

What to do next:

1. If you uploaded custom plugins before restoring your Tenable Security Center configuration, re-upload the custom plugins. For more information, see [Custom Plugin Packages for NASL and CA Certificate Upload](#).
2. Perform discovery scans to re-populate your repositories with vulnerability data. For more information, see [Scanning Overview](#).



# Tenable Lumin Synchronization

You can use Tenable Lumin to quickly and accurately assess your Cyber Exposure risk and compare your health and remediation performance to other Tenable customers in your Salesforce industry and the larger population. Tenable Lumin correlates raw vulnerability data with asset business criticality and threat context data to support faster, more targeted analysis workflows than traditional vulnerability management tools. For more information about Tenable Lumin, see [Tenable Lumin](#) in the *Tenable Vulnerability Management User Guide*.

After you acquire a Tenable Lumin license for use with Tenable Security Center, you can configure Tenable Security Center synchronization to send limited Tenable Security Center data to Tenable Vulnerability Management for use in Tenable Lumin analysis. Tenable Security Center communicates with Tenable Vulnerability Management using an encrypted connection, as described in [Encryption Strength](#).

When you send data to Tenable Vulnerability Management, the system does not remove the data from your Tenable Security Center. You can continue normal operation of Tenable Security Center.

For more information, see:

- [Plan Your Tenable Lumin Synchronization](#)
- [Configure Tenable Lumin Synchronization](#)
- [View Tenable Lumin Synchronization Status](#)
- [View Tenable Lumin Data Synchronization Logs](#)
- [View Tenable Lumin Metrics](#)
- [Disable Tenable Lumin Synchronization](#)

## Tenable Lumin Synchronization Options

Option	Description
<b>Access Key</b>	The Tenable Vulnerability Management API access key for a Tenable Vulnerability Management user with Administrator permissions.
<b>Secret Key</b>	The Tenable Vulnerability Management API secret key for a Tenable Vul-



Option	Description
<b>Network Support</b>	<p>nerability Management user with Administrator permissions.</p> <p>Supports accurate tracking of assets in repositories with overlapping IPv4 addresses.</p> <div data-bbox="367 436 1479 930" style="border: 1px solid green; padding: 10px;"><p><b>Tip:</b> The default setting for <b>Network Support</b> depends on the Tenable Security Center version where you configured Tenable Lumin synchronization. For the purpose of determining the default setting for <b>Network Support</b>, Tenable Lumin synchronization is configured if you have configured the <b>Tenable.io Connection Settings</b> and selected at least one repository to synchronize.</p><ul style="list-style-type: none"><li>• Tenable Security Center 5.18.x or earlier —Disabled by default if Tenable Lumin is already configured.</li><li>• Tenable Security Center 5.19.x or later —Enabled by default and cannot be disabled.</li></ul></div> <ul style="list-style-type: none"><li>• Enabled —Tenable Security Center synchronizes each IPv4 repository, agent repository, and universal repository to its own network in Tenable Vulnerability Management, named <b>TSC-Repository Name</b>. You do not need to resolve <a href="#">repository overlaps</a> if you enable <b>Network Support</b>.</li></ul> <div data-bbox="448 1178 1479 1255" style="border: 1px solid blue; padding: 5px;"><p><b>Note:</b> Once enabled, you cannot disable <b>Network Support</b>.</p></div> <ul style="list-style-type: none"><li>• Disabled —Tenable Security Center synchronizes all repository data to the Default network in Tenable Vulnerability Management. You must resolve all <a href="#">repository overlaps</a> before synchronizing your Tenable Security Center data to Tenable Vulnerability Management.</li></ul> <p>For more information, see <a href="#">Networks</a> in the <i>Tenable Vulnerability Management User Guide</i>.</p> <p>Contact your Tenable representative to enable <b>Network Support</b>.</p>





## Plan Your Tenable Lumin Synchronization

Tenable recommends planning your synchronization strategy to accommodate synchronization limitations and limit data duplication in Tenable Vulnerability Management.

### Can I communicate with Tenable Vulnerability Management through a proxy?

To use the proxy configured for your Tenable Security Center instance for communications with your Tenable Vulnerability Management instance, contact Tenable Support.

### Can I synchronize multiple Tenable Security Center instances?

You can synchronize data from one Tenable Security Center to one Tenable Vulnerability Management instance. You cannot synchronize data from multiple Tenable Security Center instances to a single Tenable Vulnerability Management instance.

If you purchase multiple Tenable Vulnerability Management instances, you can synchronize one Tenable Security Center to each Tenable Vulnerability Management instance.

### What data does synchronization include?

Tenable Security Center supports synchronizing:

- IPv4 addresses within dynamic assets and IPv4 addresses within static assets.

**Note:** You cannot synchronize IPv6 addresses within static assets. If an asset contains a mix of IPv4 and IPv6 addresses, Tenable Security Center synchronizes only the IPv4 addresses.

**Note:** You cannot synchronize non-IPv4 assets within dynamic assets. If a dynamic asset contains other asset types, Tenable Security Center synchronizes only the IPv4 addresses.

**Note:** You cannot synchronize DNS name list assets, LDAP query assets, combination assets, watchlist assets, or import assets.

- Active or agent cumulative database and scan result vulnerability data stored in IPv4, IPv6, agent, and universal repositories.



The initial synchronization includes all cumulative database data from the repository. All subsequent synchronizations include only the new or modified scan result data imported to the repository.

**Note:** You cannot synchronize passive scan result vulnerability data. Tenable Security Center identifies vulnerability data by plugin family and excludes Tenable Nessus Network Monitor and LCE plugin families from synchronization.

**Caution:** To avoid data merge issues in Tenable Vulnerability Management, Tenable recommends enabling **Network Support** or resolving all repository overlaps before synchronizing data to Tenable Vulnerability Management. You cannot resolve data merge issues after synchronizing a repository with Tenable Vulnerability Management; you must enable **Network Support** or resolve overlapping repositories in Tenable Security Center before synchronizing a repository for the first time. For more information, see [Network Support and Repository Overlap](#).

## Do I need to synchronize both data types (repositories and assets)?

Yes. In order to accurately assess your Cyber Exposure risk with Tenable Lumin, you must synchronize one or more asset lists and one or more repositories containing vulnerability data for those assets.

## Should I resolve repository overlaps or enable **Network Support**?

If you first configured Tenable Lumin synchronization in Tenable Security Center 5.19.x or later, **Network Support** is enabled by default and cannot be disabled.

If you first configured Tenable Lumin synchronization in Tenable Security Center 5.18.x or earlier and upgraded to Tenable Security Center 5.19.x or later, you can decide to enable **Network Support** instead of resolving repository overlaps in the Tenable Security Center repositories you synchronize with Tenable Vulnerability Management. Contact your Tenable representative to enable **Network Support**.

**Tip:** For the purpose of determining the default setting for **Network Support**, Tenable Lumin synchronization is configured if you have configured the **Tenable.io Connection Settings** and selected at least one repository to synchronize.

For more information, see [Network Support and Repository Overlap](#) and [Tenable Lumin Synchronization Options](#).



## How long does synchronization take to complete?

Vulnerability and asset data synchronize differently to Tenable Vulnerability Management.

Data	Synchronization Method	Timing
Vulnerability data	<ul style="list-style-type: none"><li>• Manual initial synchronization.</li><li>• Automatic subsequent synchronizations when new scan result data imports to your synchronized repositories.</li></ul>	<p>After you initiate a synchronization, Tenable Security Center immediately begins transferring data to Tenable Vulnerability Management. After 10-15 minutes, data begins appearing in Tenable Vulnerability Management.</p> <p>Newly transferred data does not immediately impact your Tenable Lumin metrics (for example, your CES). Tenable requires up to 48 hours to recalculate your metrics.</p>
Asset data ( <i>tags</i> in Tenable Vulnerability Management)	<ul style="list-style-type: none"><li>• Manual initial synchronization.</li><li>• On-demand, automatic, or scheduled subsequent synchronizations, depending on your synchronization configuration.</li></ul>	<p>All data and recalculated Tenable Lumin metrics appear in Tenable Vulnerability Management within 48 hours.</p> <p>Recalculated metrics appear in Tenable Security Center after the next daily retrieval.</p>

To monitor the success or failure of synchronizations, see [View Tenable Lumin Synchronization Status](#) and [View Tenable Lumin Data Synchronization Logs](#).

## Which of my synchronized assets count toward my Tenable Vulnerability Management license?

Synchronized assets that count toward your Tenable Security Center license also count toward your Tenable Vulnerability Management license. For more information about Tenable Security Center asset counting, see [License Requirements](#).



## Where will I see synchronized data in Tenable Vulnerability Management?

**Tip:** Viewing vulnerability data is temporarily not possible in Tenable Vulnerability Management. You can view asset and solutions data, but not vulnerability data. For more information, contact your Tenable representative.

You can view your synchronized data in both the Vulnerability Management and Tenable Lumin areas of Tenable Vulnerability Management.

### Vulnerability Management

View your synchronized data on the **Assets** page. For more information, see [View Assets in Tenable Vulnerability Management](#).

### Tenable Lumin

View your synchronized data on any Tenable Lumin page. For more information, see [Get Started with Tenable Lumin](#) in the *Tenable Vulnerability Management User Guide*.

**Tip:** To view limited metrics Tenable Security Center retrieves from Tenable Lumin in Tenable Vulnerability Management, see [View Tenable Lumin Metrics](#).



## Network Support and Repository Overlap

Two or more IPv4 repositories *overlap* if their specified **IP Ranges** contain intersecting IP addresses. To avoid data merge issues in Tenable Vulnerability Management, Tenable recommends enabling **Network Support** or resolving all repository overlaps before synchronizing data to Tenable Vulnerability Management.

While both methods avoid data merge issues, Tenable recommends enabling **Network Support** to support accurate tracking of assets in repositories with overlapping IPv4 addresses without manually resolving repository overlaps.

### Synchronize Repositories to Individual Tenable Vulnerability Management Networks

**Tip:** The default setting for **Network Support** depends on the Tenable Security Center version where you configured Tenable Lumin synchronization. For the purpose of determining the default setting for **Network Support**, Tenable Lumin synchronization is configured if you have configured the **Tenable.io Connection Settings** and selected at least one repository to synchronize.

- Tenable Security Center 5.18.x or earlier —Disabled by default if Tenable Lumin is already configured.
- Tenable Security Center 5.19.x or later —Enabled by default and cannot be disabled.

Because **Network Support** synchronizes each IPv4 and agent repository to its own individual network in Tenable Vulnerability Management, repositories with overlap do not cause data merge issues in Tenable Vulnerability Management.

For more information, see [Tenable Lumin Synchronization Options](#).

### Resolve Repository Overlaps

If **Network Support** is disabled and you do not plan to enable it, you must resolve repository overlaps before synchronizing new repositories to Tenable Vulnerability Management.

To resolve an overlap between two repositories, edit the repository configurations and reconfigure the **IP Ranges** to avoid intersecting IP addresses, as described in [IPv4/IPv6 Repositories](#).



**Caution:** You cannot resolve data merge issues after synchronizing a repository with Tenable Vulnerability Management; you must enable **Network Support** or resolve overlapping repositories in Tenable Security Center before synchronizing a repository for the first time.

If you cannot resolve all overlaps and you do not want to enable **Network Support**, plan to synchronize a limited number of repositories to avoid conflicts. For example, to avoid a conflict between two repositories, synchronize one repository but not the other repository.



## Configure Tenable Lumin Synchronization

**Required Additional License:** Tenable Lumin

**Required Tenable Security Center User Role:** Administrator

**Required Tenable Vulnerability Management User Role:** Administrator

You can configure Tenable Security Center to send limited Tenable Security Center data to Tenable Vulnerability Management for use in Tenable Lumin analysis. For more information, see [Tenable Lumin Synchronization](#).

Before you begin:

- License and enable Tenable Lumin in Tenable Vulnerability Management, as described in [License and Enable Tenable Lumin](#) in the *Tenable Vulnerability Management User Guide*.
- Plan your synchronization strategy and review known limitations and dependencies, as described in [Plan Your Tenable Lumin Synchronization](#).
- Note that Tenable Security Center repositories are not case-sensitive, but networks in Tenable Vulnerability Management are case-sensitive. When you synchronize a repository, ensure that the name is unique from any existing Tenable Vulnerability Management networks.
- Plan your strategy for avoiding data merge issues and perform any required cleanup, as described in [Network Support and Repository Overlap](#).

**Caution:** You cannot resolve data merge issues after synchronizing a repository with Tenable Vulnerability Management; you must enable **Network Support** or resolve overlapping repositories in Tenable Security Center before synchronizing a repository for the first time.

- Generate Tenable Vulnerability Management API keys for a Tenable Vulnerability Management user with Administrator permissions, as described in [Generate API Keys](#) in the *Tenable Vulnerability Management User Guide*.
- Share any assets you want to synchronize with the **Full Access** group, as described in [Groups](#). You cannot synchronize assets with more limited sharing.

To configure data synchronization between Tenable Security Center and Tenable Lumin in Tenable Vulnerability Management:



1. Log in to Tenable Security Center via the user interface.
2. Click **System > Configuration**.

The **Configuration** page appears.

3. Click the **Tenable Lumin** tile.

The **Tenable Lumin Configuration** page appears.

4. In the **Tenable Vulnerability Management Connection Settings** section, type an **Access Key** and **Secret Key** for the Tenable Vulnerability Management user you want to have full access to your data in Tenable Vulnerability Management. For more information, see [Tenable Lumin Synchronization Options](#).

Tenable Security Center validates the connection to Tenable Vulnerability Management and locks the key configuration.

5. (Optional) To test the connection to Tenable Vulnerability Management, click **Test Connection**.

Tenable Security Center tests the connection to Tenable Vulnerability Management using the access key and secret key you provided.

Tenable Security Center displays a notification indicating the status of the connection to Tenable Vulnerability Management.

6. In the **Vulnerability Data Synchronization** section:

- a. (Optional) If you did not enable **Network Support** and you want to synchronize each Tenable Security Center repository to its own network in Tenable Vulnerability Management, contact your Tenable representative to enable **Network Support**. For more information, see [Tenable Lumin Synchronization Options](#).

**Note:** Once enabled, you cannot disable **Network Support**.

- b. Select one or more repositories that contain the scan result data you want to synchronize with Tenable Vulnerability Management.


The initial synchronization includes all cumulative database data from the repository. All subsequent synchronizations include only the new or modified scan result data imported to the repository.





**Note:** You cannot synchronize passive scan result vulnerability data. Tenable Security Center identifies vulnerability data by plugin family and excludes Tenable Nessus Network Monitor and LCE plugin families from synchronization.

**Caution:** To avoid data merge issues in Tenable Vulnerability Management, Tenable recommends enabling **Network Support** or resolving all repository overlaps before synchronizing data to Tenable Vulnerability Management. You cannot resolve data merge issues after synchronizing a repository with Tenable Vulnerability Management; you must enable **Network Support** or resolve overlapping repositories in Tenable Security Center before synchronizing a repository for the first time. For more information, see [Network Support and Repository Overlap](#).

**Tip:** Hover over the  to view [details](#) for a repository (including information about unresolved repository overlaps).

- c. Click **Synchronize**.


A confirmation window appears.

- d. Click **Synchronize**.

Tenable Security Center begins synchronizing your vulnerability data to Tenable Vulnerability Management.

## 7. In the **Asset to Tag Synchronization** section:

- a. If you want to synchronize asset data at a scheduled time:

- i. Click to enable the **Custom Schedule** slider.
- ii. Next to the schedule link, click the  button.
- iii. Modify the **Time** and **Timezone** options to specify when you want synchronizations to occur.

**Tip:** You cannot modify the **Frequency** or **Repeat Every** options; all Tenable Lumin synchronizations occur once daily.

If you do not schedule your asset synchronizations, Tenable Security Center automatically synchronizes once daily, after business hours for your local time zone.



b. If you want to filter the assets that appear in the **Unstaged Assets** section, do any of the following:

- Select an organization from the **Organization Filter** drop-down list and click **Apply Filters**.
- Select an asset type from the **Asset Type Filter** drop-down list and click **Apply Filters**.
- Type an asset name in the **Search Name** box and press **Enter**.

**Note:** You can synchronize any assets shared with the **Full Access** group. You cannot synchronize assets with more limited sharing.

Tenable Security Center applies your filter to the **Unstaged Assets** section.

c. To stage one or more assets for synchronization, do one of the following:

- Click the **Add All** button to stage all visible assets for synchronization.

Tenable Security Center stages all visible assets for synchronization and displays them in the **Staged Assets** section.

- In the rows for individual assets you want to stage for synchronization, click the **+** button.

Tenable Security Center stages your selected assets for synchronization and displays them in the **Staged Assets** section.

**Note:** You cannot synchronize IPv6 addresses within static assets. If an asset contains a mix of IPv4 and IPv6 addresses, Tenable Security Center synchronizes only the IPv4 addresses.

**Note:** You cannot synchronize non-IPv4 assets within dynamic assets. If a dynamic asset contains other asset types, Tenable Security Center synchronizes only the IPv4 addresses.

**Note:** You cannot synchronize DNS name list assets, LDAP query assets, combination assets, watchlist assets, or import assets.

**Tip:** Click an asset row to view [details](#) for an asset.



- d. Click **Synchronize Staged Assets**.

A confirmation window appears.

- e. Click **Synchronize**.

Tenable Security Center begins synchronizing your assets to Tenable Vulnerability Management.

8. Wait for data transfer and Tenable Lumin data calculations to complete. For more information, see [How long does synchronization take to complete?](#)
9. Monitor the synchronization and confirm there were no errors, as described in [View Tenable Lumin Synchronization Status](#) or [View Tenable Lumin Data Synchronization Logs](#).

What to do next:

- Begin using Tenable Vulnerability Management and Tenable Lumin, as described in [Where will I see synchronized data in Tenable Vulnerability Management?](#)
- View Tenable Lumin metrics information within Tenable Security Center, as described in [View Tenable Lumin Metrics](#).
- By default, synchronized data is visible to the Tenable Vulnerability Management Administrator account used for synchronization and to all other users in Tenable Vulnerability Management. If you want to restrict privileges for synchronized data, configure access groups as described in [Access Groups](#) in the *Tenable Vulnerability Management User Guide*.



# View Tenable Lumin Synchronization Status

**Required Additional License:** Tenable Lumin

**Required User Role:** Administrator

After you configure Tenable Security Center data synchronization to Tenable Lumin in Tenable Vulnerability Management, you can view the status of your synchronizations.

For information about viewing logs for past synchronizations, see [View Tenable Lumin Data Synchronization Logs](#).

Before you begin:

- Configure Tenable Lumin synchronization, as described in [Configure Tenable Lumin Synchronization](#).

To monitor the status of your data synchronization between Tenable Security Center and Tenable Lumin in Tenable Vulnerability Management:


1. Log in to Tenable Security Center via the user interface.
2. Click **System > Configuration**.

The **Configuration** page appears.

3. Click the **Tenable Lumin** tile.

The **Tenable Lumin Configuration** page appears.

4. In the **Vulnerability Data Synchronization** section:

- View the **Last Successful Sync** date and time for data from any repository.
- View details for a repository by hovering over the  that appears when you hover over a repository name:

Data	Description
Name	The repository name.



Data	Description
Format	The repository type: <b>IPv4/IPv6</b> , <b>Agent</b> , or <b>Universal</b> .
First Successful Synchronization	The date and time of the first synchronization of this repository.
Last Successful Synchronization	The date and time of the most recent synchronization of this repository.
Error Status	If the most recent synchronization of this repository failed, a description of the failure.
Last Failed Synchronization	The date and time of the most recent failed synchronization of this repository.
Repositories Overlapping with <Repository Name>	The names of other repositories with <b>IP Ranges</b> that overlap this repository. For more information, see <a href="#">Network Support and Repository Overlap</a> .

5. In the **Asset to Tag Synchronization** section:



- In the **Unstaged Assets** or **Staged Assets** section, click an asset row to view details for an asset:

Data	Description
Description	The asset description.
First Sync Success	The date and time of the first synchronization of this asset.
Last Sync Success	The date and time of the most recent synchronization of this asset.
Last Sync Failure	The date and time of the most recent failed synchronization of this asset.
Sync Error	If the most recent synchronization of this asset failed, a description of the failure.

- View the **Last Successful Sync** date and time for any asset data.



# Disable Tenable Lumin Synchronization

**Required Additional License:** Tenable Lumin

**Required User Role:** Administrator

When you disable Tenable Lumin synchronization, Tenable Security Center stops synchronizing new or updated scan result and asset data with Tenable Lumin in Tenable Vulnerability Management. Existing Tenable Security Center data remains visible in Tenable Vulnerability Management.

To stop synchronizing data with Tenable Lumin in Tenable Vulnerability Management:

1. Log in to Tenable Security Center via the user interface.
2. Click **System > Configuration**.

The **Configuration** page appears.

3. Click the **Tenable Lumin** tile.

The **Tenable Lumin Configuration** page appears.

4. In the **Vulnerability Data Synchronization** section:
  - a. Deselect all of your repositories.
  - b. Click **Synchronize**.

Tenable Security Center stops synchronizing vulnerability data to Tenable Vulnerability Management. Existing Tenable Security Center data remains visible in Tenable Vulnerability Management.

5. In the **Asset to Tag Synchronization** section:
  - a. In the **Staged Assets** section, click **Remove All**.

All staged assets move to the **Unstaged Assets** section.

- b. Click **Synchronize Staged Assets**.

Tenable Security Center stops synchronizing asset data to Tenable Vulnerability Management. Existing Tenable Security Center data remains visible in Tenable Vulnerability Management.



---

## Configure Scans

---

See the following sections to configure Tenable Security Center scans.

- [Scanning Overview](#)
- [Resources](#)
- [Repositories](#)
- [Active Scans](#)
- [Active Scan Objects](#)
- [Agent Scans](#)
- [Agent Scanning](#)
- [Freeze Windows](#)
- [Patch Management](#)





## Scanning Overview

You can perform two types of scans using Tenable products: *discovery scans* and *assessment scans*. Tenable recommends performing discovery scans to get an accurate picture of the assets on your network and assessment scans to understand the vulnerabilities on your assets.

Configuring both methods provides a comprehensive view of the organization's security posture and reduces false positives. For more information about Tenable scanning strategies, see the [Tenable Scan Strategy Guide](#).

Scan Type	Description	Licensing
Discovery Scan	<p>Find assets on your network. For example:</p> <ul style="list-style-type: none"><li>• a scan configured with the <b>Host Discovery</b> template.</li><li>• a scan configured to use only discovery plugins.</li><li>• an <a href="#">Tenable Nessus Network Monitor instance in discovery mode</a>.</li></ul>	Assets identified by discovery scans do not count toward your license.
Assessment Scan	<p>Find vulnerabilities on your assets. For example:</p> <ul style="list-style-type: none"><li>• an <i>authenticated</i> or <i>unauthenticated</i> <a href="#">active scan</a> using a Tenable Nessus or Tenable Vulnerability Management scanner.</li><li>• an <a href="#">agent scan</a> using an agent-capable Tenable Vulnerability Management or Tenable Nessus Manager scanner.</li></ul> <p><b>Authenticated Active Scans</b></p> <p>Configure authenticated scans, also known as credentialed scans, by adding access credentials to your assessment scan configuration.</p> <p>Credentialed scans can perform a wider variety of checks than non-credentialed scans, which can result in more accurate scan results. This facilitates scanning of</p>	In general, assets assessed by assessment scans count toward your license.



a very large network to determine local exposures or compliance violations.

Credentialed scans can perform any operation that a local user can perform. The level of scanning depends on the privileges granted to the user account. The more privileges the scanner has via the login account (e.g., root or administrator access), the more thorough the scan results.

For more information, see [Credentials](#).

### **Unauthenticated Active Scans**

If you do not add access credentials to your assessment scan configuration, Tenable Vulnerability Management performs a limited number of checks when scanning your assets.

For more information about how discovered and assessed assets are counted towards your license, see [License Requirements](#).



---

## Resources

---

Administrator users can configure supporting resources.

- [Tenable Nessus Scanners](#)
- [Tenable Nessus Network Monitor Instances](#)
- [Tenable Log Correlation Engines](#)
- [Tenable Log Correlation Engine Clients](#)
- [Tenable Log Correlation Engine Client Policies](#)
- [Tenable OT Security Instances](#)

Scan zone resources are considered active scan objects. For more information, see [Active Scan Objects](#) and [Scan Zones](#).

LDAP server resources are part of user account configuration. For more information, see [User Accounts](#) and [LDAP Authentication](#).



# Tenable Nessus Scanners

For high level information about active and agent scanning, see [Active Scans](#) and [Agent Scans](#).

In the Tenable Security Center framework, the Tenable Nessus scanner behaves as a server, while Tenable Security Center serves as a client that schedules and initiates scans, retrieves results, reports results, and performs a wide variety of other important functions.

You can add Tenable Nessus or Tenable Vulnerability Management deployments to Tenable Security Center as Tenable Nessus scanners in Tenable Security Center:

- Managed or unmanaged Tenable Nessus scanners

**Note:** Tenable Security Center cannot perform scans with or update plugins for scanners running unsupported versions of Tenable Nessus. For minimum Tenable Nessus scanner version requirements, see the [Tenable Security Center Release Notes](#) for your version.

- Tenable Nessus Manager instances

**Note:** If you enabled clustering on Tenable Nessus Manager, add the parent node of the cluster to Tenable Security Center. For more information, see [Clustering](#) in the *Tenable Nessus User Guide*.

- Tenable Vulnerability Management instances

For more information, see:

- [Add a Tenable Nessus Scanner](#)
- [Add a Tenable Vulnerability Management Scanner](#)
- [Manage Nessus Scanners](#)
- [View Your Nessus Scanners](#)
- [View Details for a Nessus Scanner](#)
- [Delete a Nessus Scanner](#)
- [View Tenable Nessus Instances in Tenable Security Center](#)

For information about Tenable Security Center-Tenable Nessus and Tenable Security Center-Tenable Vulnerability Management communications encryption, see [Encryption Strength](#).

## Tenable Nessus Scanner Settings



Option	Description
<b>Name</b>	A descriptive name for the scanner.
<b>Description</b>	A scanner description, location, or purpose.
<b>Host</b>	The hostname or IP address of the scanner.
<b>Port</b>	The TCP port that the scanner listens on for communications from Tenable Security Center. The default is port 8834.
<b>Enabled</b>	A scanner may be <b>Enabled</b> or <b>Disabled</b> within Tenable Security Center to allow or prevent access to the scanner.
<b>Verify Hostname</b>	<p>Adds a check to verify that the hostname or IP address entered in the <b>Host</b> option matches the CommonName (CN) presented in the SSL certificate from the Nessus server.</p> <div style="border: 1px solid blue; padding: 5px;"><p><b>Note:</b> Confirm that the correct CA certificate is configured for use by Tenable Security Center. If you are using a custom CA, configure Tenable Security Center to trust your custom CA, as described in <a href="#">Trust a Custom CA</a>. You do not need to perform this step when using the default certificates for Tenable Nessus servers.</p></div>
<b>Use Proxy</b>	Instructs Tenable Security Center to use its configured proxy for communication with the scanner.
<b>Authentication Type</b>	<p>Select <b>Password</b>, <b>SSL Certificate</b>, or <b>API Keys</b> for the authentication type to connect to the scanner.</p> <p>For complete information about Tenable Nessus SSL certificate authentication, see <a href="#">Manual Tenable Nessus SSL Certificate Exchange</a>.</p>
<b>Username</b>	Username generated during the install for daemon to client communications. This must be an administrator user in order to send plugin updates to the scanner. If the scanner is updated by a different method, such as through another Tenable Security Center, a standard user account may be used to perform scans. This option is only available if the <b>Authentication Type</b> is set to <b>Password</b> .
<b>Password</b>	The login password must be entered in this option. This option is only



Option	Description
	available if the <b>Authentication Type</b> is set to <b>Password</b> .
<b>Certificate</b>	<p>If you set <b>Authentication Type</b> to <b>SSL Certificate</b>, specifies the <code>nes-suscert.pem</code> file you want to use for authentication to the scanner.</p> <p>For complete information about Tenable Nessus SSL certificate authentication, see <a href="#">Manual Tenable Nessus SSL Certificate Exchange</a>.</p>
<b>Certificate Passphrase</b>	If you selected <b>SSL Certificate</b> as the <b>Authentication Type</b> and the private key that decrypts your SSL certificate is encrypted with a passphrase, the passphrase for the private key.
<b>Zones</b>	The scan zones that can use this scanner. For more information, see <a href="#">Scan Zones</a> .
<b>Agent Capable</b>	<p>Specifies whether you want this scanner to provide Tenable Nessus Agent scan results to Tenable Security Center.</p> <p>Agent capable scanners must be either Tenable Vulnerability Management or Nessus Manager 6.5 or later. When using Nessus Manager, you must use an organizational user account to connect from Tenable Security Center.</p>
<b>Organizations</b>	When the <b>Agent Capable</b> option is enabled, or you select <b>API Keys</b> as the <b>Authentication Type</b> , specifies one or more organizations that you want to grant access to import Tenable Nessus Agent data into Tenable Security Center.
<b>API Keys</b>	<p>When the <b>Agent Capable</b> option is enabled, specifies whether you want to use secure API keys when importing agent scan data from Tenable Nessus or Tenable Vulnerability Management scanners.</p> <p>For more information about retrieving your access key and secret key from Tenable Nessus and Tenable Vulnerability Management, see <a href="#">Generate a Nessus API Key</a> in the <i>Tenable Nessus User Guide</i> and <a href="#">Generate a Tenable Vulnerability Management API Key</a> in the <i>Tenable Vulnerability Management User Guide</i>.</p>



Option	Description
<b>Access Key</b>	<p>When the <b>API Keys</b> option is enabled, specifies the access key for the Tenable Nessus or Tenable Vulnerability Management scanner.</p> <p>When you select <b>API Keys</b> as the <b>Authentication Type</b>, specifies the access key for the Tenable Nessus Agent.</p>
<b>Secret Key</b>	<p>When the <b>API Keys</b> option is enabled, specifies the secret key for the Tenable Nessus or Tenable Vulnerability Management scanner.</p> <p>When you select <b>API Keys</b> as the <b>Authentication Type</b>, specifies the secret key for the Tenable Nessus Agent.</p>



## Add a Tenable Nessus Scanner

**Required User Role:** Administrator

For more information, see [Tenable Nessus Scanners](#).

**Note:** Tenable Security Center cannot perform scans with or update plugins for scanners running unsupported versions of Tenable Nessus. For minimum Tenable Nessus scanner version requirements, see the [Tenable Security Center Release Notes](#) for your version.

**Note:** Tenable Security Center does not send plugins to linked Nessus Managers. Nessus Manager pulls plugins directly from Tenable's plugin sites. Therefore, to update plugin sets, Nessus Manager needs access to the internet and Tenable's plugin sites (for more information, see the [Which Tenable sites should I allow?](#) community article). If your Nessus Manager does not have internet access, you can manually update its version and plugins offline (for more information, see [Manage Nessus Offline](#) in the *Nessus User Guide*).

To add a Tenable Nessus scanner to Tenable Security Center:

1. Log in to Tenable Security Center via the user interface.
2. Click **Resources > Tenable Nessus Scanners**.

The **Tenable Nessus Scanners** page appears.

3. At the top of the table, click **Add**.

The **Add Tenable Nessus Scanner** page appears.

4. Configure Tenable Nessus scanner options, as described in [Tenable Nessus Scanners](#).
  - a. In the **Name** box, type a name for the scanner.
  - b. In the **Description** box, type a description for the scanner.
  - c. In the **Host** box, type the hostname or IP address for the scanner.
  - d. In the **Port** box, view the default (**8834**) and modify, if necessary.
  - e. If you want to disable this scanner's connection to Tenable Security Center, click **Enabled** to disable the connection.





- f. If you want to verify that the hostname or IP address entered in the **Host** option matches the CommonName (CN) presented in the SSL certificate from the Tenable Nessus scanner, click **Verify Hostname** to enable the toggle.
- g. If you want to use the proxy configured in Tenable Nessus for communication with the scanner, click **Use Proxy** to enable the toggle.
- h. In the **Type** drop-down box, select the authentication type.
  - i. If you selected **Password** as the **Type**:
    - i. In the **Username** box, type the username for the account generated during the Tenable Nessus installation for daemon-to-client communications.
    - ii. In the **Password** box, type the password associated with the username you provided.
  - j. If you selected **SSL Certificate** as the **Type**:
    - i. Click **Choose File** to upload the `nessuscert.pem` file you want to use for authentication to the scanner. For more information, see [Manual Tenable Nessus SSL Certificate Exchange](#).
    - ii. (Optional) If the private key that decrypts your SSL certificate is encrypted with a passphrase, in the **Certificate Passphrase** box, type the passphrase for the private key.
- k. Check the box for all active scan zones you want to use this scanner.
- l. If you want this scanner to provide Tenable Nessus Agent scan results to Tenable Security Center:
  - i. Click **Agent Capable** to enable the toggle.
  - ii. Check the box for one or more **Organizations** that you want to grant access to import Tenable Nessus Agent data into Tenable Security Center.
  - iii. If you want to use secure API keys when importing agent scan data from Tenable Nessus scanners:



- a. Click **API Keys** to enable the toggle.
- b. In the **Access Key** box, type the access key.
- c. In the **Secret Key** box, type the secret key.

5. Click **Submit**.

Tenable Security Center saves your configuration.

What to do next:

- Configure a scan zone, repository, and active scan objects, as described in [Active Scans](#).



## Add a Tenable Vulnerability Management Scanner

**Required User Role:** Administrator

Tenable Security Center supports the use of Tenable Vulnerability Management as a Tenable Nessus scanner within Tenable Security Center. Tenable Vulnerability Management is an enterprise-class remote vulnerability scanning service you can use to audit internet-facing IP addresses for both network and web application vulnerabilities from the cloud. While Tenable Security Center does not manage Tenable Vulnerability Management scanners (for example, Tenable Security Center does not push plugins to the scanner), you can add Tenable Vulnerability Management scanners to Tenable Security Center the same way you add internal, local, or remote Tenable Nessus scanners.

Before you begin:

- Confirm that you have a valid, active Tenable Vulnerability Management subscription.

To add Tenable Vulnerability Management to Tenable Security Center as a Tenable Nessus scanner:

1. Log in to Tenable Security Center via the user interface.
2. Click **Resources > Tenable Nessus Scanners**.
3. At the top of the table, click **Add**.



## Add Nessus Scanner ← Back

### General

Name\*

Description

Host\*

Port\*

Enabled

Verify Hostname

Use Proxy

### Authentication

Type

Username\*

Password\*

### Active Scans

Zones

Default Scan Zone

### Agents

Agent Capable

4. Configure Tenable Nessus scanner options, as described in [Tenable Nessus Scanners](#). You use Tenable Vulnerability Management-specific values for some settings.



Option	Value for a Tenable Vulnerability Management Configuration
Host	<ul style="list-style-type: none"><li>• Commercial Tenable Vulnerability Management: <i>cloud.tenable.com</i></li><li>• Tenable Vulnerability Management FedRAMP: <i>fed-cloud.tenable.com</i></li></ul>
Port	443
Username	The username for an active Tenable Vulnerability Management user account.
Password	The password for an active Tenable Vulnerability Management user account.
Zones	The zones within Tenable Security Center that use Tenable Vulnerability Management as a scanner.

5. Click **Submit**.

**Note:** Existing scan reports from Tenable Vulnerability Management are not automatically available in Tenable Security Center. However, you can manually download and import them into Tenable Security Center.

**Note:** By default, Tenable Vulnerability Management selects the corresponding regional scanner. For example, if you run a scan in the United States, Tenable Vulnerability Management selects the United States scanner. If you run a scan in Germany, Tenable Vulnerability Management selects the Germany scanner.

What to do next:

- Configure a scan zone, repository, and active scan objects, as described in [Active Scans](#).



## Tenable Nessus Scanner Statuses

You can view the status for scanners, as described in [View Your Nessus Scanners](#).

Status	Description	Recommended Action
<b>Authentication Error</b>	Tenable Security Center could not authenticate to the scanner using the credentials you provided.	Check your <a href="#">scanner configuration settings</a> and confirm the <b>Username</b> and <b>Password</b> options specify valid login credentials for the scanner.
<b>Certificate Mismatch</b>	Tenable Security Center could not confirm the validity of the SSL certificate presented by the scanner.	Do one of the following: <ul style="list-style-type: none"><li>• <a href="#">Edit your scanner configuration</a> and select a different authentication type.</li><li>• (Tenable Nessus scanners only) Check your <a href="#">scanner configuration settings</a> and confirm the <b>Certificate</b> option specifies the correct <code>nessuscert.pem</code> file. For more information about managing SSL certificates in Nessus, see <a href="#">Manage SSL Certificates</a> in the <i>Tenable Nessus User Guide</i>.</li></ul>
<b>Connection Error</b>	Tenable Security Center cannot connect to the scanner because the scanner is unreachable or does not exist at the IP address or hostname provided.	Do one or both of the following: <ul style="list-style-type: none"><li>• <a href="#">Check your scanner configuration</a> and confirm the <b>Host</b> option specifies the correct IP address or hostname for the scanner.</li><li>• Confirm the network devices and firewalls between Tenable</li></ul>



		Security Center and the scanner are configured to permit network traffic.
<b>Connection Timeout</b>	Tenable Security Center connected to the scanner but timed out waiting for a reply.	Contact your network administrator for troubleshooting assistance.
<b>Invalid Configuration</b>	The scanner attempted to connect to a scanner on port 0, or the provided API key is for a scanner that does not support agent scans.	Do one or both of the following: <ul style="list-style-type: none"><li>• <a href="#">Check your scanner configuration</a> and confirm the <b>Port</b> option specifies a valid TCP port to connect to your scanners. For more information, see <a href="#">Port Requirements</a>.</li><li>• <a href="#">Check your scanner configuration</a> and confirm the <b>Access Key</b> and <b>Secret Key</b> options specify valid keys for a Tenable Nessus Manager or cloud scanner.</li></ul>
<b>Permission Error</b>	The provided API keys do not have the correct permissions to run agent scans.	<a href="#">Check your scanner configuration</a> and confirm the <b>Access Key</b> and <b>Secret Key</b> options specify valid keys for the scanner.
<b>Plugins Out of Sync</b>	The plugin sets on the scanner do not match the plugin sets in Tenable Security Center.	For troubleshooting assistance, see the <a href="#">knowledge base</a> article.
<b>Protocol Error</b>	Tenable Security Center connected to the scanner but the scanner returned an HTTPS protocol negotiation error.	Contact your network administrator for troubleshooting assistance.



<b>Reloading Scanner</b>	The scanner is temporarily unable to run scans because Tenable Nessus is restarting on the scanner.	None.
<b>Updating Plugins</b>	Tenable Security Center is performing a plugin update on the scanner.	You may want to schedule plugin updates to run a few hours before your scheduled scans. For more information, see <a href="#">Edit Plugin and Feed Settings and Schedules</a> .  If a scanner has a persistent <b>Updating Plugins</b> status, the plugin update have been interrupted. For troubleshooting assistance, see the <a href="#">knowledge base</a> article.
<b>Updating Status</b>	Tenable Security Center is refreshing the status of the scanner. Scanners can continue to run scans while Tenable Security Center refreshes the status.  <div style="border: 1px solid blue; padding: 5px;"><p><b>Note:</b> Tenable Security Center automatically refreshes scanner statuses every 15 minutes.</p><p>If you create a new scanner, edit a scanner, or manually refresh the status using the <b>Update Status</b> option, Tenable Security Center refreshes the status of the scanner on demand.</p></div>	None.
<b>Upgrade Required</b>	The version of Tenable Nessus on the scanner is unsupported and requires an upgrade.	Upgrade to a supported version of Tenable Nessus, as described in <a href="#">Upgrade Nessus</a> in the <i>Tenable Nes-</i>





	<p>Tenable Security Center cannot perform scans with or update plugins for scanners running unsupported versions of Tenable Nessus. For minimum Tenable Nessus scanner version requirements, see the <a href="#">Tenable Security Center Release Notes</a> for your version.</p>	<p><i>sus User Guide.</i></p>
<b>User Disabled</b>	<p>A Tenable Security Center user disabled the scanner.</p>	<p><a href="#">Edit your scanner configuration</a> and click the <b>Enabled</b> toggle to re-enable the scanner.</p> <p>For more information about scanner options, see <a href="#">Tenable Nessus Scanners</a>.</p>
<b>Working</b>	<p>The scanner is connected to Tenable Security Center and able to run scans.</p>	<p>None.</p>



# Manage Nessus Scanners

**Required User Role:** Administrator

For more information, see [Tenable Nessus Scanners](#).

To manage your Tenable Nessus scanners:

1. Log in to Tenable Security Center via the user interface.

2. Click **Resources > Tenable Nessus Scanners**.

The **Tenable Nessus Scanners** page appears.

3. To filter the scanners that appear on the page, apply a filter as described in [Apply a Filter](#).

4. To view the list of configured scanners, see [View Your Nessus Scanners](#).

5. To view details for a scanner, see [View Details for a Nessus Scanner](#).

6. To edit a scanner:

- a. Right-click the row for the scanner.

The actions menu appears.

-or-

Select the check box for the scanner.

The available actions appear at the top of the table.

- b. Click **More > Edit**.

The **Edit Tenable Nessus Scanner** page appears.

- c. Modify the scanner options. For more information about scanner options, see [Tenable Nessus Scanners](#).

- d. Click **Submit**.

7. To download logs for a scanner, see [Download Tenable Nessus Scanner Logs](#).

8. To delete a scanner, see [Delete a Nessus Scanner](#).



# View Your Nessus Scanners

**Required User Role:** Administrator

For more information, see [Tenable Nessus Scanners](#).

To view a list of configured Tenable Nessus scanners:

1. Log in to Tenable Security Center via the user interface.
2. Click **Resources > Tenable Nessus Scanners**.

The **Tenable Nessus Scanners** page appears.

3. View details about each Tenable Nessus scanner.
  - **Name** —The name for the scanner.
  - **Features** —Specifies whether the scanner is a **Standard** scanner or an **Agent Capable** scanner. Agent capable scanners provide Tenable Nessus Agent scan results to Tenable Security Center.
  - **Status** —The status of the scanner. For more information, see [Tenable Nessus Scanner Statuses](#).
  - **Host** —The IP address or hostname of the scanner.
  - **Version** —The scanner's Tenable Nessus version.
  - **Type** —The type of scanner connection.

Type	Description
Unknown	Tenable Security Center could not identify the scanner.
Nessus (Unmanaged Plugins)	Tenable Security Center accesses the scanner using a Tenable Nessus user account with <b>Standard</b> permissions.  Tenable Security Center cannot send plugin updates to the scanner or manage the scanner's activation code.
Nessus (Man-	Tenable Security Center manages the scanner and authen-



Type	Description
aged Plugins)	ticates via a Tenable Nessus user account.  Tenable Security Center sends plugin updates to the scanner and manages the scanner's activation code.
Tenable.io (Unmanaged Plugins)	Tenable Security Center accesses the instance using a Tenable Vulnerability Management user account with <b>Standard</b> permissions.  Tenable Security Center cannot send plugin updates to the instance or manage the instance's activation code.

- **Uptime** —The length of time, in days, that the scanner has been running.
  - **Last Modified** —The date and time the scanner was last modified.
4. To view details of a specific Tenable Nessus scanner, see [View Details for a Nessus Scanner](#).
  5. To filter the scanners that appear on the page, apply a filter as described in [Apply a Filter](#).
  6. To manually refresh the **Status** data, at the top of the table, click **Update Status**.

Tenable Security Center refreshes the **Status** data.



## View Details for a Nessus Scanner

**Required User Role:** Administrator

For more information, see [Tenable Nessus Scanners](#).

To view details for a Tenable Nessus scanner:

1. Log in to Tenable Security Center via the user interface.
2. Click **Resources > Tenable Nessus Scanners**.

The **Tenable Nessus Scanners** page appears.

3. Right-click the row for the scanner you want to view.

The actions menu appears.

-or-

Select the check box for the scanner you want to view.

The available actions appear at the top of the table.

4. Click **View**.


The **View Tenable Nessus Scanner** page appears.

Section	Action
<b>Options</b> drop-down box	<ul style="list-style-type: none"><li>• To edit the scanner, click <b>Edit</b>.</li><li>• To delete the scanner, click <b>Delete</b>, as described in <a href="#">Delete a Nessus Scanner</a>.</li><li>• To download logs for the scanner, click <b>Download Logs</b>. For more information, see <a href="#">Download Tenable Nessus Scanner Logs</a>.</li></ul>
<b>General</b>	View general information about the scanner.
<b>Authentication</b>	View authentication information for the scanner.



Section	Action
Active Scans	View active scan information for the scanner.
Agents	<p>View agent information for the scanner.</p> <ul style="list-style-type: none"><li>• <b>Agent Capable</b> —Specifies whether the scanner is agent capable: <b>Yes</b> or <b>No</b>.</li><li>• <b>Organizations</b> —If the scanner is agent capable, the organization configured for the scanner.</li><li>• <b>API Keys Set</b> —If the scanner is agent capable, specifies whether API keys are configured for the scanner: <b>Yes</b> or <b>No</b>.</li></ul>
Data summary	<p>View metadata and performance metrics for the scanner.</p> <div style="border: 1px solid blue; padding: 5px;"><p><b>Note:</b> Tenable Security Center refreshes the load information every 15 minutes.</p></div>
Nessus Scanner Health	<p>If you are viewing details for a managed Tenable Nessus scanner running version 8.2.0 or later, view scanner health summary data:</p> <ul style="list-style-type: none"><li>• <b>Running Scans</b> —The number of scans currently running on the scanner.</li><li>• <b>Hosts Being Scanned</b> —The number of hosts currently being scanned by the scanner.</li><li>• <b>CPU Load</b> —The percent of the total CPU currently in use by the scanner.</li><li>• <b>Total Memory</b> —The total memory installed on the scanner.</li><li>• <b>Memory Used</b> —The percent of the total memory currently in use by the scanner.</li><li>• <b>Total Disk Space</b> —The total disk space installed on the scanner.</li><li>• <b>Disk Space Used</b> —The percent of the total disk space cur-</li></ul>



Section	Action
	<p>rently in use by the scanner.</p> <ul style="list-style-type: none"><li>• <b>Last Updated</b>—The date and time Tenable Security Center last updated the scanner data.</li></ul> <p>Tenable Security Center refreshes the data when you load the <b>View Nessus Scanner</b> page. To force a manual refresh, click the  button.</p>



## View Tenable Nessus Instances in Tenable Security Center

**Required User Role:** Administrator

Administrators can view and manage Tenable Nessus scanner configurations from the Tenable Security Center user interface. For more information about Tenable Nessus scanners in Tenable Security Center, see [Tenable Nessus Scanners](#).

**Note:** You cannot use **Picture in Picture** with a Tenable Nessus scanner if you enabled **Use Proxy** for the scanner or if the scanner's **Authentication Type** is **SSL Certificate**. For more information, see [Tenable Nessus Scanner Settings](#).

Before you begin:

- Enable **Picture in Picture**, as described in [Enable Picture in Picture](#).

To view Tenable Nessus instances inside the Tenable Security Center user interface:

1. Log in to Tenable Security Center via the user interface.
2. Click **Resources > Tenable Nessus Scanners**.

The **Tenable Nessus Scanners** page appears.

3. Right-click the row for the Tenable Nessus scanner.

The actions menu appears.

-or-

Select the check box for the Tenable Nessus scanner.

The available actions appear at the top of the table.

4. Click **Manage System**.

The Tenable Nessus instance opens inside the Tenable Security Center user interface.

What to do next:





- Manage your Tenable Nessus scanner configurations using the picture in picture window in Tenable Security Center. For more information about Tenable Nessus and Tenable Nessus settings, see the *Tenable Nessus User Guide*.
- To exit the Picture in Picture view, in the upper-right corner, click **Back**.



# Download Tenable Nessus Scanner Logs

**Required User Role:** Administrator

You can download a log file for Tenable Nessus scanners managed by Tenable Security Center. The Tenable Nessus scanner must be running version 8.0.0 or later to send logs to Tenable Security Center for download.

All Tenable Nessus scanner logs include:

- Recent Tenable Nessus log data
- System information (operating system version, CPU statistics, available memory, available disk space, etc.)
- Troubleshooting data

If you include extended logs, the system also downloads recent Tenable Nessus web server log records, system log data, and network configuration information.

To download logs for a Tenable Nessus scanner:

1. Log in to Tenable Security Center via the user interface.
2. Click **Resources > Nessus Scanners**.

The **Nessus Scanners** page appears.

3. Right-click the row for the scanner for which you want to download logs.

The actions menu appears.

-or-

Select the check box for the scanner for which you want to download logs.

The available actions appear at the top of the table.

4. Click **Download Logs**.

The **Download Nessus Scanner Logs** window appears.



5. To include recent Tenable Nessus web server log records, system log data, and network configuration information, click to enable the **Extended Logs** toggle.
6. To hide the first two octets of IPv4 addresses within the logs, click to enable the **Sanitize IPs** toggle.
7. Click **Download**.

Tenable Security Center downloads the tar .gz file in your browser.

**Tip:** If you use 7-Zip to extract the tar .gz file, you may see the following error message: There are some data after the end of the payload data. You can safely ignore this error.



## Delete a Nessus Scanner

**Required User Role:** Administrator

For more information, see [Tenable Nessus Scanners](#).

To delete a Tenable Nessus scanner:

1. Log in to Tenable Security Center via the user interface.
2. Click **Resources > Nessus Scanners**.

The **Nessus Scanners** page appears.

3. Select the scanner you want to delete:

To delete a single scanner:

- a. In the table, right-click the row for the scanner you want to delete.

The actions menu appears.

- b. Click **Delete**.

To delete multiple scanners:

- a. In the table, select the check box for each scanner you want to delete.

The available actions appear at the top of the table.

- b. At the top of the table, click **More > Delete**.

A confirmation window appears.

4. Click **Delete**.

Tenable Security Center deletes the scanner.



## Tenable Nessus Network Monitor Instances

Tenable Nessus Network Monitor (Tenable Nessus Network Monitor) is a patented network discovery and vulnerability analysis software solution that delivers real-time network profiling and monitoring for continuous assessment of an organization's security posture in a non-intrusive manner. Tenable Nessus Network Monitor monitors network traffic at the packet layer to determine topology, services, and vulnerabilities. Where an active scanner takes a snapshot of the network in time, Tenable Nessus Network Monitor behaves like a security motion detector on the network.

Tenable Security Center communicates with Tenable Nessus Network Monitor utilizing the XMLRPC protocol on port 8835 by default. For information about Tenable Security Center-Tenable Nessus Network Monitor communications encryption, see [Encryption Strength](#).

**Note:** It is important for you to restrict the data Tenable Nessus Network Monitor collects to only the desired IP address ranges. For example, if your attached Tenable Nessus Network Monitor collects information on 1100 hosts and Tenable Security Center is licensed for 1000 hosts, Tenable Security Center imports all of the Tenable Nessus Network Monitor data and indicates that you exceeded your host count. For more information, see [License Requirements](#).

Tenable Security Center will ask Tenable Nessus Network Monitor for the latest (if any) vulnerability report once every hour by default. The pull interval may be changed under the System Configuration page under the Update tab.

To fully configure passive scan data retrieval from Tenable Nessus Network Monitor:

1. Configure Tenable Nessus Network Monitor, as described in [Get Started](#) in the *Tenable Nessus Network Monitor User Guide*.
2. Add your Tenable Nessus Network Monitor license to Tenable Security Center, as described in [Apply a New License](#).
3. Add an IPv4, IPv6, or Universal repository for Tenable Nessus Network Monitor data in Tenable Security Center, as described in [Add a Repository](#).
4. Add an Tenable Nessus Network Monitor instance in Tenable Security Center, as described in [Add an Tenable Nessus Network Monitor Instance](#).
5. (Optional) Configure Tenable Nessus Network Monitor plugin import schedules, as described in [Edit Plugin and Feed Settings and Schedules](#). By default, Tenable Security Center checks for



---

new passive vulnerability plugins every 24 hours and pushes them to your attached Tenable Nessus Network Monitor instances.

What to do next:

- View vulnerability data filtered by your Tenable Nessus Network Monitor repository, as described in [Vulnerability Analysis](#).

## Considerations for Licensing

If you want Tenable Security Center to push plugin updates to Tenable Nessus Network Monitor, you must add the product activation code to Tenable Security Center. For more information, see [Apply a New License](#).

For detailed information about plugins counted toward the Tenable Security Center license count, see [License Requirements](#).

## Considerations for Tenable Nessus Network Monitor Discovery Mode

Your Tenable Nessus Network Monitor instances can run in two modes: discovery mode disabled and discovery mode enabled. For more information, see [NNM Settings](#) in the *Tenable Nessus Network Monitor User Guide*.

If discovery mode is enabled on an Tenable Nessus Network Monitor instance, Tenable Security Center stores discovery mode asset data to Tenable Security Center repositories. Since discovery mode only discovers limited asset data, the repository data appears incomplete.

Tenable Security Center does not count IP addresses present only from Tenable Nessus Network Monitor instances in discovery mode toward your license count.



# Add an Tenable Nessus Network Monitor Instance

**Required User Role:** Administrator

Before you begin:

- Confirm you understand the complete scanning configuration process, as described in [Tenable Nessus Network Monitor Instances](#).

To add an Tenable Nessus Network Monitor instance to Tenable Security Center:

1. Log in to Tenable Security Center via the user interface.
2. Click **Resources > Tenable Nessus Network Monitors**.

The **Tenable Nessus Network Monitor Scanners** page appears.

3. At the top of the table, click **Add**.

The **Add Tenable Nessus Network Monitor Scanner** page appears.

4. Configure the settings, as described in [Tenable Nessus Network Monitor Instance Settings](#).
  - a. In the **Name** box, type a name for the scanner.
  - b. In the **Description** box, type a description for the scanner.
  - c. In the **Host** box, type the hostname or IP address for the scanner.
  - d. In the **Port** box, view the default (**8835**) and modify, if necessary.
  - e. If you want to disable this scanner's connection to Tenable Security Center, click **Enabled** to disable the connection.
  - f. If you want to verify that the hostname or IP address entered in the **Host** option matches the CommonName (CN) presented in the SSL certificate from the Tenable Nessus Network Monitor server, click **Verify Hostname** to enable the toggle.
  - g. If you want to use the proxy configured in Tenable Nessus Network Monitor for communication with the scanner, click **Use Proxy** to enable the toggle.
  - h. In the **Type** drop-down box, select the authentication type.



- i. If you selected **Password** as the **Type**:
    - i. In the **Username** box, type the username for the account generated during the Tenable Nessus Network Monitor installation for daemon-to-client client communications.
    - ii. In the **Password** box, type the password for the account generated during the Tenable Nessus Network Monitor installation for daemon-to-client client communications
  - j. If you selected **SSL Certificate** as the **Type**, click **Choose File** to upload a certificate.
  - k. If you selected **SSL Certificate** as the **Type**:
    - i. Click **Choose File** to upload a certificate.
    - ii. (Optional) If the private key that decrypts your SSL certificate is encrypted with a passphrase, in the **Certificate Passphrase** box, type the passphrase for the private key.
  - l. In the **Repositories** list, select one or more repositories where you want Tenable Security Center to store the scanner data.
5. Click **Submit**.

Tenable Security Center saves your configuration.





# View Your Tenable Nessus Network Monitor Instances

**Required User Role:** Administrator

For more information, see [Tenable Nessus Network Monitor Instances](#).

To view your Tenable Nessus Network Monitor instances in Tenable Security Center:

1. Log in to Tenable Security Center via the user interface.
2. Click **Resources > Nessus Network Monitors**.

The **Nessus Network Monitor Scanners** page appears.

3. View details about each Tenable Nessus Network Monitor instance.
  - **Name** —The name for the instance.
  - **Status** —The status of the instance.
  - **Host** —The IP address of the instance.
  - **Version** —The instance's Tenable Nessus Network Monitor version.
  - **Uptime** —The length of time, in days, that the instance has been running.
  - **Last Report** —The date and time Tenable Nessus Network Monitor most recently reported data to Tenable Security Center.
4. (Optional) To manually refresh the **Status** data, at the top of the table, click **Update Status**.

Tenable Security Center refreshes the **Status** data.



## Tenable Nessus Network Monitor Instance Settings

Use the following options to configure Tenable Nessus Network Monitor instances in Tenable Security Center, as described in [Add an Tenable Nessus Network Monitor Instance](#).

Option	Description
Name	Descriptive name for the Tenable Nessus Network Monitor instance.
Description	Instance description, location, or purpose.
Host	Hostname or IP address of the instance.
Port	TCP port that the Tenable Nessus Network Monitor instance listens on for communications from Tenable Security Center. The default is port 8835.
State	A instance may be marked as <b>Enabled</b> or <b>Disabled</b> within Tenable Security Center to allow or prevent access to the instance.
Authentication Type	Select Password or SSL Certificate for the authentication type to connect to the Tenable Nessus Network Monitor instance.
Username	Username generated during the Tenable Nessus Network Monitor install for daemon to client communications. This must be an administrator user in order to send plugin updates to the Tenable Nessus Network Monitor instance. This option is only available if the <b>Authentication Type</b> is set to <b>Password</b> .
Password	The login password must be entered in this option. This option is only available if the <b>Authentication Type</b> is set to <b>Password</b> .
Certificate	This option is available if the <b>Authentication Type</b> is <b>SSL Certificate</b> . Click the <b>Browse</b> button, choose a SSL Certificate file to upload, and upload to the Tenable Security Center.
Certificate Passphrase	If you selected <b>SSL Certificate</b> as the <b>Authentication Type</b> and the private key that decrypts your SSL certificate is encrypted with a passphrase, the passphrase for the private key.
Verify Hostname	Adds a check to verify that the hostname or IP address entered in the



Option	Description
	<b>Host</b> option matches the CommonName (CN) presented in the SSL certificate from the Tenable Nessus Network Monitor server.
Use Proxy	Instructs Tenable Security Center to use its configured proxy for communication with the instance.
Repositories	The repositories which this Tenable Nessus Network Monitor instance will save its data to. If Tenable Nessus Network Monitor will be reporting IPv4 and IPv6 data, at least two repositories (one for IPv4 and one for IPv6 data) must be selected.



# Tenable Log Correlation Engines

Tenable Tenable Log Correlation Engine (Log Correlation Engine) is a software module that aggregates, normalizes, correlates, and analyzes event log data from the myriad of devices within the infrastructure. Log Correlation Engine also has the ability to analyze logs for vulnerabilities.

Tenable Security Center performs vulnerability, compliance, and event management, but without Log Correlation Engine integration it does not directly receive logs or IDS/IPS events. With Log Correlation Engine integration, Log Correlation Engine processes the events and passes the results to Tenable Security Center.

Log Correlation Engine's close integration with Tenable Security Center allows you to centralize log analysis and vulnerability management for a complete view of your organization's security posture.

**Note:** If you add an Log Correlation Engine server to Tenable Security Center and enable **Import Vulnerabilities**, Log Correlation Engine data counts against your Tenable Security Center license. For more information, see [License Requirements](#).

For more information, see [Add a Tenable Log Correlation Engine Server](#).

If remote root or root equivalent user login is prohibited in your environment, you can add the Log Correlation Engine server using SSH key authentication. For more information, see [Manual Log Correlation Engine Key Exchange](#).

For information about Tenable Security Center-Tenable Log Correlation Engine communications encryption, see [Encryption Strength](#).

## Tenable Log Correlation Engine Options

Option	Description
<b>Name</b>	Name for the integrated Tenable Log Correlation Engine.
<b>Description</b>	Descriptive text for the integrated Tenable Log Correlation Engine.
<b>Host</b>	IP address of the integrated Tenable Log Correlation Engine.
<b>Check Authentication</b>	Whether Tenable Security Center checks the status of authentication between itself and the Log Correlation Engine server.
<b>Organizations</b>	Organizations that can access data from the integrated Tenable Log Cor-



Option	Description
	relation Engine.
<b>Repositories</b>	The repositories where you want Tenable Security Center to store the imported Log Correlation Engine data.
<b>Port</b>	The port where the Log Correlation Engine reporter is listening on the Log Correlation Engine server.
<b>Username and Password</b>	<p>The username and password you want Tenable Security Center to use for authentication to the Log Correlation Engine server to retrieve vulnerability information.</p> <p>This user account must be able to make changes on the remote system to enable the SSH key exchange between Tenable Security Center and Log Correlation Engine. The appropriate permissions level is typically root, root equivalent, or other high-level user permissions on the Log Correlation Engine system. Tenable Security Center uses these credentials a single time to exchange SSH keys for secure communication between Tenable Security Center and Log Correlation Engine.</p>



## Add a Tenable Log Correlation Engine Server

**Required User Role:** Administrator

**Tip:** You can configure more than one Tenable Log Correlation Engine to work with Tenable Security Center.

Before you begin:

- Confirm you understand the complete scanning configuration process, as described in [Tenable Log Correlation Engines](#).

To add an Log Correlation Engine server to Tenable Security Center:

1. Log in to Tenable Security Center via the user interface.
2. Click **Resources > Log Correlation Engines**.  
The **LCE Servers** page appears.
3. At the top of the table, click **Add**.  
The **Add LCE Server** window appears.
4. Configure the **General** options, as described in [Tenable Log Correlation Engines](#).
  - a. In the **Name** box, type a name for the Log Correlation Engine server.
  - b. In the **Description** box, type a description for the Log Correlation Engine server.
  - c. In the **Host** box, type the hostname or IP address for the Log Correlation Engine server.
  - d. In the **Port** box, view the default (**1243**) and modify, if necessary.
5. (Optional) To allow Tenable Security Center to log in to the Log Correlation Engine server and retrieve vulnerability information:
  - a. Enable **Import Vulnerabilities**.

**Note:** If you use an Log Correlation Engine server with Tenable Security Center, Tenable Security Center counts the IP addresses associated with each imported instance against your license. For more information, see [License Requirements](#).



- b. Select a **Repository** for the event vulnerability data.
- c. Type a **Username** and **Password** you want Tenable Security Center to use for access to the Log Correlation Engine server.

6. Click **Submit**.

Tenable Security Center saves your configuration.

7. (Optional) If you enabled the **Check Authentication** option above, Tenable Security Center checks its ability to authenticate with the Log Correlation Engine server.
- If authentication is successful, Tenable Security Center displays a message to acknowledge that fact.
  - If authentication fails, Tenable Security Center prompts you for credentials to the Log Correlation Engine server:
    - a. Type a username and password.
    - b. Click **Push Key** to initiate the transfer of the SSH Key.

If the transfer is successful, Tenable Security Center displays a message to acknowledge that fact.



## Tenable Log Correlation Engine Clients

The Log Correlation Engine server manages configuration files for Log Correlation Engine 5.x clients remotely from the command line. Tenable Security Center manages the configuration files for Tenable Log Correlation Engine 5.x clients via a graphical interface.

The default view for the Log Correlation Engine Clients page displays all of the available clients for the selected Tenable Log Correlation Engine server in the **Filters** section, and may be changed by updating the Log Correlation Engine Server filter. Use the other filter options, to narrow down the displayed clients for the selected server by a mix of criteria based on combinations of the displayed columns.

Current Log Correlation Engine Client versions display information in the table including their name, host address, authorization status, client type, host OS, assigned policy file, date last updated, and client version. Log Correlation Engine Client configurations can be managed from Tenable Security Center.

**Tip:** Configured clients prior to version 5.x appear in the list without OS and policy information. However, these clients cannot have their policy files centrally managed from Tenable Security Center.

Each client may have a name assigned to it to help easily identify the client. The currently assigned name appears in the **Name** column. To change the name, click on the client to edit from the list, and type the name. Client names may not contain spaces. Click the **Submit** button to save the change.

Log Correlation Engine Clients are initially configured to send their data to a particular Log Correlation Engine server, but must be authorized by the Log Correlation Engine sever for the server to accept the data. The client's authorization status appears in the left-side column. If there is no icon, the client is authorized to send data to the Log Correlation Engine server. If there is a broken link icon, the client is not authorized to send data to the Log Correlation Engine server. To do this, right-click the row for the client or select the check box for the client, then click **Authorize** or **Revoke Authorization**.

Each client must have a policy assigned to it that specifies the appropriate data to send. The currently assigned policy appears in the **Policy** column. To change the assigned policy, select the client to edit and click the appropriate policy from the drop-down box. Search client policies by name by entering text into the Policy box. Click the **Submit** button to save the change. The policy updates on the client on its next connection.





## Tenable Log Correlation Engine Client Policies

The **Log Correlation Engine Client Policies** page contains a list of all the client policies currently available for use by Log Correlation Engine clients. The list contains the name of the policy, the operating system it is configured for use on, and the type of client the policy can be applied to.

Example policy files are available for use with the names default and beginning with **TNS-**. You can use these policy files as is or export them to be used as a basis for custom policy files. Tenable may update or change these example policy files without notice, so using them as is may return different results at a later time.

Use the **Add** button to add customized Log Correlation Engine Client policy files to the Log Correlation Engine server and make them available for use. The **Name** option is appended to the beginning of the file name and offers a description of the function or use of the policy file. The **OS Type** is used in the file name to easily identify the OS for which the policy is designed. The **Client Type** indicates the LCE Client for which the policy is written. The **Source** option is used to select and upload the custom policy file or type the policy file into the box. Click the **Submit** button to save the policy file and send it to the Log Correlation Engine server.

**Note:** The default and **TNS** prefixes should only be used by policies supplied by Tenable. If you use default or **TNS** as a prefix for custom policy files, they may be overwritten or manipulated.

Right-click or select the check box for a policy, then click **Export** to save the policy to a local drive. The file is in XML format, which you can edit with standard text or XML editors.

Right-click or select the check box for a policy, then click **View** to display the policy name and source of the policy in a window within Tenable Security Center. You cannot edit the information from within this window.

**Note:** For more information on creating Log Correlation Engine Client policy files, see the *Tenable Log Correlation Engine Client Guide*.



## Tenable OT Security Instances

Tenable OT Security protects industrial networks by providing industrial and critical infrastructure operations with visibility, security, and control to ensure safe facility operation while reducing overall risk. You can use Tenable Security Center to analyze Tenable OT Security asset and vulnerability data alongside your data from other scanners.

When you configure data synchronization from Tenable OT Security to Tenable Security Center, Tenable OT Security sends asset and vulnerability data to an agent repository in Tenable Security Center. Tenable OT Security communicates with Tenable Security Center using the Tenable Security Center API.

**Note:** It is important to restrict the data Tenable OT Security collects to only the desired host IP address ranges. For example, if Tenable OT Security collects information on 1100 hosts and Tenable Security Center is licensed for 1000 hosts, Tenable OT Security sends all of the data to Tenable Security Center and Tenable Security Center will indicate that you exceeded your host count. For more information, see [License Requirements](#).

Before you begin:

- Deploy Tenable OT Security, as described in the *Tenable OT Security User Guide*.
- Begin vulnerability assessment in Tenable OT Security, as described in the *Tenable OT Security User Guide*.

To fully configure data synchronization from Tenable OT Security to Tenable Security Center:

1. Add a designated agent repository for Tenable OT Security data in Tenable Security Center, as described in [Add a Repository](#).
2. Using the Tenable OT Security API, configure the Tenable Security Center integration to specify the sync schedule, import repository, and authentication.

What to do next:

- View scan results from Tenable OT Security, as described in [View Scan Results](#).
- View vulnerability data filtered by your Tenable OT Security repository, as described in [Vulnerability Analysis](#).



## Repositories

*Repositories* are databases within Tenable Security Center that contain vulnerability data. You can share repositories with users and organizations based on admin-defined assets. Repositories provide scalable and configurable data storage. Optionally, you can share repository data between multiple Tenable Security Centers.

**Note:** The maximum repository size is 64 GB. For best performance, Tenable recommends splitting repositories larger than 32 GB.

When adding a *local repository*, you designate storage within Tenable Security Center for different types of vulnerability data (identified by IPv4 addresses, IPv6 addresses, agents, or mobile scanners). Scanners attached to a Tenable Security Center populate your local repositories with vulnerability data. For more information, see [Local Repositories](#).

When adding an *external repository*, you access a local repository from another Tenable Security Center:

- Remote repositories allow you to share repository data from one Tenable Security Center deployment to your primary Tenable Security Center deployment via an SSH session.
- Offline repositories allow you to share repository data from one Tenable Security Center deployment to your primary Tenable Security Center deployment via manual export and import (a `.tar.gz` archive file). You can combine data from several repository files into a single offline repository by importing multiple files to the offline repository.

External repository data is static and used solely for reporting purposes. For more information, see [External Repositories](#).

For more information, see [Add a Repository](#) and [Manage Repositories](#). For information about Tenable Security Center repository data encryption, see [Encryption Strength](#).

**Tip:** If you need to remove data from a repository (for example, to remove retired asset data or to resolve a license issue), see the [knowledge base](#) article.



# Add a Repository

**Required User Role:** Administrator

For more information about repositories, see [Repositories](#).

To add a repository:

1. Log in to Tenable Security Center via the user interface.

2. Click **Repositories > Repositories**.

The Repositories page appears.

3. At the top of the table, click **Add**.

The **Add Repository** page appears.

4. Click the tile for the repository type you want to add.

The **Add Repository** page appears.

5. Configure the options for your repository type:

- [IPv4/IPv6 Repositories](#)
- [Mobile Repositories](#)
- [Agent Repositories](#)
- [Universal Repositories](#)
- [Remote Repositories](#)
- [Offline Repositories](#)

6. Click **Submit**.

Tenable Security Center saves your configuration.

What to do next:



- If you added an offline repository, export one or more repositories from your other Tenable Security Center as described in [Export a Repository](#).
- If you added an offline repository, import one or more exported repository files as described in [Import a Repository](#).



# Manage Repositories

**Required User Role:** Administrator

For more information, see [Repositories](#).

To manage your repositories:

1. Log in to Tenable Security Center via the user interface.
2. Click **Repositories** > **Repositories**.

The **Repositories** page appears.

3. To filter the repositories that appear on the page, apply a filter as described in [Apply a Filter](#).

4. To view details for a repository:

- a. Right-click the row for the repository you want to view.

The actions menu appears.

-or-

Select the check box for the repository you want to view.

The available actions appear at the top of the table.

- b. Click **View**.

The **View Repository** page appears. For more information, see [Repository Details](#).

5. To edit a repository:

- a. Right-click the row for the repository you want to edit.

The actions menu appears.

-or-

Select the check box for the repository you want to edit.

The available actions appear at the top of the table.

- b. Click **More** > **Edit**.



The **Edit Repository** page appears.

- c. Modify the repository options, as described in [IPv4/IPv6 Repositories](#), [Mobile Repositories](#), [Agent Repositories](#), [Universal Repositories](#), [Remote Repositories](#), or [Offline Repositories](#).
- d. Click **Submit**.

Tenable Security Center saves your configuration.

6. To export a repository, see [Export a Repository](#).
7. To import a repository file into an offline repository, see [Import a Repository](#).
8. To delete a repository, see [Delete a Repository](#).



## View Your Repositories

**Required User Role:** Administrator

You can view a list of all repositories on your Tenable Security Center. For more information, see [Repositories](#).

To view a list of your repositories:

1. Log in to Tenable Security Center via the user interface.
2. Click **Repositories** > **Repositories**.

The **Repositories** page appears.

3. View details about each repository.

- **Name** —The name of the repository.
- **Vulnerability Count** —The total number of vulnerability instances in the repository.

**Tip:** A vulnerability instance is a single instance of a vulnerability appearing on an asset, identified uniquely by plugin ID, port, and protocol.

- **IP/Device Count** —The total number of assets for which the repository contains vulnerability data.
- **Type** —The repository type.
- **Capacity** —(IPv4, IPv6, Agent, and Universal repositories only) The percentage of maximum available repository space you are currently using. The maximum repository size is 64 GB.

**Tip:** For best performance, Tenable recommends splitting repositories larger than 32 GB.

- **Last Updated** —The date and time the repository was last updated.





## View Repository Details

**Required User Role:** Administrator

You can view details for any repository. For more information, see [Repositories](#).

To view repository details:

1. Log in to Tenable Security Center via the user interface.

2. Click **Repositories > Repositories**.

The **Repositories** page appears.

3. Right-click the row for the repository you want to view.

The actions menu appears.

-or-

Select the check box for the repository you want to view.

The available actions appear at the top of the table.

4. Click **View**.

The **View Repository** page appears.

Section	Repository Type	Action
<b>General</b>	All	<p>View general information for the repository.</p> <ul style="list-style-type: none"><li>• <b>Name</b> —The repository name.</li><li>• <b>Description</b> —The repository description.</li><li>• <b>IP Count</b> —The total number of assets for which the repository contains vulnerability data.</li><li>• <b>Last Vuln Update</b> —The date and</li></ul>



Section	Repository Type	Action
		<p>time the repository was last updated.</p> <ul style="list-style-type: none"><li>• <b>Vulnerability Count</b> —The total number of vulnerability instances in the repository. <div data-bbox="959 485 1479 716" style="border: 1px solid green; padding: 5px;"><p><b>Tip:</b> A vulnerability instance is a single instance of a vulnerability appearing on an asset, identified uniquely by plugin ID, port, and protocol.</p></div></li><li>• <b>Repository Capacity</b> —(IPv4, IPv6, Agent, and Universal repositories only) The percentage of maximum available repository space you are currently using. The maximum repository size is 64 GB. <div data-bbox="959 1062 1479 1220" style="border: 1px solid green; padding: 5px;"><p><b>Tip:</b> For best performance, Tenable recommends splitting repositories larger than 32 GB.</p></div></li><li>• <b>Created</b> —The date the repository was created.</li><li>• <b>Last Modified</b> —The date the repository was last modified.</li><li>• <b>ID</b> —The repository ID.</li></ul>
<b>MDM</b>	Mobile	View a summary of your settings for the repository. For more information about a setting, see <a href="#">Mobile Repositories</a> .
<b>Data</b>	IPv4/IPv6, Agent,	View a summary of the repository data (for



Section	Repository Type	Action
	Remote, Offline, Universal	example, the IP address range). For more information, see: <ul style="list-style-type: none"><li>• <a href="#">IPv4/IPv6 Repositories</a></li><li>• <a href="#">Agent Repositories</a></li><li>• <a href="#">Universal Repositories</a></li><li>• <a href="#">Remote Repositories</a></li><li>• <a href="#">Offline Repositories</a></li></ul>
<b>Access</b>	All	View the name of the organizations with access to this repository.
<b>Advanced Settings</b>	IPv4/IPv6, Agent, Remote, Offline, Universal	View a summary of your settings for the repository. For more information about a setting, see: <ul style="list-style-type: none"><li>• <a href="#">IPv4/IPv6 Repositories</a></li><li>• <a href="#">Agent Repositories</a></li><li>• <a href="#">Universal Repositories</a></li><li>• <a href="#">Remote Repositories</a></li><li>• <a href="#">Offline Repositories</a></li></ul>
<b>Tenable.io Synchronization Data</b>	All supported for Tenable Lumin synchronization	View synchronization summary data: <ul style="list-style-type: none"><li>• <b>Status</b> —The status of the repository in Tenable Lumin synchronization:<ul style="list-style-type: none"><li>• <b>Finished</b> —The most recent synchronization that included this repository succeeded.</li><li>• <b>Not Synced</b> —The repository is</li></ul></li></ul>



Section	Repository Type	Action
		<p>not configured for Tenable Lumin synchronization.</p> <ul style="list-style-type: none"><li>• <b>Error</b> —An error occurred. For more information, see <a href="#">View Tenable Lumin Data Synchronization Logs</a>.</li><li>• <b>First Synchronization</b> —The date and time of the first synchronization of this repository.</li><li>• <b>Last Success</b> —The date and time of the most recent synchronization of this repository.</li><li>• <b>Last Failure</b> —The date and time of the most recent failed synchronization of this repository.</li></ul> <p>For more information about Tenable Lumin synchronization, see <a href="#">Tenable Lumin Synchronization</a>.</p>
<b>Vulnerability Data Lifetime</b>	IPv4/IPv6, Agent, Universal	<p>View the data expiration settings for the repository. For more information, see:</p> <ul style="list-style-type: none"><li>• <a href="#">IPv4/IPv6 Repositories</a></li><li>• <a href="#">Agent Repositories</a></li><li>• <a href="#">Universal Repositories</a></li></ul>



## Export a Repository

**Required User Role:** Administrator

You can export a repository from one Tenable Security Center and import it as an offline repository on another Tenable Security Center. You can export repositories via the Tenable Security Center user interface or the CLI. For more information, see [Offline Repositories](#).

**Note:** Depending on the size of the repository database, this file can be quite large. It is important to save the file to a location with sufficient free disk space.

**Tip:** If the repository you want to export has trend data enabled and you want to include trend data in your repository export, export the repository via the CLI. Repositories that you export via the user interface do not include trend data. For more information about trend data, see [IPv4/IPv6 Repositories](#), [Agent Repositories](#), and [Universal Repositories](#).

To export a repository via the user interface:

1. Log in to Tenable Security Center via the user interface.
2. Click **Repositories > Repositories**.

The **Repositories** page appears.

3. Right-click the row for the repository you want to export.

The actions menu appears.

-or-

Select the check box for the repository you want to export.

The available actions appear at the top of the table.

4. Click **Export**.

Tenable Security Center exports the repository.

To export a repository via the CLI:



1. Log in to Tenable Security Center via the command line interface (CLI).
2. Prepare the command you want to run.

```
/opt/sc/customer-tools/exportRepository.sh [repID] [trendingDays] [trendWithRaw]
```

Variable	Description
<i>repID</i>	The repository ID of the repository you want to export. To locate the repository ID, view the details for the repository, as described in <a href="#">View Repository Details</a> .
<i>trendingDays</i>	(IP, Agent, and Universal repositories only) The number of days of vulnerability trending data to include. To use the preconfigured repository setting, type <b>default</b> .  <b>Note:</b> The number of days of trending data included in the export cannot exceed the <b>Days Trending</b> setting for the repository or the number of days of trending data available for the repository. For example, if you request 30 days of trending data, but trending data has been enabled for only 15 days, then the export includes only 15 days of trending data. For more information about repository settings, see <a href="#">IPv4/IPv6 Repositories</a> , <a href="#">Agent Repositories</a> , and <a href="#">Universal Repositories</a> .
<i>trendWithRaw</i>	(IP, Agent, and Universal repositories only) Specify whether you want the export to include plugin output data: <b>yes</b> or <b>no</b> . To use the preconfigured repository setting, type <b>default</b> .

(Optional) To automatically overwrite an existing repository file with the same name, include the optional argument `-f`.

3. In the CLI in Tenable Security Center, run the export command.

For example:

```
/opt/sc/customer-tools/exportRepository.sh 1 default default -f
```

Tenable Security Center exports the repository.

What to do next:



- To import the repository to another Tenable Security Center, add an offline repository to that Tenable Security Center, as described in [Add a Repository](#).



## Import a Repository

**Required User Role:** Administrator

You can import one or more repository files to an offline repository. For more information, see [Offline Repositories](#).

**Note:** When importing the repository archive, the default maximum file import size is 360MB. This is specified by the `post_max_size` directive in `/opt/sc/support/etc/php.ini`. If larger file uploads are required, increase the default value.

Before you begin:

- Export one or more repository files from your other Tenable Security Center, as described in [Export a Repository](#).
- Add an offline repository, as described in [Add a Repository](#).

To import an exported repository to an offline repository:

1. Log in to Tenable Security Center via the user interface.
2. Click **Repositories** > **Repositories**.

The **Repositories** page appears.

3. Right-click the row for the offline repository you created.

The actions menu appears.

-or-

Select the check box for the offline repository you created.

The available actions appear at the top of the table.

4. Click **Upload** and browse to the file you want to upload.

Tenable Security Center imports the repository.





## Delete a Repository

**Required User Role:** Administrator

To delete a repository:

1. Log in to Tenable Security Center via the user interface.
2. Click **Repositories > Repositories**.

The **Repositories** page appears.

3. Select the repository you want to delete:

To delete a single repository:

- a. In the table, right-click the row for the repository you want to delete.

The actions menu appears.

- b. Click **Delete**.

To delete multiple repositories:

- a. In the table, select the check box for each repository you want to delete.

The available actions appear at the top of the table.

- b. At the top of the table, click **More > Delete**.

A confirmation window appears.

4. Click **Delete**.

Tenable Security Center deletes the repository.



---

## Local Repositories

---

When adding *local repositories*, you designate storage within Tenable Security Center for different types of vulnerability data. Scanners attached to a Tenable Security Center populate your local repositories with vulnerability data.

Tenable Security Center supports four types of local repositories: [IPv4/IPv6 Repositories](#), [Mobile Repositories](#), [Agent Repositories](#), and [Universal Repositories](#).

For more information, see [Repositories](#) and [Add a Repository](#).



## IPv4/IPv6 Repositories

These are the most common types of repositories used with Tenable Security Center. They store IPv4 and IPv6 data from active and passive scans. Data stored in local repositories can be shared between organizations and includes the full range of event and vulnerability metadata.

**Caution:** When creating Tenable Security Center IPv4 or IPv6 repositories, Log Correlation Engine event source IP address ranges must be included along with the vulnerability IP address ranges or the event data and event vulnerabilities are not accessible from the Tenable Security Center web interface.

For more information, see [Add a Repository](#).

### IP Repository Options

Option	Description
<b>General</b>	
Name	The repository name.
Description	(Optional) A description for the repository.
<b>Data</b>	
IP Ranges	Specifies the IP address range of vulnerability data you want to store in the repository.  Type the range as a comma-delimited list of IP addresses, IP address ranges, and/or CIDR blocks.
<b>Access</b>	
Organizations	Specifies which organizations have access to the vulnerability data stored in the repository.  If groups are configured for the organization, Tenable Security Center prompts you to grant or deny access to all of the groups in the organization. For more granular control, grant access within the settings for that group.
<b>Advanced Settings</b>	



Option	Description
<b>Generate Trend Data</b>	<p>When enabled, Tenable Security Center generates trend data by taking periodic snapshots of the cumulative database. Trend data is displayed in some Tenable Security Center tools (e.g., trending line charts and trending area charts).</p> <p>Tenable Security Center also produces differential data (snapshot comparison data), which improves performance when displaying trend data in Tenable Security Center tools.</p> <div data-bbox="440 632 1479 709" style="border: 1px solid green; padding: 5px;"><b>Tip:</b> Disable this option to reduce your disk space usage.</div>
<b>Days Trending</b>	<p>Specifies the number of days of cumulative vulnerability data that you want Tenable Security Center to display in dashboard and report vulnerability trending displays.</p>
<b>Enable Full Text Search</b>	<p>When enabled, Tenable Security Center includes vulnerability text in periodic snapshots of .nessus data for vulnerability trending purposes. For more information about the <b>Vulnerability Text</b> filter component, see <a href="#">Vulnerability Analysis Filter Components</a>.</p>
<b>Log Correlation Engine Correlation</b>	<p>Not supported for IPv6 repositories.</p> <p>The Log Correlation Engine server where you want Tenable Security Center to retrieve data. The data retrieved depends on the <b>Import Vulnerabilities</b> setting in your Log Correlation Engine server configuration:</p> <ul style="list-style-type: none"><li>• If <b>Import Vulnerabilities</b> is enabled, Tenable Security Center retrieves vulnerability data and Log Correlation Engine events.</li><li>• If <b>Import Vulnerabilities</b> is disabled, Tenable Security Center retrieves Log Correlation Engine events.</li></ul>
<b>Vulnerability Data Lifetime</b> (Data Expiration Settings)	
<b>Active</b>	<p>The number of days you want Tenable Security Center to retain active scan vulnerability data stored in IP repositories. The default value of this option is 365 days.</p>



Option	Description
<b>Passive</b>	The number of days you want Tenable Security Center to retain Tenable Nessus Network Monitor vulnerability data stored in IP repositories. The default value of this option is 7 days.
<b>Event</b>	(IPv4 repositories only) The number of days you want Tenable Security Center to retain Log Correlation Engine event data stored in IPv4 repositories. The default value of this option is 365 days.
<b>Compliance</b>	The number of days you want Tenable Security Center to retain audit compliance data stored in agent repositories. The default value of this option is 365 days.
<b>Mitigated</b>	The number of days you want Tenable Security Center to retain mitigated vulnerability data. The default value of this option is 365 days.



# Mobile Repositories

The mobile repository is a local type that stores data from various servers. For more information, see [Add a Repository](#).

- [General Options](#)
- [ActiveSync Options](#)
- [AirWatch MDM Options](#)
- [Apple Profile Manager Options](#)
- [Blackberry UEM Options](#)
- [Good MDM Options](#)
- [Microsoft Intune Options](#)
- [Mobile Iron Options](#)

## General Options

Configure the following options for all mobile repository types.

Option	Description	Default
<b>Name</b>	The repository name.	--
<b>Description</b>	(Optional) A description for the repository.	--
<b>Type</b>	The type of repository you want to configure. Your <b>Type</b> selection determines the type-specific options you must configure: <a href="#">ActiveSync Options</a> , <a href="#">AirWatch MDM Options</a> , <a href="#">Apple Profile Manager Options</a> , <a href="#">Blackberry UEM Options</a> , <a href="#">Good MDM Options</a> , <a href="#">Microsoft Intune Options</a> , or <a href="#">Mobile Iron Options</a> .	--
<b>Organizations</b>	Specifies which organizations have access to the vulnerability data stored in the repository.  If groups are configured for the organization, Tenable Secur-	--



Option	Description	Default
	ity Center prompts you to grant or deny access to all of the groups in the organization. For more granular control, grant access within the settings for that group.	

## ActiveSync Options

The following table describes the additional options to configure when creating an **ActiveSync** mobile repository.

Option	Description	Default
<b>Domain Controller</b>	The domain controller for ActiveSync.	--
<b>Domain</b>	The Windows domain for ActiveSync.	--
<b>Domain Username</b>	The username for the domain administrator's account that Tenable Security Center uses to authenticate to ActiveSync.	--
<b>Domain Password</b>	The password for the domain administrator user.	--
<b>Scanner</b>	Specifies which Tenable Nessus scanner Tenable Security Center uses when scanning the server. Tenable Security Center can only use one Tenable Nessus scanner to add data to a mobile repository.	--
<b>Update Schedule</b>	Specifies when Tenable Security Center scans the server to update the mobile repository. On each scan, Tenable Security Center removes the current data in the repository and replaces it with data from the latest scan.	Every day at 12:30 - 04:00

## AirWatch MDM Options

The following table describes the additional options to configure when creating an **AirWatch MDM** mobile repository.



Option	Description	Default
<b>AirWatch Environment API URL</b>	The SOAP URL or REST API URL you want Tenable Security Center to use to authenticate with AirWatch.	--
<b>Port</b>	The TCP port that AirWatch listens on for communications from Tenable Security Center.	443
<b>Username</b>	The username for the AirWatch user account Tenable Security Center uses to authenticate to AirWatch's REST API.	--
<b>Password</b>	The password for the AirWatch user.	--
<b>API Key</b>	The API key for the AirWatch REST API.	--
<b>HTTPS</b>	When enabled, Tenable Security Center connects using secure communication (HTTPS).  When disabled, Tenable Security Center connects using standard HTTP.	Enabled
<b>Verify SSL Certificate</b>	When enabled, Tenable Security Center verifies that the SSL certificate on the server is signed by a trusted CA.  <b>Tip:</b> If you are using a self-signed certificate, disable this setting.	Enabled
<b>Scanner</b>	Specifies which Tenable Nessus scanner Tenable Security Center uses when scanning the server. Tenable Security Center can only use one Tenable Nessus scanner to add data to a mobile repository.	--
<b>Update Schedule</b>	Specifies when Tenable Security Center scans the server to update the mobile repository. On each scan, Tenable Security Center removes the current data in the repository and replaces it with data from the latest scan.	Every day at 12:30 - 04:00

## Apple Profile Manager Options





The following table describes the additional options to configure when creating an **Apple Profile Manager** mobile repository.

Option	Description	Default
<b>Server</b>	The server URL Tenable Security Center uses to authenticate with Apple Profile Manager.	--
<b>Port</b>	The TCP port that Apple Profile Manager listens on for communications from Tenable Security Center.	443
<b>Username</b>	(Optional) The username for the Apple Profile Manager user account Tenable Security Center uses to authenticate to Apple Profile Manager.	--
<b>Password</b>	(Optional) The password for the Apple Profile Manager user.	--
<b>HTTPS</b>	When enabled, Tenable Security Center connects using secure communication (HTTPS).  When disabled, Tenable Security Center connects using standard HTTP.	Enabled
<b>Verify SSL Certificate</b>	When enabled, Tenable Security Center verifies that the SSL certificate on the server is signed by a trusted CA.  <b>Tip:</b> If you are using a self-signed certificate, disable this setting.	Enabled
<b>Scanner</b>	Specifies which Tenable Nessus scanner Tenable Security Center uses when scanning the server. Tenable Security Center can only use one Tenable Nessus scanner to add data to a mobile repository.	--
<b>Update Schedule</b>	Specifies when Tenable Security Center scans the server to update the mobile repository. On each scan, Tenable Security Center removes the current data in the repository and replaces it with data from the latest scan.	Every day at 12:30 - 04:00



## Blackberry UEM Options

The following table describes the additional options to configure when creating a **Blackberry UEM** mobile repository.

Option	Description	Default
<b>Blackberry UEM Hostname</b>	The hostname for the Blackberry UEM server.	--
<b>Blackberry UEM Port</b>	The port you want Tenable Security Center to use for authenticating to the Blackberry UEM server.	--
<b>Blackberry UEM Tenant</b>	The SRP ID value in Blackberry UEM.	--
<b>Blackberry UEM Domain</b>	(Optional) The domain name value in Blackberry UEM.	--
<b>Blackberry UEM Username</b>	The username for the Blackberry UEM user account Tenable Security Center uses to authenticate to Blackberry UEM.	--
<b>Blackberry UEM Password</b>	The password for the Blackberry UEM user.	--
<b>Blackberry UEM SSL</b>	When enabled, Tenable Security Center uses an encrypted connection to authenticate with Blackberry UEM.	Disabled
<b>Blackberry UEM Verify SSL Certificate</b>	When enabled, Tenable Security Center verifies that the SSL certificate on the server is signed by a trusted CA. <div style="border: 1px solid green; padding: 5px; margin-top: 10px;"><b>Tip:</b> If you are using a self-signed certificate, disable this setting.</div>	Disabled
<b>Scanner</b>	Specifies which Tenable Nessus scanner Tenable Security Center uses when scanning the server. Tenable Security Center can only use one Tenable Nessus scanner to add data to a mobile repository.	--
<b>Update Schedule</b>	Specifies when Tenable Security Center scans the server	Every day at



Option	Description	Default
	to update the mobile repository. On each scan, Tenable Security Center removes the current data in the repository and replaces it with data from the latest scan.	12:30 - 04:00

## Good MDM Options

The following table describes the additional options to configure when creating a **Good MDM** mobile repository.

Option	Description	Default
<b>Server</b>	The server URL Tenable Security Center uses to authenticate with Good MDM.	--
<b>Port</b>	The TCP port that Good MDM listens on for communications from Tenable Security Center.	--
<b>Domain</b>	The domain name for Good MDM.	--
<b>Username</b>	The username for the Good MDM user account Tenable Security Center uses to authenticate to Good MDM.	--
<b>Password</b>	The password for the Good MDM user.	--
<b>HTTPS</b>	When enabled, Tenable Security Center connects using secure communication (HTTPS).  When disabled, Tenable Security Center connects using standard HTTP.	Enabled
<b>Verify SSL Certificate</b>	When enabled, Tenable Security Center verifies that the SSL certificate on the server is signed by a trusted CA.  <b>Tip:</b> If you are using a self-signed certificate, disable this setting.	Enabled
<b>Scanner</b>	Specifies which Tenable Nessus scanner Tenable Security Center uses when scanning the server. Tenable Secur-	--



Option	Description	Default
	ity Center can only use one Tenable Nessus scanner to add data to a mobile repository.	
<b>Update Schedule</b>	Specifies when Tenable Security Center scans the server to update the mobile repository. On each scan, Tenable Security Center removes the current data in the repository and replaces it with data from the latest scan.	Every day at 12:30 - 04:00

## Microsoft Intune Options

The following table describes the additional options to configure when creating a **Microsoft Intune** mobile repository.

Option	Description	Default
<b>Intune Tenant</b>	The Microsoft Azure Directory value in your Microsoft Intune registration.	--
<b>Intune Client</b>	The Microsoft Azure Application value generated during your Microsoft Intune registration.	--
<b>Intune Secret</b>	The Microsoft Azure client secret key.	--
<b>Intune Username</b>	The username for the Microsoft Intune user account Tenable Security Center uses to authenticate to Microsoft Intune.	--
<b>Intune Password</b>	The password for the Microsoft Intune user.	--
<b>Scanner</b>	Specifies which Tenable Nessus scanner Tenable Security Center uses when scanning the server. Tenable Security Center can only use one Tenable Nessus scanner to add data to a mobile repository.	--
<b>Update Schedule</b>	Specifies when Tenable Security Center scans the server to update the mobile repository. On each scan, Tenable Security Center removes the current data in the repository and replaces it with data from the latest scan.	Every day at 12:30 - 04:00



## Mobile Iron Options

The following table describes the additional options to configure when creating a **Mobile Iron** mobile repository.

Option	Description	Default
<b>MobileIron VSP Admin Portal URL</b>	The server URL Tenable Security Center uses to authenticate to the MobileIron administrator portal.	--
<b>VSP Admin Portal Port</b>	(Optional) The TCP port that the MobileIron administrator portail listens on for communications from Tenable Security Center.	--
<b>MobileIron Port</b>	The TCP port that MobileIron listens on for communications from Tenable Security Center.	443
<b>Username</b>	The username for the MobileIron administrator account Tenable Security Center uses to authenticate to MobileIron.	--
<b>Password</b>	The password for the MobileIron administrator user.	--
<b>HTTPS</b>	When enabled, Tenable Security Center connects using secure communication (HTTPS).  When disabled, Tenable Security Center connects using standard HTTP.	Enabled
<b>Verify SSL Certificate</b>	When enabled, Tenable Security Center verifies that the SSL certificate on the server is signed by a trusted CA.  <b>Tip:</b> If you are using a self-signed certificate, disable this setting.	Enabled
<b>Scanner</b>	Specifies which Tenable Nessus scanner Tenable Security Center uses when scanning the server. Tenable Security Center can only use one Tenable Nessus scanner to add data to a mobile repository.	--
<b>Update Schedule</b>	Specifies when Tenable Security Center scans the server	Every day



Option	Description	Default
	to update the mobile repository. On each scan, Tenable Security Center removes the current data in the repository and replaces it with data from the latest scan.	at 12:30 - 04:00



## Agent Repositories

Agent repositories can store data from Tenable Nessus Agents (identified by agent ID) or Tenable OT Security (identified by Tenable OT Security UUID).

An agent ID uniquely identifies agent-detected assets that may share a common IP address.

Tenable OT Security assigns UUIDs to assets to uniquely identify them, since not all operational technology assets have IP addresses. Then, Tenable Security Center uses the UUIDs to uniquely identify Tenable OT Security data in Tenable Security Center. For more information about viewing Tenable OT Security data in Tenable Security Center, see [Tenable OT Security Instances](#).

For more information, see [Add a Repository](#).

### Agent Repository Options

Option	Description
<b>General</b>	
<b>Name</b>	The repository name.
<b>Description</b>	(Optional) A description for the repository.
<b>Access</b>	
<b>Organizations</b>	Specifies which organizations have access to the vulnerability data stored in the repository.  If groups are configured for the organization, Tenable Security Center prompts you to grant or deny access to all of the groups in the organization. For more granular control, grant access within the settings for that group.
<b>Advanced Settings</b>	
<b>Generate Trend Data</b>	When enabled, Tenable Security Center generates trend data by taking periodic snapshots of the cumulative database. Trend data is displayed in some Tenable Security Center tools (e.g., trending line charts and trending area charts).



Option	Description
	<p>Tenable Security Center also produces differential data (snapshot comparison data), which improves performance when displaying trend data in Tenable Security Center tools.</p> <p><b>Tip:</b> Disable this option to reduce your disk space usage.</p>
<b>Days Trending</b>	Specifies the number of days of cumulative vulnerability data that you want Tenable Security Center to display in dashboard and report vulnerability trending displays.
<b>Enable Full Text Search</b>	When enabled, Tenable Security Center includes vulnerability text in periodic snapshots of .nessus data for vulnerability trending purposes. For more information about the <b>Vulnerability Text</b> filter component, see <a href="#">Vulnerability Analysis Filter Components</a> .
<b>Vulnerability Data Lifetime (Data Expiration Settings)</b>	
<b>Active</b>	The number of days you want Tenable Security Center to retain agent scan vulnerability data stored in agent repositories. The default value of this option is 365 days.
<b>Compliance</b>	The number of days you want Tenable Security Center to retain audit compliance data stored in agent repositories. The default value of this option is 365 days.
<b>Mitigated</b>	The number of days you want Tenable Security Center to retain mitigated vulnerability data. The default value of this option is 365 days.





## Universal Repositories

Universal repositories can store data from Tenable Nessus and Tenable Nessus Agent scans, as well as IPv4 and IPv6 data from Tenable Nessus Network Monitor, and Log Correlation Engine scans.

Tenable Security Center assigns UUIDs to assets to uniquely identify vulnerability data in universal repositories, since not all operational technology assets have IP addresses or Tenable UUIDs.

For more information, see [Add a Repository](#).

### Universal Repository Options

Option	Description
<b>General</b>	
<b>Name</b>	The repository name.
<b>Description</b>	(Optional) A description for the repository.
<b>Data</b>	
<b>IP Ranges</b>	<p>Specifies the IP address range of vulnerability data you want to store in the repository.</p> <p>Type the range as a comma-delimited list of IP addresses, IP address ranges, and/or CIDR blocks.</p> <div style="border: 1px solid #0070C0; padding: 5px;"><b>Note:</b> Agent scans into universal repositories are not restricted by IP range.</div>
<b>Access</b>	
<b>Organizations</b>	<p>Specifies which organizations have access to the vulnerability data stored in the repository.</p> <p>If groups are configured for the organization, Tenable Security Center prompts you to grant or deny access to all of the groups in the organization. For more granular control, grant access within the settings for that group.</p>
<b>Advanced Settings</b>	



Option	Description
<b>Generate Trend Data</b>	<p>When enabled, Tenable Security Center generates trend data by taking periodic snapshots of the cumulative database. Trend data is displayed in some Tenable Security Center tools (e.g., trending line charts and trending area charts).</p> <p>Tenable Security Center also produces differential data (snapshot comparison data), which improves performance when displaying trend data in Tenable Security Center tools.</p> <div style="border: 1px solid green; padding: 5px;"><b>Tip:</b> Disable this option to reduce your disk space usage.</div>
<b>Days Trending</b>	<p>Specifies the number of days of cumulative vulnerability data that you want Tenable Security Center to display in dashboard and report vulnerability trending displays.</p>
<b>Enable Full Text Search</b>	<p>When enabled, Tenable Security Center includes vulnerability text in periodic snapshots of .nessus data for vulnerability trending purposes. For more information about the <b>Vulnerability Text</b> filter component, see <a href="#">Vulnerability Analysis Filter Components</a>.</p>
<b>Vulnerability Data Lifetime (Data Expiration Settings)</b>	
<b>Active</b>	<p>The number of days you want Tenable Security Center to retain active scan vulnerability data stored in universal repositories. The default value of this option is 365 days.</p>
<b>Passive</b>	<p>The number of days you want Tenable Security Center to retain passive scan vulnerability data stored in universal repositories. The default value of this option is 7 days.</p>
<b>Event</b>	<p>The number of days you want Tenable Security Center to retain event data stored in universal repositories. The default value of this option is 365 days.</p>
<b>Compliance</b>	<p>The number of days you want Tenable Security Center to retain audit compliance data stored in universal repositories. The default value of this option is 365 days.</p>



Option	Description
<b>Mitigated</b>	The number of days you want Tenable Security Center to retain mitigated vulnerability data stored in universal repositories. The default value of this option is 365 days.



---

## External Repositories

---

When adding an *external repository*, you access a local repository from another Tenable Security Center:

- Offline repositories allow you to share repository data from one Tenable Security Center deployment to your primary Tenable Security Center deployment via manual export and import (a `.tar.gz` archive file). You can combine data from several repository files into a single offline repository by importing multiple files to the offline repository.
- Remote repositories allow you to share repository data from one Tenable Security Center deployment to your primary Tenable Security Center deployment via an SSH session.

External repository data is static and used solely for reporting purposes. For more information, see [Offline Repository Options](#) and [Remote Repositories](#).

For more information, see [Repositories](#) and [Add a Repository](#).



## Offline Repositories

Offline repositories allow you to share repository data from one Tenable Security Center deployment to your primary Tenable Security Center deployment via manual export and import (a `.tar.gz` archive file). You can combine data from several repository files into a single offline repository by importing multiple files to the offline repository.

Offline repositories are particularly useful to export data from air-gapped instances of Tenable Security Center. For more information, see [Considerations for Air-Gapped Environments](#).

**Note:** You cannot set an offline repository as the **Import Repository** for active scans. You can only use offline repository data for reporting purposes.

To fully configure an offline repository:

1. [Add an offline repository](#) to your primary Tenable Security Center deployment.
2. [Export](#) one or more repositories from your other Tenable Security Center deployment.
3. [Import](#) one or more repositories to the offline repository on your primary Tenable Security Center deployment.

## Offline Repository Options

Option	Description
<b>General</b>	
<b>Name</b>	The repository name.
<b>Description</b>	(Optional) A description for the repository.
<b>Access</b>	
<b>Data Type</b>	The type of data in the other Tenable Security Center repository: <b>IPv4</b> , <b>IPv6</b> , <b>Mobile</b> , <b>Agent</b> , or <b>Universal</b> .
<b>IP Ranges</b>	If the <b>Data Type</b> is <b>IPv4</b> or <b>IPv6</b> , specifies the IP address range of vulnerability data that you want to view in the offline repository. For example, to view all data from the exported repository file, specify a range that includes all data in that repository.



Option	Description
	<p>Type the range as a comma-delimited list of IP addresses, IP address ranges, and/or CIDR blocks.</p> <p>For more information, see <a href="#">IPv4/IPv6 Repositories</a>.</p>
<b>Type</b>	<p>If the <b>Data Type</b> is <b>Mobile</b>, the type of mobile repository: <b>ActiveSync</b>, <b>AirWatch MDM</b>, <b>Apple Profile Manager</b>, <b>Blackberry UEM</b>, <b>Good MDM</b>, <b>Microsoft Intune</b>, or <b>Mobile Iron</b>.</p> <p>For more information, see <a href="#">Mobile Repositories</a>.</p>
<b>Access</b>	
<b>Organizations</b>	<p>Specifies which organizations have access to the vulnerability data stored in the repository.</p> <p>If groups are configured for the organization, Tenable Security Center prompts you to grant or deny access to all of the groups in the organization. For more granular control, grant access within the settings for that group.</p>
<b>Advanced Settings</b>	
<b>Generate Trend Data</b>	<p>When enabled, Tenable Security Center generates trend data by taking periodic snapshots of the cumulative database. Trend data is displayed in some Tenable Security Center tools (e.g., trending line charts and trending area charts).</p> <p>Tenable Security Center also produces differential data (snapshot comparison data), which improves performance when displaying trend data in Tenable Security Center tools.</p> <div data-bbox="440 1562 1479 1640" style="border: 1px solid green; padding: 5px;"><b>Tip:</b> Disable this option to reduce your disk space usage.</div>
<b>Days Trending</b>	<p>Specifies the number of days of cumulative vulnerability data that you want Tenable Security Center to display in dashboard and report vulnerability trending displays.</p>



Option	Description
<b>Enable Full Text Search</b>	When enabled, Tenable Security Center includes vulnerability text in periodic snapshots of .nessus data for vulnerability trending purposes. For more information about the <b>Vulnerability Text</b> filter component, see <a href="#">Vulnerability Analysis Filter Components</a> .



## Remote Repositories

Remote repositories allow you to share repository data from one Tenable Security Center deployment to your primary Tenable Security Center deployment via an SSH session.

**Note:** You cannot set a remote repository as the **Import Repository** for active scans. You can use remote repository data only for reporting purposes.

**Note:** If your remote repository exists on a Tenable Security Center running 5.19.x or later, upgrade your primary Tenable Security Center deployment to Tenable Security Center 5.19.x or later.

For more information, see [Add a Repository](#).

To use tiered remote repositories for large enterprise deployments of Tenable Security Center, see [Tiered Remote Repositories](#).

Option	Description
<b>General</b>	
<b>Name</b>	The repository name.
<b>Description</b>	(Optional) A description for the repository.
<b>Remote Tenable Security Center</b>	
<b>Host</b>	The IP address for the host you want to synchronize with to obtain repository data. After you type the IP address: <ol style="list-style-type: none"><li>1. Click <b>Request Repositories</b>.</li><li>2. Type the username and password for an administrator account on the remote Tenable Security Center.</li></ol> The Tenable Security Center deployments exchange SSH keys, and the system populates the <b>Repository</b> list with all available repositories from the remote Tenable Security Center.
<b>Repository</b>	The remote repository you want to collect IP addresses and vulnerability data from.
<b>Update Schedule</b>	Sets the schedule for the remote server to be queried for updated inform-





Option	Description
	ation.
<b>Access</b>	
<b>Organizations</b>	<p>Specifies which organizations have access to the vulnerability data stored in the repository.</p> <p>If groups are configured for the organization, Tenable Security Center prompts you to grant or deny access to all of the groups in the organization. For more granular control, grant access within the settings for that group.</p>



## Tiered Remote Repositories

Remote repositories allow you to share repository data from one Tenable Security Center deployment to your primary Tenable Security Center deployment via an SSH session.

A *tiered remote repository* configuration uses remote repositories to share data between multiple Tenable Security Center instances.

- If you plan to support 100,000-249,999 hosts, Tenable recommends a tiered remote repository configuration.
- If you plan to support 250,000 or more hosts, Tenable **requires** a tiered remote repository configuration.

Tiered Tenable Security Center instances perform informal roles in your overall Tenable Security Center deployment. Tenable recommends at least one designated reporting Tenable Security Center and an additional Tenable Security Center instance for every 100,000 to 150,000 hosts on your network.

- A *scanning tier* Tenable Security Center optimizes scanning by managing scan jobs across your attached scanners. Scanning tier Tenable Security Center instances prioritize efficient collection of scan data.
- A *reporting tier* Tenable Security Center optimizes dashboards and reporting by centralizing the data collected by scanning tier Tenable Security Center instances.

**Note:** Your scanning tier and reporting tier Tenable Security Center instances must be running the same Tenable Security Center version.

Without a tiered remote repository configuration, enterprise-scale scanning and analysis may cause performance issues on a single Tenable Security Center. Tiered remote repositories optimize your analysis and report generation without negatively impacting scanning performance.

For more information, see [Configure Tiered Remote Repositories](#).

**Tip:** Configuring tiered remote repositories does not allow you to monitor the status of scanning tier Tenable Security Center instances. To monitor the status of multiple Tenable Security Center instances, connect your Tenable Security Center instances to Tenable Security Center Director. For more information about Tenable Security Center Director, see the *Tenable Security Center Director User Guide*.



## Configure Tiered Remote Repositories

You may want to configure tiered remote repositories in large deployments of Tenable Security Center. For more information, see [Tiered Remote Repositories](#).

To configure a tiered remote repository deployment:

1. On the scanning tier Tenable Security Center instance, [create one or more repositories](#) for storing scan result data.

**Note:** To view trend data for scanning tier Tenable Security Center instances on your reporting tier Tenable Security Center instance, enable the **Generate Trend Data** option for each repository on your scanning tier Tenable Security Center instances. For more information, see [Agent Repositories](#) and [IPv4/IPv6 Repositories](#).

2. On the scanning tier Tenable Security Center instance, [run scans](#) to populate the repositories with data.
3. On the reporting tier Tenable Security Center instance, [create a remote repository](#) for each repository on your scanning tier Tenable Security Center instance.

The reporting tier Tenable Security Center syncs scan result data from the scanning tier Tenable Security Center repositories.



## Active Scans

In active scanning, the scanner sends packets to a remote target to provide a snapshot of network services and applications. Tenable Security Center compares this data to a plugin database to determine if any vulnerabilities are present. Tenable Security Center can also use a scanner located outside the local network to simulate what an external entity might see.

For more information about supported active scanner types (Tenable Nessus and Tenable Vulnerability Management deployments) in Tenable Security Center, see [Tenable Nessus Scanners](#).

You can use credentialed Tenable Nessus scans, a type of active scanning, to perform highly accurate and rapid patch, configuration, and vulnerability audits on Unix, Windows, Cisco, and database systems by actually logging in to the target system with provided credentials. Credentialed scans can also enumerate all UDP and TCP ports in just a few seconds. Tenable Security Center can manage these credentials securely across thousands of different systems and also share the results of these audits only with users who need to access them.

For more information, see [Manage Active Scans](#) and [Active Scan Settings](#).

To fully configure active scans using a Tenable Nessus or Tenable Vulnerability Management scanner:

1. If you are configuring a Tenable Nessus scanner (not a Tenable Vulnerability Management deployment), configure scanning in Tenable Nessus, as described in [Scans](#) in the *Tenable Nessus User Guide*.

**Note:** For information about credentialed scanning in Tenable Nessus, see [Credentialed Checks](#) in the *Tenable Nessus User Guide*.

2. Add the Tenable Nessus scanner or your Tenable Vulnerability Management deployment in Tenable Security Center, as described in [Tenable Nessus Scanners](#).
3. Add a scan zone in Tenable Security Center, as described in [Add a Scan Zone](#).
4. Add a repository for the scan data in Tenable Security Center, as described in [Add a Repository](#).
5. Create active scan objects in Tenable Security Center, as described in:



- a. [Add a Template-Based Asset](#) or [Add a Custom Asset](#).
  - b. [Add Credentials](#).
  - c. [Add a Template-Based Audit File](#) or [Add a Custom Audit File](#).
  - d. [Add a Scan Zone](#).
  - e. [Add a Scan Policy](#).
6. Add an active scan in Tenable Security Center, as described in [Add an Active Scan](#).

What to do next:

- View scan results, as described in [Scan Results](#).
- View vulnerability data by IP address, as described in [Vulnerability Analysis](#).

## Special Active Scans

### Diagnostic Scans

If you experience issues with an active scan, Tenable Support may ask you to run a diagnostic scan to assist with troubleshooting. After Tenable Security Center runs the diagnostic scan, download the diagnostic file and send it to Tenable Support.

For more information, see [Run a Diagnostic Scan](#).

### Remediation Scans

You can run a remediation scan to run a followup active scan against existing active scan results. A remediation scan evaluates a specific plugin against a specific target or targets where the related vulnerability was present in your earlier active scan.

For more information, see [Launch a Remediation Scan](#).



## Add an Active Scan

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information about active scan options, see [Active Scan Settings](#).

Before you begin:

- Confirm you are running Tenable Nessus 6.3.6 or later.
- Confirm you understand the complete scanning configuration process, as described in [Active Scans](#).

To add an active scan:

1. Log in to Tenable Security Center via the user interface.
2. Click **Scans > Active Scans**.  
The **Active Scans** page appears.
3. Click **Add**.  
The **Add Active Scan** page appears.
4. Click **General**.
5. Type a **Name** for the scan.
6. (Optional) Type a **Description** for the scan.
7. Select a **Policy** for the scan.
8. (Optional) If you want to schedule the scan to run automatically, select a **Schedule** for the scan.
9. Click **Settings**.  
The **Settings** tab appears.
10. If prompted, select a preconfigured **Scan Zone** for the scan.
11. Select an **Import Repository** for the scan.



12. Select a **Scan Timeout Action** for the scan.
13. Select a **Rollover Schedule** for the scan.
14. Enable or disable the **Advanced** options.
15. Click **Targets**.

The **Targets** tab appears.

16. Select a **Target Type** for the scan.
17. Select one or more **Assets** and **IPs / DNS Names** for the scan.
18. (Optional) To configure credentialed scanning, do the following:

- a. Click **Credentials**.

The **Credentials** tab appears.

- b. Click **Add Credential**.
- c. In the drop-down boxes, select a credential type and a preconfigured credential.
- d. Click the check mark to save your selection.

19. (Optional) If you want to configure multiple credentials for the active scan, repeat step 19.

**Note:** When running an active scan, Tenable Security Center attempts authentication using the newest credentials added by an Administrator user. If the newest Administrator-added credentials do not match, Tenable Security Center attempts authentication with older Administrator-added credentials.

Then, if no Administrator-added credentials match, Tenable Security Center attempts to authenticate using the newest credentials added by an organizational user. If the newest organizational user-added credentials do not match, Tenable Security Center attempts authentication with older organizational user-added credentials.

If no credentials match, the scan runs without credentialed access.

20. (Optional) To configure post-scan options, do the following:
  - a. Click **Post Scan**.

The **Post Scan** tab appears.



- b. To configure automatic report generation, click **Add Report**.
- c. Select the report you want to run after the scan completes, as described in [Add a Report to a Scan](#).

21. Click **Submit**.

Tenable Security Center saves your configuration.





## Configure vSphere Scanning

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

You can configure a scan policy to scan the following virtual environments:

- ESXi/vSphere managed by vCenter
- ESXi/vSphere that is not managed by vCenter
- Virtual machines

### Scanning ESXi/vSphere Not Managed by vCenter

To configure an ESXi/vSphere scan that is not managed by vCenter:

1. Begin configuring a scan policy that supports credentialed access, as described in [Add a Scan Policy](#). For more information about authentication options in scan policies, see [Authentication Options](#).
2. In the left navigation menu, click **Authentication**.  
The **Authentication** tab appears.
3. Click **Add Authentication Settings**.  
The authentication options appear.
4. In the first **Type** drop-down box, select **Miscellaneous**.
5. In the second **Type** drop-down box, select **VMware ESX SOAP API**.
6. Click **Select**.  
The VMware ESX SOAP API options appear. For more information, see [VMware ESX SOAP API](#).
7. In the **Username** box, type the username associated with the local ESXi account.
8. In the **Password** box, type the password associated with the username you provided.
9. If your vCenter host includes an SSL certificate (not a self-signed certificate), disable the **Do not verify SSL Certificate** toggle.



10. Click the  button.

Tenable Security Center applies the VMware ESX SOAP API authentication options to the scan policy.

What to do next:

- Reference the scan policy in an active scan configuration, as described in [Add an Active Scan](#).


## Scanning vCenter Managed ESXi/ vSpheres

**Note:** The SOAP API requires a vCenter admin account with read and write permissions. The REST API requires a vCenter admin account with read permissions, and a VMware vSphere Lifecycle manager account with read permissions.

To configure an ESXi/vSphere scan managed by vCenter:

1. Begin configuring a scan policy that supports credentialed access, as described in [Add a Scan Policy](#). For more information about authentication options in scan policies, see [Authentication Options](#).
2. In the left navigation menu, click **Authentication**.  
The **Authentication** tab appears.
3. Click **Add Authentication Settings**.  
The authentication options appear.
4. In the first **Type** drop-down box, select **Miscellaneous**.
5. In the second **Type** drop-down box, select **VMware vCenter SOAP API**.
6. Click **Select**.  
The VMware vCenter SOAP API options appear. For more information, see [VMware vCenter SOAP API](#).
7. In the **vCenter Host** box, type the IP address of the vCenter host.
8. In the **vCenter Port** box, type the port for the vCenter host.
9. In the **Username** box, type the username associated with the local ESXi account.



10. In the **Password** box, type the password associated with the username you provided.
11. If the vCenter host is not SSL enabled, disable the **HTTPS** toggle.
12. If your vCenter host includes an SSL certificate (not a self-signed certificate), enable the **Verify SSL Certificate** toggle.
13. Click the  button.

Tenable Security Center applies the VMware vCenter SOAP API authentication options to the scan policy.

What to do next:

- Reference the scan policy in an active scan configuration, as described in [Add an Active Scan](#).

## Scanning Virtual Machines

You can scan virtual machines just like any other host on the network. Be sure to include the IP addresses of virtual machines you want to scan in your scan targets. For more information, see [Add an Active Scan](#).



# Manage Active Scans

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information about active scans, see [Active Scans](#).

To manage active scans:

1. Log in to Tenable Security Center via the user interface.
2. Click **Scans > Active Scans**.

The **Active Scans** page appears.

3. To filter the scans that appear on the page, apply a filter as described in [Apply a Filter](#).
4. To start or pause a scan, see [Start or Pause a Scan](#).
5. To suspend or resume a scheduled scan, see [Suspend or Resume a Scheduled Active Scan](#).

6. To view details for a scan:

- a. Right-click the row for the scan.

The actions menu appears.

-or-

Select the check box for the scan.

The available actions appear at the top of the table.

- b. Click **View**.

The **View Active Scan** page appears.

7. To edit a scan:

- a. Right-click the row for the scan.

The actions menu appears.

-or-



Select the check box for the scan.

The available actions appear at the top of the table.

- b. Click **Edit**.

The **Edit Active Scan** page appears.

- c. Modify the scan options.
- d. Click **Submit**.

Tenable Security Center saves your configuration.

#### 8. To copy a scan:

- a. Right-click the row for the scan.

The actions menu appears.

-or-

Select the check box for the scan.

The available actions appear at the top of the table.

- b. Click **Copy**.

Tenable Security Center creates a copy of the scan.

#### To copy multiple scans:

- a. In the table, select the check box for each scan you want to copy.

The available actions appear at the top of the table.

- b. At the top of the table, click **Copy**.

A confirmation window appears.

- c. Click **Copy**.

Tenable Security Center creates a copy of the scan.

9. To run a diagnostic scan, see [Run a Diagnostic Scan](#).

#### 10. To delete a scan:



- a. In the table, right-click the row for the scan.

The actions menu appears.

- b. Click **Delete**.

A confirmation window appears.

- c. Click **Delete**.

Tenable Security Center deletes the scan.

#### To delete multiple scans:

- a. In the table, select the check box for each scan you want to delete.

The available actions appear at the top of the table.

- b. At the top of the table, click **Delete**.

A confirmation window appears.

- c. Click **Delete**.

Tenable Security Center deletes the scans.



## Start or Pause a Scan

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

To start or pause an active scan, agent scan, or agent synchronization job:

1. Log in to Tenable Security Center.
2. Click one of the following:
  - **Scans > Active Scans** (to manage active scans)
  - **Scans > Agent Synchronization Jobs** (to manage agent synchronization jobs)
  - **Scans > Agent Scans** (to manage agent scans)
  - **Scans > Scan Results** (to manage a scan from the results page).
3. Do one of the following:
  - To pause the scan or synchronization job, select the check box for the scan or synchronization job, and click **Pause** at the top of the table.
  - To start the scan or synchronization job, select the check box for the scan or synchronization job, and click **Launch** at the top of the table.



## Suspend or Resume a Scheduled Active Scan

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

If you suspend a scheduled active scan, Tenable Security Center stops launching new scans for that active scan configuration. Tenable Security Center does not disrupt scans already in progress or prevent users from launching scans on demand.

If you resume a suspended active scan, Tenable Security Center resumes launching scans on the schedule configured for that active scan.

For more information, see [Active Scans](#).

Before you begin:

- Configure a scheduled active scan, as described in [Add an Active Scan](#).

To suspend or resume a scheduled active scan:

1. Log in to Tenable Security Center via the user interface.
2. Click **Scans > Active Scans**.

The **Active Scans** page appears.

3. Right-click the row for the scheduled scan you want to suspend or resume.

The actions menu appears.

-or-

Select the check box for the scheduled scan you want to suspend or resume.

The available actions appear at the top of the table.

4. Click **Suspend Schedule** or **Resume Schedule**.

The page updates to reflect the scan schedule status. When a scan is suspended, Tenable Security Center displays a line through the **Start Time** and **Schedule** values.





## Run a Diagnostic Scan

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

If you experience issues with an active scan, Tenable Support may ask you to run a diagnostic scan to assist with troubleshooting. After Tenable Security Center runs the diagnostic scan, download the diagnostic file and send it to Tenable Support.

Before you begin:

- Add an active scan, as described in [Add an Active Scan](#).
- Confirm the scanner associated with the active scan is running a supported version of Tenable Nessus. For minimum Tenable Nessus scanner version requirements, see the [Tenable Security Center Release Notes](#) for your version.

To run a diagnostic scan:

1. Click **Scans > Active Scans**.
2. Right-click the row for the scan where you want to run a diagnostic scan.

The actions menu appears.

-or-

Select the check box for the scan where you want to run a diagnostic scan.

The available actions appear at the top of the table.

3. Click **Run Diagnostic Scan**.

**Note:** You must resolve repository errors before running a diagnostic scan.

4. In the **Diagnostic Target** box, type a target as a single IPv4 address, IPv6 address, or host-name. The target must also be specified in the active scan's **Targets**.
5. In the **Diagnostic Password** box, type a password to secure the diagnostic file.
6. Click **Submit**.



The diagnostic scan runs and finishes.

7. Click **Scans > Scan Results**.

8. Locate the diagnostic scan and confirm that the scan finished without errors.

9. Right-click the row for the diagnostic scan result.

The actions menu appears.

-or-

Select the check box for the diagnostic scan result.

The available actions appear at the top of the table.

10. Click **Download Diagnostic Info**.

The diagnostic scan file downloads.



# Active Scan Settings

For more information, see [Add an Active Scan](#).

- [General Options](#)
- [Settings Options](#)
- [Targets Options](#)
- [Credentials Options](#)
- [Post Scan Options](#)

## General Options

Parameter	Description
<b>General</b>	
<b>Name</b>	The scan name that is associated with the scan's results and may be any name or phrase (for example, <i>SystemA</i> , <i>DMZ Scan</i> , or <i>Daily Scan of the Web Farm</i> ).
<b>Description</b>	Descriptive information related to the scan.
<b>Policy</b>	The policy on which you want to base the scan. You can scroll through the list, or search by entering text in the search box at the top of the list of available policies.
<b>Schedule</b>	
<b>Schedule</b>	<p>The frequency you want to run the scan.</p> <ul style="list-style-type: none"><li>• <b>Now</b> specifies that you want Tenable Security Center to launch the scan immediately without saving the configuration for later.</li></ul> <div style="border: 1px solid #0070C0; padding: 5px; margin: 10px 0;"><p><b>Note:</b> Scans configured to run <b>Now</b> do not appear on the <b>Active Scans</b> page.</p></div> <ul style="list-style-type: none"><li>• <b>Once</b> specifies that you want Tenable Security Center to launch the scan at the specified time without saving the configuration for later.</li></ul>



Parameter	Description
	<p><b>Note:</b> Scans configured to run <b>Once</b> do not appear on the <b>Active Scans</b> page.</p> <ul style="list-style-type: none"><li>• <b>Daily, Weekly, or Monthly</b> specifies that you want Tenable Security Center to launch the scan at a scheduled interval.</li></ul> <p><b>Note:</b> If you schedule your scan to repeat monthly, Tenable recommends setting a start date no later than the 28th day. If you select a start date that does not exist in some months (e.g., the 29th), Tenable Security Center cannot run the scan on those days.</p> <ul style="list-style-type: none"><li>• <b>On Demand</b> specifies that you want to manually launch the scan at any time.</li><li>• <b>Dependent</b> specifies that you want Tenable Security Center to launch the scan every time Tenable Security Center finishes a scheduled run of the dependent scan you select.</li></ul>

## Settings Options

Parameter	Description
<b>Basic</b>	
<b>Scan Zone</b>	<p><b>Note:</b> If your organization's <b>Distribution Method</b> setting is <b>Locked Zone</b>, you cannot modify this setting. If your organization's <b>Distribution Method</b> setting is <b>Automatic Distribution Only</b>, Tenable Security Center automatically chooses one or more scan zones and hides this setting.</p> <p>Specifies the scan zone you want to use to run the scan. Depending on your organization's <b>Distribution Method</b> setting, you can select one of the following:</p> <ul style="list-style-type: none"><li>• An available zone —use a single scan zone to run the scan.</li></ul> <p><b>Note:</b> If you select a single scan zone, Tenable Security Center ignores the ranges in the scan zone and scans all of the <a href="#">targets</a> you specify in</p>



Parameter	Description
	<p>the scan configuration.</p> <ul style="list-style-type: none"><li>• <b>Automatic Distribution</b> —allow Tenable Security Center to choose the best scan zone to run the scan.</li></ul> <p>For more information, see <a href="#">Organizations</a> and <a href="#">Scan Zones</a>.</p>
<b>Import Repository</b>	Specifies the repository where Tenable Security Center imports the scan results. Select a IPv4, IPv6, or Universal repository to receive IPv4 or IPv6 results appropriate to the scan.
<b>Scan Timeout Action</b>	The action you want Tenable Security Center to perform in the event a scan is incomplete: <ul style="list-style-type: none"><li>• <b>Import Completed Results With Rollover</b> —(Default) The system imports the results from the scan into the database and creates a rollover scan that you can launch manually to complete the scan.</li><li>• <b>Import Completed Results</b> —The system imports the results of the current scan and discards the information for the unscanned hosts.</li><li>• <b>Discard Results</b> —The system does not import any of the results obtained by the scan to the database.</li></ul>
<b>Rollover Schedule</b>	If you set the Scan Timeout Action to <b>Import results with Rollover</b> , this option specifies how to handle the rollover scan. You can create the rollover scan as a template to launch manually, or to launch the next day at the same start time as the just-completed scan.
<b>Advanced</b>	
<b>Scan Virtual Hosts</b>	Specifies whether the system treats a new DNS entry for an IP address as a virtual host as opposed to a DNS name update.  When Tenable Security Center finds a new DNS name for an IP address: <ul style="list-style-type: none"><li>• If <b>Scan Virtual Hosts</b> is enabled, vulnerability data for the two DNS names appears as two entries with the same IP address in the IP</li></ul>



Parameter	Description
	<p>Summary analysis tool.</p> <ul style="list-style-type: none"><li>• If <b>Scan Virtual Hosts</b> is disabled, vulnerability data for the two DNS names merge into a single IP address entry in the IP Summary analysis tool.</li></ul>
<b>Track hosts which have been issued new IP address</b>	<p>This option uses the DNS name, NetBIOS name, Agent ID, and MAC address (if known), in that order, to track a host when its IP address changes. Once Tenable Security Center finds a match, Tenable Security Center does not search further for matches.</p> <p>For example, if Tenable Security Center does not match a DNS name, but it does match a NetBIOS name, the system does not check the MAC address. Networks using DHCP require that you set this option to properly track hosts.</p>
<b>Immediately remove vulnerabilities from scanned hosts that do not reply</b>	<p>If a previously responsive host does not reply to a scan, Tenable Security Center removes the host's vulnerabilities from the cumulative database. If the host has vulnerabilities in the mitigated database, they remain in the mitigated database.</p> <ul style="list-style-type: none"><li>• If you enable this option, the system removes the vulnerabilities immediately after the scan completes.</li><li>• If you disable this option, the system removes the vulnerabilities according to the interval set in the <b>Number of days to wait before removing dead hosts</b> option.</li></ul>
<b>Number of days to wait before removing dead hosts</b>	<p>If you disable <b>Immediately remove vulnerabilities from scanned hosts that do not reply</b>, this value specifies how many days the system waits to remove vulnerabilities.</p>
<b>Max scan duration (hours)</b>	<p>Specifies the maximum number of hours you want a scan to run.</p> <p>If a scan reaches this threshold, Tenable Security Center automatically creates a rollover scan that you can launch manually to complete the</p>



Parameter	Description
	scan. Tenable Security Center creates a rollover scan regardless of your <b>Scan Timeout Action</b> setting.

## Targets Options

The **Targets** section identifies the devices Tenable Security Center scans.

Option	Description
<b>Target Type</b>	Specifies the target type for the scan: <ul style="list-style-type: none"><li>• <b>Assets</b>—Scan one or more assets. For more information, see <a href="#">Assets</a>.</li><li>• <b>IP / DNS Name</b>—Scan one or more IP addresses or DNS names.</li><li>• <b>Mixed</b>—Scan a combination of asset lists, IP addresses, and DNS names.</li></ul>
<b>Assets</b>	(Available if <b>Target Type</b> is <b>Assets</b> or <b>Mixed</b> ) The list of assets to scan. Click to select or deselect the assets you want to scan.
<b>IPs / DNS Names</b>	(Available if <b>Target Type</b> is <b>IP / DNS Name</b> or <b>Mixed</b> ) The IP addresses or DNS names you want to scan.  Specify IP addresses and DNS names using the following valid formats: <ul style="list-style-type: none"><li>• A single IPv4 address (for example, 192.0.2.202)</li><li>• A single IPv6 address (for example, 2001:d-b8:d54e:cca6:4109:ac02:2fbe:134e)</li><li>• An IP address range in dot-decimal or CIDR notation (for example, 192.0.2.0-192.0.2.255 or 192.0.2.0/24)</li><li>• A resolvable hostname (for example, www.yourdomain.com)</li></ul> <div style="border: 1px solid blue; padding: 5px;"><b>Note:</b> You cannot scan both IPv4 and IPv6 addresses in the same scan, because you can only select one Import Repository.</div>

## Credentials Options



The **Credentials** section allows users to select pre-configured credential sets for authenticated scanning. For more information, see [Credentials](#).

Tenable Security Center active scans support the following credential types:

- [Windows Credentials](#)
- [SSH Credentials](#)
- [SNMP Credentials](#)
- [Database Credentials](#)
- [API Gateway Credentials](#)

## Post Scan Options

These options determine what actions occur immediately before and after the active scan completes.

Option	Description
<b>Reports to Run on Scan Completion</b>	
<b>Add Report</b>	This option provides a list of reports available to the user to run when the scan completes. For more information, see <a href="#">Add a Report to a Scan</a> .





## Launch a Remediation Scan

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can run a remediation scan to run a followup active scan against existing active scan results. A remediation scan evaluates a specific plugin against a specific target or targets where the related vulnerability was present in your earlier active scan.

Remediation scans allow you to validate whether your vulnerability remediation actions on the targets have been successful. If a remediation scan cannot identify a vulnerability on targets where it was previously identified, the system changes the status of the vulnerability to mitigated. For more information, see [Cumulative vs. Mitigated Vulnerabilities](#).

Note the following:

- You can perform remediation scans only for active scan results.
- You cannot perform remediation scans for agent repository scan results.
- If the selected plugin requires dependent plugins, the system automatically includes those plugins in the remediation scan.
- Remediation scans only evaluate plugins against the port you specify. Keep this in mind when launching a remediation scan for a plugin that typically targets multiple ports.
- Remediation scans work best for un-credentialed network scan results. Use caution when running a remediation scan for a plugin that requires scan credentials. If you neglect to add scan credentials when required for a specific plugin, or if you mis-enter the credentials, the system may identify the related vulnerabilities as mitigated, not because they are mitigated, but because the system could not complete the credentialed scan.

To launch a remediation scan:

1. Log in to Tenable Security Center via the user interface.
2. Click **Analysis > Vulnerabilities**.

The **Vulnerabilities** page appears.

3. In the analysis tools drop-down box, select **Vulnerability Detail List**.



The page refreshes to show the analysis tool view you selected.

4. Right-click the row for the vulnerability for which you want to launch a remediation scan and click **Launch Remediation Scan**.

The **Launch Remediation Scan** page appears.

**Note:** A remediation scan inherits certain settings from the vulnerability or vulnerability instance you selected. The **Launch Remediation Scan** page:

- Automatically populates the relevant plugin information.
- Provides an editable scan name in the format "Remediation Scan of Plugin # *number*".
- Populates the target IP address based on the asset where the previous scan identified the vulnerability.

5. Configure the settings for the scan, as described in [Active Scan Settings](#).

**Note:** You do not need to associate the remediation scan with a scan policy.

**Note:** You cannot schedule a remediation scan. The scan launches as soon as you submit it.

6. Click **Submit**.

Tenable Security Center launches the remediation scan.



---

## Attack Surface Domain Discovery

---

On the **Attack Surface Domain Discovery** page, you can manage your domains. When you add a domain, Tenable Security Center identifies internet-accessible assets associated with the domain that may not otherwise be visible to your organization. Tenable Security Center uses DNS records, IP addresses, and Autonomous System Numbers (ASN) to identify assets.

To view a list of assets identified on your domain, see the [Domain Inventory Assets page](#).

For more information about domain inventory assets, see:

- [View Domain Inventory Assets](#)
- [Export Domain Inventory Assets](#)

To view your domains:

1. Log in to Tenable Security Center via the user interface.
2. In the left navigation, click **Scans > Attack Surface Domain Discovery**.

The **Attack Surface Domain Discovery** page appears.

3. (Optional) [Add your organization's domain](#) to begin identifying assets.
4. Click **Submit**.

Tenable Security Center saves your configuration.



## Add a Domain

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

**Note:** You can add a maximum of two domains across your system.

When you add a domain, Tenable Security Center identifies internet-accessible assets associated with the domain. For more information, see [Attack Surface Domain Discovery](#).

To add a domain:

1. Log in to Tenable Security Center via the user interface.
2. In the left navigation, click **Scans > Attack Surface Domain Discovery**.

The **Attack Surface Domain Discovery** page appears.

3. At the top of the table, click **Add**.

The **Add Domain** panel appears.

4. In the **Add a Domain to Your Inventory** box, type your organization's domain.
5. Click **Submit**.

Tenable Security Center saves your configuration.

What to do next:

- View the assets associated with your domain, as described in [View Domain Inventory Assets](#).
- Export a CSV file of the assets associated with your domain, as described in [Export Domain Inventory Assets](#).



## View Domain Details

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information about domains, see [Attack Surface Domain Discovery](#).

To view domain details:

1. Log in to Tenable Security Center via the user interface.
2. In the left navigation, click **Scans > Attack Surface Domain Discovery**.

The **Attack Surface Domain Discovery** page appears.

3. In the table, select the domain you want to view.

The **View Domain** panel appears, with details about the domain:

- **Domain Name** —The name of the domain.
- **Created Time** - When the domain was added to Tenable Security Center.
- **Last Refresh** - The last time the [list of domain assets](#) was updated.

4. (Optional) [Delete the domain](#).



## Delete a Domain

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information about domains, see [Attack Surface Domain Discovery](#).

To delete a domain:

1. Log in to Tenable Security Center via the user interface.
2. In the left navigation, click **Scans > Attack Surface Domain Discovery**.

The **Attack Surface Domain Discovery** page appears.

3. In the table, select the domain you want to delete.

The **View Domain** panel appears.

4. Click **Delete Domain**.

A dialog box appears, confirming your selection to delete the domain.

5. Click **Delete**.

The domain and related [domain inventory assets](#) are deleted.

---



## Active Scan Objects

---

Complete Tenable Security Center scan configurations rely on the following scan objects. For information about active scans, see [Active Scans](#).

Scan Object	Description
assets	<p>Assets are lists of devices (for example, laptops, servers, tablets, or phones) within a Tenable Security Center organization. You can share assets with one or more users based on local security policy requirements.</p> <p>You can add an asset to group devices that share common attributes. Then, you can use the asset during scan configuration to target the devices in the asset.</p> <p>For more information, see <a href="#">Assets</a>.</p>
credentials	<p>Credentials are reusable objects that facilitate a login to a scan target. You can configure various types of credentials with different authentication methods for use within scan policies. You can also share credentials between users for scanning purposes.</p> <p>Tenable Security Center supports an unlimited number of SSH, Windows, and database credentials, and four SNMP credential sets per scan configuration.</p> <p>For more information, see <a href="#">Credentials</a>.</p>
audit files	<p>During a configuration audit, auditors verify that your server and device configurations meet an established standard and that you maintain them with an appropriate procedure. Tenable Security Center can perform configuration audits on key assets by using local Tenable Nessus checks that can log directly on to a Unix or Windows server without an agent.</p> <p>Tenable Security Center supports several audit standards. Some of these come from best practice centers like the PCI Security Standards Council and the Center for Internet Security (CIS). Some of these are based on Tenable's interpretation of audit requirements to comply with specific industry standards such as PCI DSS or legislation such as Sarbanes-Oxley.</p> <p>In addition to base audits, you can create customized audits for the par-</p>



	<p>particular requirements of any organization. You can upload customized audits into Tenable Security Center and make them available to anyone performing configuration audits within an organization.</p> <p>You can upload and use NIST SCAP files in the same manner as an audit file. Navigate to NIST's SCAP website (<a href="http://scap.nist.gov">http://scap.nist.gov</a>) and under the SCAP Content section, download the desired SCAP security checklist zip file. You can then upload the file to Tenable Security Center and select it for use in Tenable Nessus scan jobs.</p> <p>Once you configure audit scan policies in Tenable Security Center, you can use them as needed. Tenable Security Center can also perform audits intended for specific assets. A Tenable Security Center user can use audit policies and asset lists to determine the compliance posture of any specified asset.</p> <p>For more information, see <a href="#">Audit Files</a>.</p>
scan zones	<p>Scan zones represent areas of your network that you want to target in an active scan, associating an IP address or range of IP addresses with one or more scanners in your deployment. Scan zones define the IP address ranges associated with the scanner along with organizational access.</p> <p>For more information, see <a href="#">Scan Zones</a>.</p>
scan policies	<p>Scan policies contain options related to performing an active scan. For example:</p> <ul style="list-style-type: none"><li>• Options that control technical aspects of the scan such as timeouts, number of hosts, type of port scanner, and more.</li><li>• Options that provide plugin family-based or individual plugin-based scan specifications.</li><li>• Options that control compliance policy checks (Windows, Linux, Database, etc.), report verbosity, service detection scan settings, audit files, patch management systems, and more.</li></ul> <p>For more information, see <a href="#">Scan Policies</a>.</p>





---

# Assets

---

Tenable Security Center *assets* are lists of devices (for example, laptops, servers, tablets, or phones) within a Tenable Security Center organization. Assets can be shared with one or more users based on local security policy requirements.

You can add an asset to group devices that share common attributes. Then, you can use the asset during scan configuration to target the devices in the asset. Examples of common attributes include:

- IP address ranges
- hardware types
- vulnerabilities
- outdated software versions
- operating systems

Tenable Security Center supports template-based and custom assets. For more information, see [Add a Template-Based Asset](#) and [Add a Custom Asset](#). To view details for any of your assets, see [View Asset Details](#).

To view details about individual hosts that appear in your assets, see [View Hosts](#) and [View Host Details](#).

## Template-Based Assets

Tenable provides asset templates that you can customize for your environment. Tenable-provided asset templates are updated via the Tenable Security Center feed and visible depending on other configurations.

## Custom Assets

Tenable Security Center supports the following custom assets types: [Static Assets](#), [DNS Name List Assets](#), [LDAP Query Assets](#), [Combination Assets](#), [Dynamic Assets](#), [Watchlist Assets](#), and [Import Assets](#).

## Static Assets



Static assets are lists of IP addresses. You can use static assets immediately after configuration.

For example, if your organization assigns laptops within a defined IP address range, you can create a custom static asset for laptops using that IP address range.

Option	Description
<b>Name</b>	A name for the asset.
<b>Description</b>	A description for the asset.
<b>Tag</b>	A tag for the asset. For more information, see <a href="#">Tags</a> .
<b>IP Addresses</b>	IP addresses to include within the asset (20,000 character limit). <ul style="list-style-type: none"><li>• Type a comma-separated list of IP addresses, CIDR addresses, or ranges.</li><li>• Upload a .txt file containing a comma-separated list of IP addresses, CIDR addresses, or ranges.</li></ul>

## DNS Name List Assets

Option	Description
<b>Name</b>	A name for the asset.
<b>Description</b>	A description for the asset.
<b>DNS Names</b>	The DNS hostnames for the asset to be based on.

## LDAP Query Assets

The LDAP query asset type appears if your organization includes a configured LDAP server.

Option	Description
<b>Name</b>	A name for the asset.
<b>Description</b>	A description for the asset.
<b>LDAP Server</b>	The LDAP server where you want to perform the query.



Option	Description
	<p><b>Note:</b> If the LDAP server uses a different DNS server than Tenable Security Center, Tenable Security Center cannot resolve hostnames retrieved from the LDAP server.</p> <p><b>Note:</b> Tenable Security Center cannot retrieve more than one page of LDAP results. If Tenable Security Center asset or user authentication queries are not retrieving all expected results, consider modifying your LDAP pagination control settings to increase the results per page.</p>
<b>Search Base</b>	The LDAP search base used as the starting point to search for specific LDAP data.
<b>Search String</b>	Modify this string to create a search based on a location or filter other than the default search base or attribute.
<b>Generate Preview</b>	Click to display a preview query in the <b>Results Preview</b> section. The preview lists the LDAP data that matches the defined search string.

## Combination Assets

Combination assets allow you to create an asset based on existing assets and the AND, OR, and NOT operators.

Combination assets can include agent IDs if the asset contains exclusively dynamic assets. You may experience unexpected asset behavior if your combination asset contains other asset types and interacts with agent repository data.

Option	Description
<b>Name</b>	A name for the asset.
<b>Description</b>	A description for the asset.
<b>Combination</b>	This option accepts multiple existing assets utilizing the operators AND, OR, and NOT. You can use these operators and multiple existing assets to create new unique assets. If the source assets change, the <b>Combination</b> asset updates to match the new conditions.



Option	Description
	<p>To configure the query:</p> <ol style="list-style-type: none"><li>1. Click inside the <b>Combination</b> box. A list of assets appears.</li><li>2. Click one of the options in the list to select it.</li><li>3. Press Space.</li><li>4. Continue selecting options and pressing space to describe the combination asset you want to configure.</li></ol> <div data-bbox="423 722 1479 837" style="border: 1px solid green; padding: 5px;"><p><b>Tip:</b> A red border around a combination option indicates there is a problem in the query logic.</p></div>

## Dynamic Assets

Dynamic assets are flexible groups of condition statements that Tenable Security Center uses to retrieve a list of devices meeting the conditions. Tenable Security Center refreshes dynamic asset lists using the results from Tenable Security Center scans. You cannot use dynamic assets until after Tenable Security Center performs an initial discovery scan and retrieves a list of devices.

**Note:** If a dependent scan uses a dynamic asset list, the asset list will update before the scan runs.

Dynamic assets can include agent IDs.



## Add Dynamic Asset ← Back

### General

Name\*

Description

Tag

### Asset Definition

All of the following are true:

- Plugin ID  is equal to  ✓ ✕
- TCP Port is equal to 80
- Operating System is equal to Linux

For example, in the asset above, Tenable Security Center retrieves a list of Linux systems listening on TCP Port 80. For more information about using dynamic asset conditions, see [Dynamic Assets](#).

Option	Description
<b>Name</b>	A name for the asset.
<b>Description</b>	A description for the asset.
<b>Asset Definition</b>	Defines the rules for creating a dynamic asset list. Hover over an existing rule to display the options to add, edit, or delete a group or a rule.

### Dynamic Asset Rule Logic

Valid Operators	Effect
<b>Plugin ID</b>	
is equal to	Value must be equal to value specified.



Valid Operators	Effect
not equal to	Value must be not equal to value specified.
is less than	Value must be less than the value specified.
is greater than	Value must be greater than the value specified.
<b>Plugin Text</b>	
is equal to	Value must be equal to value specified.
not equal to	Value must be not equal to value specified.
contains the pattern	Value must contain the text specified (for example, ABCDEF contains ABC).
Posix regex	Any valid Posix regex pattern contained within “/” and “/” (example: /. *ABC.*/).
Perl compatible regex	Any valid Perl compatible regex pattern.
<b>Operating System</b>	
is equal to	Value must be equal to value specified.
not equal to	Value must be not equal to value specified.
contains the pattern	Value must contain the text specified (for example, ABCDEF contains ABC).
Posix regex	Any valid Posix regex pattern contained within “/” and “/” (for example, /. *ABC.*/).
Perl compatible regex	Any valid Perl compatible regex pattern.
<b>IP Address</b>	
is equal to	Value must be equal to value specified.
not equal to	Value must be not equal to value specified.



Valid Operators	Effect
<b>DNS, NetBIOS Host, NetBIOS Workgroup, MAC, SSH v1 Fingerprint, SSH v2 Fingerprint</b>	
is equal to	Value must be equal to value specified.
not equal to	Value must be not equal to value specified.
contains the pattern	Value must contain the text specified (for example, 1.2.3.124 contains 124).
Posix regex	Any valid Posix regex pattern contained within “/” and “/” (for example, /. *ABC.*/).
Perl compatible regex	Any valid Perl compatible regex pattern.
<b>Port, TCP Port, UDP Port</b>	
is equal to	Value must be equal to value specified.
not equal to	Value must be not equal to value specified.
is less than	Value is less than value specified.
is greater than	Value is greater than the value specified.
<b>Days Since Discovery, Days Since Observation</b>	
is equal to	Value must be equal to value specified (maximum 365).
not equal to	Value must be not equal to value specified (maximum 365).
is less than	Value is less than value specified (maximum 365).
is greater than	Value is greater than the value specified (maximum 365).
where Plugin ID is	Any valid plugin ID number. You can enter multiple plugin IDs using a range or comma-separated plugin IDs (for example, 3, 10189, 34598, 50000-55000, 800001-800055).
<b>Severity</b>	
is equal to	Value must be equal to value specified: <b>Info, Low, Medium, High, or Critical.</b>



Valid Operators	Effect
not equal to	Value must be not equal to value specified: <b>Info</b> , <b>Low</b> , <b>Medium</b> , <b>High</b> , or <b>Critical</b> .
is less than	Value must be less than the value specified: <b>Info</b> , <b>Low</b> , <b>Medium</b> , <b>High</b> , or <b>Critical</b> .
is greater than	Value must be greater than the value specified: <b>Info</b> , <b>Low</b> , <b>Medium</b> , <b>High</b> , or <b>Critical</b> .
where Plugin ID is	Any valid plugin ID number. You can enter multiple plugin IDs using a range or comma-separated plugin IDs (for example, 3, 10189, 34598, 50000-55000, 800001-800055).
<b>Exploit Available</b>	
Is	Click <b>True</b> or <b>False</b> in the drop-down box.
<b>Exploit Frameworks</b>	
is equal to	Value must be equal to value specified.
Is not equal to	Value must not be equal to value specified.
contains the pattern	Value must contain the pattern entered.
<b>XRef</b>	
Value must be in the XRef option.	

## Watchlist Assets

You can use a watchlist asset to maintain lists of IPs that are not in the user's managed range of IP addresses. You can filter for IPs from a watchlist regardless of your IP address range configuration to help analyze event activity originating outside of the user's managed range. For example, if a block of IP addresses is a known source of malicious activity, you could add it to a Malicious IPs watchlist and added to a custom query.

**Note:** Watchlists only uses event data to create the asset list.





Option	Description
<b>Name</b>	A name for the asset.
<b>Description</b>	A description for the asset.
<b>IP Addresses</b>	IP addresses to include within the asset list (20,000 character limit). You can enter one address, CIDR address, or range per line.  Click <b>Choose File</b> to import a list of IP addresses from a saved file.

## Import Assets

Option	Description
<b>Name</b>	The asset name.
<b>Asset</b>	Click <b>Choose File</b> to choose the asset that was previously exported for import into Tenable Security Center.



## Add a Template-Based Asset

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

For information, see [Assets](#).

To add an asset from a Tenable-provided template:

1. Log in to Tenable Security Center via the user interface.
2. In the left navigation, click **Assets > Assets**.

The **Assets** page appears.

3. Click **Add**.





The **Asset Templates** page appears.

4. (Optional) If you want to search for a specific asset template, type a search phrase in the **Search Templates** box.

5. In the **Common** section, click a template type.

The **Add Asset Template** page for the template type appears.

6. View the available templates.

- The four square icon () on the left side indicates a collection of several assets.
- The data icons () on the right side indicate the data required to build the asset. The Tenable Nessus Network Monitor (PVS), Log Correlation Engine, and NS icons indicate you must have Tenable Nessus Network Monitor, Log Correlation Engine, or Tenable Nessus data. The key icon () indicates you must have credentials for the device. The notepad icon () indicates you must have compliance data.

7. (Optional) If you want to search for a specific asset template, type a search phrase in the **Search Templates** box or select a category from the **All** drop-down box.

8. Click the row for the template you want to use.

The detail page for the template type appears.



9. Click **Add**.

The **Assets** page appears.

10. Click the row for the asset you just added.

The **Edit** page appears.

11. View the details for the asset.

12. (Optional) If necessary, edit the asset to customize it for your environment. For more information about asset options, see [Assets](#).

13. Click **Submit**.

Tenable Security Center saves your configuration.



---

## Add a Custom Asset

---

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

For information, see [Assets](#).

To add a custom asset:

1. Log in to Tenable Security Center via the user interface.
2. In the left navigation, click **Assets > Assets**.

The **Assets** page appears.

3. At the top of the table, click **Add**.

The **Asset Templates** page appears.

4. In the **Other** section, click an asset type.

The **Add Assets** page for the asset type appears.

5. Configure the required options for the asset type, as described in [Assets](#).
6. Click **Submit**.

Tenable Security Center saves your configuration.



## View Asset Details

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can view details for any asset. For more information, see [Assets](#).

To view asset details:

1. Log in to Tenable Security Center via the user interface.
2. In the left navigation, click **Assets > Assets**.

The **Assets** page appears.

3. Right-click the row for the asset you want to view.

The actions menu appears.

-or-

Select the check box for the asset you want to view.

The available actions appear at the top of the table.

4. Click **View**.

The **View Asset** page appears.

Section	Action
General	<p>View general information for the asset.</p> <ul style="list-style-type: none"><li>• <b>Name</b> —The asset name.</li><li>• <b>Description</b> —The asset description.</li><li>• <b>Tag</b> —The tag applied to the asset. For more information, see <a href="#">Tags</a>.</li><li>• <b>IP Addresses</b> (static assets only) —The IP addresses specified in the asset. For more information, see <a href="#">Assets</a>.</li><li>• <b>Created</b> —The date the asset was created.</li></ul>



Section	Action
	<ul style="list-style-type: none"><li>• <b>Last Modified</b> —The date the asset was last modified.</li><li>• <b>Owner</b> —The username for the user who created the asset.</li><li>• <b>Group</b> —The group in which the asset belongs.</li><li>• <b>ID</b> —The asset ID.</li></ul>
Tenable.io Synchronization Data	<p>View synchronization summary data:</p> <ul style="list-style-type: none"><li>• <b>Status</b> —The status of the asset in Tenable Lumin synchronization:<ul style="list-style-type: none"><li>• <b>Finished</b> —The most recent synchronization that included this asset succeeded.</li><li>• <b>Not Synced</b> —The asset is not configured for Tenable Lumin synchronization.</li><li>• <b>Error</b> —An error occurred. For more information, see <a href="#">View Tenable Lumin Data Synchronization Logs</a>.</li></ul></li><li>• <b>First Synchronization</b> —The date and time of the first synchronization of this asset.</li><li>• <b>Last Success</b> —The date and time of the most recent synchronization of this asset.</li><li>• <b>Last Failure</b> —The date and time of the most recent failed synchronization of this asset.</li><li>• <b>Details</b> —If the <b>Status</b> is <b>Error</b>, details about the error.</li></ul> <p>For more information about Tenable Lumin synchronization, see <a href="#">Tenable Lumin Synchronization</a>.</p>



# View Hosts

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).


You can view a list of hosts associated with asset lists. For more information, see [Assets](#).

To view details for an individual host, see [View Host Details](#).

To view the list of hosts:

1. Log in to Tenable Security Center via the user interface.
2. Click **Assets > Host Assets**.

The **Host Assets** page appears.

3. (Optional) To show or hide columns on the **Host Assets** page:
  - a. In the table, click the  button next to a column header.  
  
A drop-down menu appears with a list of column names.
  - b. Check or uncheck the boxes to show or hide columns.
4. View details about each host asset.

- **Name** —The name of the host.
- **AES** —(Requires Tenable Security Center+ license) The host's Asset Exposure Score. For more information, see [Asset Exposure Score](#) in the *Tenable Vulnerability Management User Guide*.
- **ACR** —(Requires Tenable Security Center+ license) The host's Asset Criticality Rating. For more information, see [Asset Criticality Rating](#) in the *Tenable Vulnerability Management User Guide*.
- **IP Address** —The host's IP address, if available.
- **Repository** —The repository that contains vulnerability data associated with the host.
- **OS** —The operating system running on the host, if available.



- **System Type** —The host's device type, as determined by plugin 54615.
- **Net BIOS** —The host's NetBIOS name, if available.
- **DNS** —The host's DNS name, if available.
- **Last Seen** —The date and time last Tenable Security Center detected the host on your network.
- **Asset ID** —The ID of the host.
- **Source** —The type of scan that discovered the host on your network: **Tenable Nessus Scan**, **Tenable Nessus Network Monitor**, **Log Correlation Engine**, or **Agent Scan**.

**Tip:** The following columns are hidden by default: **System Type**, **Net BIOS**, **DNS**, and **Asset ID**.





## Export Hosts

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can export a list of hosts in a .csv file to share the data with others in your organization. For more information, see [Assets](#).

To view details for an individual host, see [View Host Details](#).

To view the list of hosts:

1. Log in to Tenable Security Center via the user interface.
2. Click **Assets > Host Assets**.

The **Host Assets** page appears.

3. (Optional) To filter the list of hosts, [apply a filter](#). For more information, see [Host Asset Filter Components](#).
4. At the top of the table, click **Export**.

Tenable Security Center exports the host assets in a CSV file.

---

# Host Asset Filter Components

---

For general information about using filters, see [Filters](#).

Filter Component	Description
<b>Asset Criticality Rating (ACR)</b>	<p>(Requires Tenable Security Center+ license) Filters for hosts within the specified ACR range (for example, between 1 and 5). For more information, see <a href="#">Asset Criticality Rating</a> in the <i>Tenable Vulnerability Management User Guide</i>.</p> <div style="border: 1px solid green; padding: 5px;"><p><b>Tip:</b> To edit the ACR for a host asset, see <a href="#">Edit an ACR Manually</a>.</p></div>
<b>Address</b>	<p>This filter specifies an IPv4 or IPv6 address, range, or CIDR block to limit the viewed hosts. For example, entering <code>198.51.100.28/24</code> and/or <code>2001:DB8::/32</code> limits any of the web tools to show only host data from the selected network(s). Addresses can be comma-separated or on separate lines.</p>
<b>Asset Exposure Score (AES)</b>	<p>(Requires Tenable Security Center+ license) Filters for hosts within the specified AES range (for example, between 400 and 600).</p>
<b>DNS Name</b>	<p>This filter specifies a DNS name to limit the viewed hosts. For example, entering <code>host.example.com</code> limits any of the web tools to show only host data from that DNS name.</p>
<b>Name</b>	<p>Filters for hosts with names that include the specified text.</p>
<b>Operating System</b>	<p>Filters for hosts running the specified operating system.</p>
<b>Repositories</b>	<p>Filters for hosts with associated vulnerability data in the specified repository.</p>
<b>System Type</b>	<p>Filters for hosts with the specified device type, as determined by plugin 54615.</p>



# View Domain Inventory Assets

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can view a list of assets identified in your organization's domains. For more information, see [Attack Surface Domain Discovery](#).

To view the list of domain inventory assets:

1. Log in to Tenable Security Center via the user interface.
2. Click **Assets > Domain Inventory**.

The **Domain Inventory** page appears.

3. (Optional) To filter the list of domain inventory assets, [apply a filter](#). For more information, see Domain Inventory Filter Components.

4. (Optional) To show or hide columns on the **Domain Inventory** page:

- a. In the table, click the  button next to a column header.

A drop-down menu appears with a list of column names.

- b. Check or uncheck the boxes to show or hide columns.

5. View details about each domain inventory asset.

- **Host** —The host associated with the asset.
- **Record Type** - The asset type.

**Note:** The value in this column is determined by DNS messages associated with the asset.

- **Record Value** - The name of the asset.
- **IP** - The asset's IP address, if available.
- **ASN** - The asset's Autonomous System Number.
- **Ports** - The ports to which the asset connects.



## Export Domain Inventory Assets

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can export a list of assets identified in your organization's domains. For more information, see [Attack Surface Domain Discovery](#).

To export a list of domain inventory assets:

1. Log in to Tenable Security Center via the user interface.
2. Click **Assets > Domain Inventory**.  
The **Domain Inventory** page appears.
3. (Optional) To the left of the table, click a domain to filter the list of assets.
4. At the top of the table, click **Export All**.

Tenable Security Center exports the domain inventory assets in a CSV file.



# Credentials

Credentials are reusable objects that facilitate scan target login.

Administrators can add credentials available to all organizations. Organizational users can add credentials available to other users in the same organization. For information about user access in Tenable Security Center, see [User Access](#).

Users can share credentials with other users, allowing them to scan remote hosts without knowing the credentials of the host. For information about Tenable Security Center credential data encryption, see [Encryption Strength](#).

Tenable Security Center supports the following credential types:

- [Miscellaneous Credentials](#)
- [API Gateway Credentials](#)
- [Database Credentials](#)
- [SNMP Credentials](#)
- [SSH Credentials](#)
- [Windows Credentials](#)

If a scan contains multiple instances of one type of credential, Tenable Security Center tries the credentials on each scan target in the order you added the credentials to Tenable Security Center.

**Note:** Tenable Security Center uses the first credential that allows successful login to perform credentialed checks on the target. After a credential allows a successful login, Tenable Security Center does not try any of the other credentials in the list, even if a different credential has greater privileges.

To add credentials, see [Add Credentials](#).



# Add Credentials

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information about credentials, see [Credentials](#).

**Note:** You can add up to 1000 SSH credentials in a single scan. For best performance, Tenable recommends adding no more than 10 SSH credentials per scan.

To add credentials:

1. Log in to Tenable Security Center.
2. Click **Scanning** > **Credentials** (administrator users) or **Scans** > **Credentials** (organizational users).

The **Credentials** page appears.

3. Click **Add**.

The **Credential Templates** page appears.

4. In the **Miscellaneous**, **API Gateway**, **Database**, **SNMP**, **SSH**, or **Windows** sections, click the tile for the specific method you want to configure.

The **Add Credentials** configuration page appears.

5. In the **Name** box, type a name for the credentials.
6. In the **Description** box, type a description for the credentials.
7. (Optional) Type or select a **Tag**. For more information, see [Tags](#).
8. Configure the options, as described in:

- [Miscellaneous Credentials](#)
- [API Gateway Credentials](#)
- [Database Credentials](#)
- [SNMP Credentials](#)



- [SSH Credentials](#)
- [Windows Credentials](#)

9. Click **Submit**.

Tenable Security Center saves your configuration.



## Miscellaneous Credentials

Configure the following options for all miscellaneous credentials.

Option	Description
<b>Name (Required)</b>	A name for the credential.
<b>Description</b>	A description for the credential.
<b>Tag</b>	A tag for the credential. For more information, see <a href="#">Tags</a> .

## Citrix Options

The following table describes the additional options to configure for **Citrix** credentials.

Option	Description	Default
<b>Port</b>	(Required) The TCP port that Citrix listens on for communications from Tenable Security Center.	443
<b>Username</b>	(Required) The username for the scanning Citrix account that Tenable Security Center uses to perform checks on the target system.	--
<b>Password</b>	(Required) The password for the Citrix user.	--
<b>HTTPS</b>	When enabled, Tenable Security Center connects using secure communication (HTTPS).  When disabled, Tenable Security Center connects using standard HTTP.	enabled
<b>Verify SSL Certificate</b>	When enabled, Tenable Security Center verifies that the SSL certificate on the server is signed by a trusted CA.  <b>Tip:</b> If you are using a self-signed certificate, disable this setting.	enabled

## Nutanix Prism Central Options





The following table describes the additional options to configure for **Nutanix Prism Central** credentials.

Option	Description	Default
<b>Nutanix Host</b>	(Required) The hostname or IP address for the Nutanix Prism Central host.	--
<b>Nutanix Port</b>	(Required) The port for the Nutanix Prism Central host.	9440
<b>Username</b>	(Required) The username for the Nutanix Prism Central account.	--
<b>Password</b>	(Required) The password for the Nutanix Prism Central user.	--
<b>Discover Hosts</b>	When enabled, Tenable Security Center adds all discovered Nutanix hosts to the list of scan targets.	enabled
<b>Discover Virtual Machines</b>	When enabled, Tenable Security Center adds all discovered Nutanix Virtual Machines to the list of scan targets.	enabled
<b>HTTPS</b>	When enabled, Tenable Security Center connects using secure communication (HTTPS).  When disabled, Tenable Security Center connects using standard HTTP.	enabled
<b>Verify SSL Certificate</b>	When enabled, Tenable Security Center verifies that the SSL certificate on the server is signed by a trusted CA.  <div style="border: 1px solid green; padding: 5px;"><b>Tip:</b> If you are using a self-signed certificate, disable this setting.</div>	disabled



## API Gateway Credentials

Configure the following options for all API gateway credentials.

Option	Description
Name (Required)	A name for the credential.
Description	A description for the credential.
Tag	A tag for the credential. For more information, see <a href="#">Tags</a> .

## IBM DataPower Options

The following table describes the additional options to configure for **IBM DataPower** credentials.

Option	Description
Client Certificate	The file that contains the PEM certificate used to communicate with the IBM DataPower host.
Client Certificate Private Key	The file that contains the PEM private key for the client certificate.
Client Certificate Private Key Passphrase	The passphrase for the private key, if required.
Custom Header Key	If your IBM DataPower configuration uses custom HTTP headers, the custom HTTP header key.
Custom Header Value	If your IBM DataPower configuration uses custom HTTP headers, the custom HTTP header value.
Enable for Hashicorp Vault	When enabled, allows Tenable Security Center to use the IBM DataPower credential with a Hashicorp Vault credential. <div style="border: 1px solid green; padding: 5px; margin-top: 10px;"><b>Tip:</b> If you want to run a test that does not use IBM DataPower credentials</div>



Option	Description
	<p>without having to delete the credential, you can temporarily disable this option to prevent Tenable Security Center from using IBM DataPower credentials.</p>



## Database Credentials

The following topic describes the available **Database** credentials.

**Note:** Aspects of credential options are based on Nessus plugin options. Therefore, specific credential options may differ from the descriptions documented here.

Configure the following options for all database credentials:

Options	Description
Name (Required)	A name for the credential.
Description	A description for the credential.
Tag	A tag for the credential. For more information, see <a href="#">Tags</a> .



## IBM DB2

The following table describes the additional options to configure for **IBM DB2** credentials.

Options	Description
Source	<p>The method for providing the required credential details: <b>Entry</b> or <b>Import</b>.</p> <ul style="list-style-type: none"><li>• <b>Entry</b>—Specifies you want to use a single SID value or SERVICE_NAME value for the credential. You must also configure the remaining options on the <b>Add Credential</b> page, as described in <a href="#">Add Credentials</a>.</li><li>• <b>Import</b>—Specifies you want to use multiple SID values for the credential, uploaded as a .csv file. For more information about the required .csv file format, see <a href="#">Database Credentials Authentication</a>.</li></ul>
Authentication Method	<p>The authentication method for providing the required credentials.</p> <ul style="list-style-type: none"><li>• CyberArk</li><li>• Password</li><li>• Lieberman</li><li>• Hashicorp Vault</li><li>• Wallix Bastion</li></ul> <p>For descriptions of the options for your selected authentication type, see <a href="#">Database Credentials Authentication</a>.</p>
Port	<p>The TCP port that the IBM DB2 database instance listens on for communications from Tenable Security Center. The default is port 50000.</p>
Database Name	<p>The name for your database (not the name of your instance).</p>



---

## Informix/DRDA

---

The following table describes the additional options to configure for **Informix/DRDA** credentials.

Options	Description
Username	The username for a user on the database.
Password	The password associated with the username you provided.
Port	The TCP port that the Informix/DRDA database instance listens on for communications from Tenable Security Center. The default is port 1526.

The following table describes the additional options to configure for **MySQL** credentials.

Options	Description
Source	<p>The method for providing the required credential details: <b>Entry</b> or <b>Import</b>.</p> <ul style="list-style-type: none"> <li>• <b>Entry</b>—Specifies you want to use a single SID value or SERVICE_NAME value for the credential. You must also configure the remaining options on the <b>Add Credential</b> page, as described in <a href="#">Add Credentials</a>.</li> <li>• <b>Import</b>—Specifies you want to use multiple SID values for the credential, uploaded as a .csv file. For more information about the required .csv file format, see <a href="#">Database Credentials Authentication</a>.</li> </ul>
Authentication Method	<p>The authentication method for providing the required credentials.</p> <ul style="list-style-type: none"> <li>• CyberArk</li> <li>• Password</li> <li>• Lieberman</li> <li>• Hashicorp Vault</li> <li>• Wallix Bastion</li> </ul> <p>For descriptions of the options for your selected authentication type, see <a href="#">Database Credentials Authentication</a>.</p>
Username	The username for a user on the database.
Password	The password associated with the username you provided.
Port	The TCP port that the MySQL database instance listens on for communications from Tenable Security Center. The default is port 3306.



Options	Description
SID	The name for your database instance.





## Oracle Database

The following table describes the additional options to configure for **Oracle Database** credentials.

Options	Description
Source	<p>The method for providing the required credential details: <b>Entry</b> or <b>Import</b>.</p> <ul style="list-style-type: none"><li>• <b>Entry</b>—Specifies you want to use a single SID value or SERVICE_NAME value for the credential. You must also configure the remaining options on the <b>Add Credential</b> page, as described in <a href="#">Add Credentials</a>.</li><li>• <b>Import</b>—Specifies you want to use multiple SID values for the credential, uploaded as a .csv file. For more information about the required .csv file format, see <a href="#">Database Credentials Authentication</a>.</li></ul>
Authentication Method	<p>The authentication method for providing the required credentials.</p> <ul style="list-style-type: none"><li>• CyberArk</li><li>• Password</li><li>• Lieberman</li><li>• Hashicorp Vault</li><li>• Wallix Bastion</li></ul> <p>For descriptions of the options for your selected authentication type, see <a href="#">Database Credentials Authentication</a>.</p>
Port	<p>The TCP port that the Oracle database instance listens on for communications from Tenable Security Center. The default is port 1521.</p>
Authentication	<p>The type of account you want Tenable Security Center to use to access the database instance:</p>



Options	Description
	<ul style="list-style-type: none"><li>• <b>Normal</b></li><li>• <b>System Operator</b></li><li>• <b>System Database Administrator</b></li></ul>
Service Type	The Oracle parameter you want to use to specify the database instance: <b>SID</b> or <b>Service Name</b> .
Service	The SID value or SERVICE_NAME value for your database instance.  The <b>Service</b> value you enter must match your parameter selection for the <b>Service Type</b> option.



# PostgreSQL

The following table describes the additional options to configure for **PostgreSQL** credentials.

Options	Description
Authentication Method	<p>The authentication method for providing the required credentials.</p> <ul style="list-style-type: none"><li>• CyberArk</li><li>• Password</li><li>• Lieberman</li><li>• Hashicorp Vault</li></ul> <p>For descriptions of the options for your selected authentication type, see <a href="#">Database Credentials Authentication</a>.</p>
Port	<p>The TCP port that the PostgreSQL database instance listens on for communications from Tenable Security Center. The default is port 5432.</p>
Database Name	<p>The name for your database instance.</p>



## SQL Server

The following table describes the additional options to configure for **SQL Server** credentials.

Options	Description
Source	<p>The method for providing the required credential details: <b>Entry</b> or <b>Import</b>.</p> <ul style="list-style-type: none"><li>• <b>Entry</b>—Specifies you want to use a single SID value or SERVICE_NAME value for the credential. You must also configure the remaining options on the <b>Add Credential</b> page, as described in <a href="#">Add Credentials</a>.</li><li>• <b>Import</b>—Specifies you want to use multiple SID values for the credential, uploaded as a .csv file. For more information about the required .csv file format, see <a href="#">Database Credentials Authentication</a>.</li></ul>
Authentication Method	<p>The authentication method for providing the required credentials.</p> <ul style="list-style-type: none"><li>• CyberArk</li><li>• Password</li><li>• Lieberman</li><li>• Hashicorp Vault</li><li>• Wallix Bastion</li></ul> <p>For descriptions of the options for your selected authentication type, see <a href="#">Database Credentials Authentication</a>.</p>
Username	The username for a user on the database.
Password	The password associated with the username you provided.
Port	The TCP port that the SQL Server database instance listens on for communications from Tenable Security Center. The default is port 1433.



Options	Description
Authentication	The type of account you want Tenable Security Center to use to access the database instance: <b>SQL</b> or <b>Windows</b> .
Instance Name	The name for your database instance.

## Sybase ASE

The following table describes the additional options to configure for **Sybase ASE** credentials.

Options	Description
Authentication Method	<p>The authentication method for providing the required credentials.</p> <ul style="list-style-type: none"><li>• CyberArk</li><li>• Password</li><li>• Lieberman</li><li>• Hashicorp Vault</li><li>• Wallix Bastion</li></ul> <p>For descriptions of the options for your selected authentication type, see <a href="#">Database Credentials Authentication</a>.</p>
Port	The TCP port that the Sybase ASE database instance listens on for communications from Tenable Security Center. The default is port 3638.
Sybase ASE Auth Type	The type of authentication used by the Sybase ASE database: <b>RSA</b> or <b>Plain Text</b> .

## Apache Cassandra



Option	Description
Authentication Method	<p>The authentication method for providing the required credentials.</p> <ul style="list-style-type: none"><li>• CyberArk</li><li>• Password</li><li>• Lieberman</li><li>• Hashicorp Vault</li><li>• Wallix Bastion</li></ul> <p>For descriptions of the options for your selected authentication type, see <a href="#">Database Credentials Authentication</a>.</p>
Database Port	The port the database listens on. The default is port 9042.

## MongoDB

Option	Description
Username	The username for the database.
Password	The password for the supplied username.
Database	<p>The name of the database to authenticate to.</p> <div style="border: 1px solid green; padding: 5px;"><p><b>Tip:</b> To authenticate via LDAP or saslauthd, type <b>\$external</b>.</p></div>
Port	(Required) The TCP port that the MongoDB database instance listens on for communications from Tenable Security Center.



## Database Credentials Authentication Method Settings

Depending on the authentication type you select for your database credentials, you must configure the following options. For more information about database credential settings, see [Database Credentials](#).

- [Import](#)
- [CyberArk Vault Options](#)
- [Password Options](#)
- [Lieberman Options](#)
- [Hashicorp Vault Options](#)
- [Wallix Bastion Options](#)

### Import

Upload a .csv file with the credentials entered in the specified format. For descriptions of valid values to use for each item, see [Database Credentials](#).

You must configure either CyberArk or HashiCorp credentials for a database credential in the same scan so that Tenable Security Center can retrieve the credentials.

Database Credential	CSV Format
<b>IBM DB2</b>	target, port, database_name, username, cred_manager, accountname_or_secretname
<b>MySQL</b>	target, port, database_name, username, cred_manager, accountname_or_secretname
<b>Oracle</b>	target, port, service_type, service_ID, username, auth_type, cred_manager, accountname_or_secretname
<b>SQL Server</b>	target, port, instance_name, username, auth_type, cred_manager, accountname_or_secretname



**Note:** Include the required data in the specified order, with commas between each value, without spaces. For example, for Oracle with CyberArk: 192.0.2.255,1521,SID,service\_id,username,SYSDBA,CyberArk,Database-Oracle-SYS.

**Note:** The value for cred\_manager must be either *CyberArk* or *HashiCorp*.

## CyberArk Vault Options

The following table describes the additional options to configure when using CyberArk as the **Authentication Method** for **IBM DB2**, **SQL Server**, **MySQL**, **Oracle Database**, or **PostgreSQL** database credentials.

**Note:** You must be running Tenable Nessus 7.0.0 or later to configure CyberArk credentials.

Option	Database Types	Description
Username	All	The username for the target system.
Port	All	The port the database is listening on.
Service Type	Oracle Database	The Oracle parameter you want to use to identify the database instance: <b>SID</b> or <b>Service Name</b> .
Service	Oracle Database	The SID value for your database instance or a SERVICE_NAME value.  The <b>Service</b> value you enter must match your parameter selection for the <b>Service Type</b> option.
Database Name	IBM D2 Postgre SQL	The name for your database instance.
Central Credential Provider URL Host	All	The IP/DNS address of the CyberArk Central Credential Provider.
Central Credential Pro-	All	The port the CyberArk Central Credential Provider is listening on.





Option	Database Types	Description
vider URL Port		
<b>Vault User-name</b>	All	The username for the vault, if the CyberArk Central Credential Provider is configured for basic authentication.
<b>Vault Password</b>	All	The password for the vault, if the CyberArk Central Credential Provider is configured for basic authentication.
<b>Safe</b>	All	The safe on the CyberArk Central Credential Provider server that contains the credentials you want to retrieve.
<b>CyberArk Client Certificate</b>	All	The file that contains the PEM certificate used to communicate with the CyberArk host.
<b>CyberArk Client Certificate Private Key</b>	All	The file that contains the PEM private key for the client certificate.
<b>CyberArk Client Certificate Private Key Passphrase</b>	All	The passphrase for the private key, if required.
<b>AppID</b>	All	The AppID with CyberArk Central Credential Provider permissions to retrieve the target password.
<b>Folder</b>	All	The folder on the CyberArk Central Credential Provider server that contains the credentials you want to retrieve.
<b>PolicyID</b>	All	The PolicyID assigned to the credentials you want to retrieve from the CyberArk Central Credential Provider.
<b>Vault Use SSL</b>	All	When enabled, Tenable Security Center uses SSL through IIS for secure communications. You must configure SSL through IIS in CyberArk Central Credential Provider before enabling this option.
<b>Vault Verify</b>	All	When enabled, Tenable Security Center validates the SSL



Option	Database Types	Description
SSL		certificate. You must configure SSL through IIS in CyberArk Central Credential Provider before enabling this option.  For more information about using self-signed certificates, see the Nessus custom_CA.inc documentation.
CyberArk AIM Service URL	All	The URL for the CyberArk AIM web service. By default, Tenable Security Center uses <code>/AIM/ebservice/v1.1/AIM.asmx</code> .

## Password Options

The following table describes the additional options to configure when using Password as the **Authentication Method** for database credentials.

Option	Database Types	Description
Username	All	The username for a user on the database.
Password	All	The password associated with the username you provided.
Port	All	The port the database is listening on.
Database Name	IBM D2 PostgreSQL	The name for your database instance.
Authentication	Oracle Database SQL Server	The type of account you want Tenable Security Center to use to access the database instance.
Service Type	Oracle Database	The Oracle parameter you want to use to identify the database instance: <b>SID</b> or <b>Service Name</b> .
Service	Oracle Database	The SID value for your database instance or a SERVICE_NAME value.



Option	Database Types	Description
		The <b>Service</b> value you enter must match your parameter selection for the <b>Service Type</b> option.
<b>Instance Name</b>	SQL Server	The name for your database instance.

## Lieberman Options

The following table describes the additional options to configure when using Lieberman as the **Authentication Method** for **IBM DB2**, **SQL Server**, **MySQL**, **Oracle Database**, or **PostgreSQL** database credentials.

**Note:** You must meet the version requirements specified in [Tenable Integrated Product Compatibility](#).

Option	Database Types	Description
<b>Username</b>	All	The username for a user on the database.
<b>Port</b>	All	The port the database is listening on.
<b>Database Name</b>	IBM DB2 PostgreSQL	The name for your database instance.
<b>Authentication</b>	Oracle Database SQL Server	The type of account you want Tenable Security Center to use to access the database instance.
<b>Service Type</b>	Oracle Database	The Oracle parameter you want to use to identify the database instance: <b>SID</b> or <b>Service Name</b> .
<b>Service</b>	Oracle Database	The SID value for your database instance or a SERVICE_NAME value.  The <b>Service</b> value you enter must match your parameter selection for the <b>Service Type</b> option.



Option	Database Types	Description
Instance Name	SQL Server	The name for your database instance.
Lieberman Host	All	The Lieberman IP address or DNS address.
Lieberman Port	All	The port Lieberman is listening on.
Lieberman User	All	The username for the Lieberman explicit user you want Tenable Security Center to use for authentication to the Lieberman Rapid Enterprise Defense (RED) API.
Lieberman Password	All	The password for the Lieberman explicit user.
Use SSL	All	When enabled, Tenable Security Center uses SSL through IIS for secure communications. You must configure SSL through IIS in Lieberman before enabling this option.
Verify SSL Certificate	All	When enabled, Tenable Security Center validates the SSL certificate. You must configure SSL through IIS in Lieberman before enabling this option.
System Name	All	The name for the database credentials in Lieberman.

## Hashicorp Vault Options

The following table describes the additional options to configure when using Hashicorp Vault as the **Authentication Method** for **IBM DB2**, **SQL Server**, **MySQL**, **Oracle Database**, or **PostgreSQL** database credentials.

Option	Credential	Description	Required
Port	Oracle Database IBM DB2	The port on which Tenable Security Center communicates with the database.	yes



	MySQL PostgreSQL SQL Server		
<b>SID</b>	MySQL	The security identifier used to connect to the database.	yes
<b>Database Name</b>	IBM DB2 PostgreSQL	The name of the database.	no
<b>Instance Name</b>	SQL Server	The SQL server name.	yes
<b>Hashicorp Host</b>	All	The Hashicorp Vault IP address or DNS address. <div style="border: 1px solid blue; padding: 5px; margin-top: 10px;"><b>Note:</b> If your Hashicorp Vault installation is in a subdirectory, you must include the subdirectory path. For example, type <i>IP address or hostname/sub-directory path</i>.</div>	yes
<b>Hashicorp Port</b>	All	The port on which Hashicorp Vault listens.	yes
<b>Service Type</b>	Oracle Database	The unique <b>SID</b> or <b>Service Name</b> that identifies your database.	yes
<b>Service</b>	Oracle Database	The <b>SID</b> or <b>Service Name</b> value for your database instance. <div style="border: 1px solid blue; padding: 5px; margin-top: 10px;"><b>Note:</b> The <b>Service</b> value must match the <b>Service Type</b> option parameter selection.</div>	yes
<b>Authentication Type</b>	All	Specifies the authentication type for connecting to the instance: <b>App Role</b> or <b>Certificates</b> .	yes



<b>Client Cert</b>	All	If <b>Authentication Type</b> is <b>Certificates</b> , the client certificate file you want to use to authenticate the connection.	yes
<b>Private Key</b>	All	If <b>Authentication Type</b> is <b>Certificates</b> , the private key file associated with the client certificate you want to use to authenticate the connection.	yes
<b>Role ID</b>	All	The GUID provided by Hashicorp Vault when you configured your App Role.	yes
<b>Role Secret ID</b>	All	The GUID generated by Hashicorp Vault when you configured your App Role.	yes
<b>Authentication URL</b>	All	The path/subdirectory to the authentication endpoint. This is not the full URL. For example:  /v1/auth/approle/login	yes
<b>Namespace</b>	All	The name of a specified team in a multi-team environment.	no
<b>Hashicorp Vault Type</b>	All	The type of Hashicorp Vault secrets engine: <ul style="list-style-type: none"><li>• <b>KV1</b>—Key/Value Secrets Engine Version 1</li><li>• <b>KV2</b>—Key/Value Secrets Engine Version 2</li><li>• <b>AD</b>—Active Directory</li></ul>	yes
<b>KV Engine URL</b>	All	The URL Tenable Security Center	yes



		uses to access the Hashicorp Vault secrets engine. Example: /v1/path_to_secret. No trailing /	
<b>Username Source</b>	All	(Only displays if <b>Hashicorp Vault Type</b> is <b>KV1</b> or <b>KV2</b> ) Specifies if the username is input manually or pulled from Hashicorp Vault.	yes
<b>Username key</b>	All	(Only displays if <b>Hashicorp Vault Type</b> is <b>KV1</b> or <b>KV2</b> ) The name in Hashicorp Vault that usernames are stored under.	no
<b>Username</b>	All	(Only displays if <b>Username Source</b> is <b>Manual Entry</b> ) The name in Hashicorp Vault that usernames are stored under.	yes
<b>Password key</b>	All	(Only displays if <b>Hashicorp Vault Type</b> is <b>KV1</b> or <b>KV2</b> ) The key in Hashicorp Vault that passwords are stored under.	no
<b>Secret Name</b>	All	The key secret you want to retrieve values for.	yes
<b>Use SSL</b>	All	When enabled, Tenable Security Center uses SSL for secure communications. You must configure SSL in Hashicorp Vault before enabling this option.	no
<b>Verify SSL</b>	All	When enabled, Tenable Security Center validates the SSL certificate. You must configure SSL in Hashicorp Vault before enabling	no



this option.

## Wallix Bastion Options

The following table describes the additional options to configure when using Wallix Bastion as the **Authentication Method** for **Apache Cassandra**, **IBM DB2**, **MySQL**, **Oracle Database**, **SQL Server**, or **Sybase ASE** database credentials.

Option	Description	Required
Port	The port the database is listening on.	no
WALLIX Host	The IP address for the WALLIX Bastion host.	yes
WALLIX Port	The port on which the WALLIX Bastion API communicates. By default, Tenable uses 443.	yes
Authentication Type	<b>Basic</b> authentication (with WALLIX Bastion user interface username and Password requirements) or <b>API Key</b> authentication (with username and WALLIX Bastion-generated API key requirements).	no
WALLIX User	Your WALLIX Bastion user interface login username.	yes
WALLIX Password	Your WALLIX Bastion user interface login password. Used for <b>Basic</b> authentication to the API.	yes
WALLIX API Key	The API key generated in the WALLIX Bastion user interface. Used for <b>API Key</b> authentication to the API.	yes
Get Credential by Device Account Name	The account name associated with a <b>Device</b> you want to log in to the target systems with.  <b>Note:</b> If your device has more than one account you must enter the specific device name for the	Required only if you have a target and/or device with multiple accounts.





Option	Description	Required
	<p>account you want to retrieve credentials for. Failure to do this may result in credentials for the wrong account returned by the system.</p>	
HTTPS	<p>This is enabled by default.</p> <p><b>Caution:</b> The integration fails if you disable HTTPS.</p>	yes
Verify SSL Certificate	<p>This is disabled by default and is not supported in WALLIX Bastion PAM integrations.</p>	no



## SNMP Credentials

Configure the following options for SNMP credentials. Tenable Security Center supports SNMPv1 for authentication via a community string.

Options	Description
Name	(Required) A name for the credential.
Description	A description for the credential.
Tag	A tag for the credential. For more information, see <a href="#">Tags</a> .
Community	The SNMP community string used for authentication.



## SSH Credentials

Use SSH credentials for host-based checks on Unix systems and supported network devices. Tenable Security Center uses these credentials to obtain local information from remote Unix systems for patch auditing or compliance checks. Tenable Security Center uses Secure Shell (SSH) protocol version 2 based programs (e.g., OpenSSH, Solaris SSH, etc.) for host-based checks.

Tenable Security Center encrypts the data using the AES-256-CBC algorithm to protect it from being viewed by sniffer programs.

**Note:** Non-privileged users with local access on Linux systems can determine basic security issues, such as patch levels or entries in the `/etc/passwd` file. For more comprehensive information, such as system configuration data or file permissions across the entire system, an account with root privileges is required.

**Note:** You can add up to 1000 SSH credentials in a single scan. For best performance, Tenable recommends adding no more than 10 SSH credentials per scan.

Configure the following options for SSH credentials, including options specific for your authentication method: [Arcon Options](#), [Centrify Options](#), [Certificate Options](#), [CyberArk Vault \(Legacy\) Options](#), [CyberArk Vault Options](#), [Hashicorp Vault Options](#), [Kerberos Options](#), [Password Options](#), [Public Key Options](#), [Thycotic Secret Server Options](#), [BeyondTrust Options](#), [Lieberman Options](#), and [WALLIX Bastion Options](#).

General Option	Description
Name	(Required) A name for the credential.
Description	A description for the credential.
Tag	A tag for the credential. For more information, see <a href="#">Tags</a> .

### Arcon Options

The following table describes the additional options to configure when using **Arcon** as the authentication method for SSH credentials.

Option	Description
Arcon Host	(Required) The Arcon IP address or DNS address.



	<p><b>Note:</b> If your Arcon installation is in a subdirectory, you must include the subdirectory path. For example, type <i>IP address or hostname/ subdirectory path</i>.</p>
<b>Arcon Port</b>	(Required) The port on which Arcon listens. By default, Tenable Security Center uses port 444.
<b>API User</b>	(Required) The API user provided by Arcon.
<b>API Key</b>	(Required) The API key provided by Arcon.
<b>Authentication URL</b>	(Required) The URL Tenable Security Center uses to access Arcon.
<b>Password Engine URL</b>	(Required) The URL Tenable Security Center uses to access the passwords in Arcon.
<b>Username</b>	(Required) The username to log in to the hosts you want to scan.
<b>Checkout Duration</b>	<p>(Required) The length of time, in minutes, that you want to keep credentials checked out in Arcon. Configure the <b>Checkout Duration</b> to exceed the typical duration of your Tenable Security Center scans. If a password from a previous scan is still checked out when a new scan begins, the new scan fails.</p> <p><b>Tip:</b> Configure the password change interval in Arcon so that password changes do not disrupt your Tenable Security Center scans. If Arcon changes a password during a scan, the scan fails.</p>
<b>Use SSL</b>	When enabled, Tenable Security Center uses SSL through IIS for secure communications. You must configure SSL through IIS in Arcon before enabling this option.
<b>Verify SSL Certificate</b>	When enabled, Tenable Security Center validates the SSL certificate. You must configure SSL through IIS in Arcon before enabling this option.



<b>Privilege Escalation</b>	The privilege escalation method you want to use to increase users' privileges after initial authentication. Your <b>Privilege Escalation</b> selection determines the specific options you must configure. For more information, see <a href="#">Privilege Escalation</a> .
-----------------------------	---

## Centrify Options

The following table describes the additional options to configure when using **Centrify** as the authentication method for SSH credentials.

Option	Description
<b>Centrify Host</b>	(Required) The Centrify IP address or DNS address.  <b>Note:</b> If your Centrify installation is in a subdirectory, you must include the subdirectory path. For example, type <i>IP address or hostname/subdirectory path</i> .
<b>Centrify Port</b>	(Required) The port on which Centrify listens. By default, Tenable Security Center uses port 443.
<b>API User</b>	(Required) The API user provided by Centrify.
<b>API Key</b>	(Required) The API key provided by Centrify.
<b>Tenant</b>	(Required) The Centrify tenant associated with the API. By default, Tenable Security Center uses <i>centrify</i> .
<b>Authentication URL</b>	(Required) The URL Tenable Security Center uses to access Centrify. By default, Tenable Security Center uses <i>/Security</i> .
<b>Password Query URL</b>	(Required) The URL Tenable Security Center uses to query the passwords in Centrify. By default, Tenable Security Center uses <i>/RedRock</i> .
<b>Password Engine URL</b>	(Required) The URL Tenable Security Center uses to access the passwords in Centrify. By default, Tenable Security Center uses <i>/ServerManage</i> .



<b>Username</b>	(Required) The username to log in to the hosts you want to scan.
<b>Checkout Duration</b>	(Required) The length of time, in minutes, that you want to keep credentials checked out in Centrify.  Configure the <b>Checkout Duration</b> to exceed the typical duration of your Tenable Security Center scans so that password changes do not disrupt your Tenable Security Center scans. If Centrify changes a password during a scan, the scan fails. If a password from a previous scan is still checked out when a new scan begins, the new scan fails.
<b>Use SSL</b>	When enabled, Tenable Security Center uses SSL through IIS for secure communications. You must configure SSL through IIS in Centrify before enabling this option.
<b>Verify SSL Certificate</b>	When enabled, Tenable Security Center validates the SSL certificate. You must configure SSL through IIS in Centrify before enabling this option.

## Certificate Options

The following table describes the additional options to configure when using **Certificate** as the authentication method for SSH credentials.

Option	Description
<b>Username</b>	(Required) The username for a user on the host system.
<b>User Certificate</b>	(Required) The RSA or DSA OpenSSH certificate file for the user.
<b>Private Key</b>	(Required) The RSA or DSA OpenSSH private key file for the user.
<b>Passphrase</b>	The passphrase for the private key, if required.
<b>Privilege Escalation</b>	The privilege escalation method you want to use to increase users' privileges after initial authentication. Your <b>Privilege Escalation</b> selection determines




Option	Description
	the specific options you must configure. For more information, see <a href="#">Privilege Escalation</a> .

## CyberArk Vault (Legacy) Options

The following table describes the additional options to configure when using **CyberArk Vault (Legacy)** as the authentication method for SSH credentials.

Option	Description
<b>Username</b>	(Required) The username for the target system.
<b>CyberArk elevate privileges with</b>	The privilege escalation method you want to use to increase users' privileges after initial authentication. Your <b>CyberArk elevate privileges with</b> selection determines the specific options you must configure. For more information, see <a href="#">Privilege Escalation</a> .
<b>Central Credential Provider URL Host</b>	(Required) The CyberArk Central Credential Provider IP/DNS address.
<b>Central Credential Provider URL Port</b>	(Required) The port the CyberArk Central Credential Provider is listening on.
<b>CyberArk Address</b>	The domain for the CyberArk account. You must configure SSL through IIS in CyberArk Central Credential Provider before configuring this option.
<b>Vault Username</b>	The username for the vault, if the CyberArk Central Credential Provider is configured for basic authentication.
<b>Vault Password</b>	The password for the vault, if the CyberArk Central Credential Provider is configured for basic authentication.
<b>Safe</b>	(Required) The safe on the CyberArk Central Credential Provider server that contains the credentials you want to retrieve.
<b>CyberArk Cli-</b>	The file that contains the PEM certificate used to communicate with the



Option	Description
ent Certificate	CyberArk host.
CyberArk Client Certificate Private Key	The file that contains the PEM private key for the client certificate.
CyberArk Client Certificate Private Key Passphrase	The passphrase for the private key, if required.
AppID	(Required) The AppID with CyberArk Central Credential Provider permissions to retrieve the target password.
Folder	(Required) The folder on the CyberArk Central Credential Provider server that contains the credentials you want to retrieve.
PolicyID	The PolicyID assigned to the credentials you want to retrieve.
Vault Use SSL	When enabled, Tenable Security Center uses SSL through IIS for secure communications. You must configure SSL through IIS in CyberArk Central Credential Provider before enabling this option.
Vault Verify SSL	When enabled, Tenable Security Center validates the SSL certificate. You must configure SSL through IIS in CyberArk Central Credential Provider before enabling this option.
CyberArk Escalation Account Details Name	The unique name of the credential you want to retrieve from CyberArk. 





Option	Description
<b>CyberArk AIM Service URL</b>	The URL for the CyberArk AIM web service. By default, Tenable Security Center uses <code>/AIMWebservice/v1.1/AIM.asmx</code> .

## CyberArk Vault Options

The following table describes the additional options to configure when using **CyberArk Vault** as the authentication method for SSH credentials.

Option	Description	Required
CyberArk Host	The IP address or FQDN name for the CyberArk AIM Web Service.	yes
Port	The port on which the CyberArk API communicates. By default, Tenable uses 443.	yes
AppId	The Application ID associated with the CyberArk API connection.	yes
Client Certificate	The file that contains the PEM certificate used to communicate with the CyberArk host.	no
Client Certificate Private Key	The file that contains the PEM private key for the client certificate.	yes, if private key is applied
Client Certificate Private Key Passphrase	The passphrase for the private key, if required.	yes, if private key is applied
Get credential by	The method with which your CyberArk API credentials are retrieved. Can be <b>Username</b> , <b>Identifier</b> , or <b>Address</b> .  <b>Note:</b> The frequency of queries for <b>Username</b> is one query per target. The frequency of queries for <b>Identifier</b> is one query per chunk. This feature requires all targets have the same identifier.	yes



Option	Description	Required
	<p><b>Note:</b> The <b>Username</b> option also adds the <b>Address</b> parameter of the API query and assigns the target IP of the resolved host to the <b>Address</b> parameter. This may lead to failure to fetch credentials if the CyberArk Account Details <b>Address</b> field contains a value other than the target IP address.</p>	
Username	(If <b>Get credential by</b> is <b>Username</b> ) The username of the CyberArk user to request a password from.	no
Safe	The CyberArk safe the credential should be retrieved from.	no
Address	The option should only be used if the Address value is unique to a single CyberArk account credential.	no
Account Name	(If <b>Get credential by</b> is <b>Identifier</b> ) The unique account name or identifier assigned to the CyberArk API credential.	no
Use SSL	If enabled, the scanner uses SSL through IIS for secure communications. Enable this option if CyberArk is configured to support SSL through IIS.	no
Verify SSL Certificate	If enabled, the scanner validates the SSL certificate. Enable this option if CyberArk is configured to support SSL through IIS and you want to validate the certificate.	no

## Hashicorp Vault Options

The following table describes the additional options to configure when using **Hashicorp Vault** as the authentication method for SSH credentials.

Option	Default Value	Required
<b>Hashicorp Host</b>	The Hashicorp Vault IP address or DNS address.	yes



	<p><b>Note:</b> If your Hashicorp Vault installation is in a sub-directory, you must include the subdirectory path. For example, type <i>IP address or hostname/subdirectory path</i>.</p>	
<b>Hashicorp Port</b>	The port on which Hashicorp Vault listens.	yes
<b>Authentication Type</b>	<p>Specifies the authentication type for connecting to the instance: <b>App Role</b> or <b>Certificates</b>.</p> <p>If you select <b>Certificates</b>, additional options for <b>Hashicorp Client Certificate</b> (Required) and <b>Hashicorp Client Certificate Private Key</b> (Required) appear. Select the appropriate files for the client certificate and private key.</p>	yes
<b>Role ID</b>	The GUID provided by Hashicorp Vault when you configured your App Role.	yes
<b>Role Secret ID</b>	The GUID generated by Hashicorp Vault when you configured your App Role.	yes
<b>Authentication URL</b>	<p>The path/subdirectory to the authentication endpoint. This is not the full URL. For example:</p> <p><code>/v1/auth/approle/login</code></p>	yes
<b>Namespace</b>	The name of a specified team in a multi-team environment.	no
<b>Hashicorp Vault Type</b>	<p>The type of Hashicorp Vault secrets engine:</p> <ul style="list-style-type: none"><li>• <b>KV1</b>—Key/Value Secrets Engine Version 1</li><li>• <b>KV2</b>—Key/Value Secrets Engine Version 2</li><li>• <b>AD</b>—Active Directory</li></ul>	yes
<b>KV Engine URL</b>	<p>The URL Tenable Security Center uses to access the Hashicorp Vault secrets engine.</p> <p>Example: <code>/v1/path_to_secret</code>. No trailing <code>/</code></p>	yes



<b>Username Source</b>	(Only displays if <b>Hashicorp Vault Type</b> is <b>KV1</b> or <b>KV2</b> ) Specifies if the username is input manually or pulled from Hashicorp Vault.	yes
<b>Username key</b>	(Only displays if <b>Hashicorp Vault Type</b> is <b>KV1</b> or <b>KV2</b> ) The name in Hashicorp Vault that usernames are stored under.	yes
<b>Password key</b>	(Only displays if <b>Hashicorp Vault Type</b> is <b>KV1</b> or <b>KV2</b> ) The key in Hashicorp Vault that passwords are stored under.	yes
<b>Secret Name</b>	The key secret you want to retrieve values for.	yes
<b>Use SSL</b>	When enabled, Tenable Security Center uses SSL for secure communications. You must configure SSL in Hashicorp Vault before enabling this option.	no
<b>Verify SSL</b>	When enabled, Tenable Security Center validates the SSL certificate. You must configure SSL in Hashicorp Vault before enabling this option.	no

## Kerberos Options

The following table describes the additional options to configure when using **Kerberos** as the authentication method for SSH credentials.

Option	Description
<b>Username</b>	(Required) The username for a user on the target system.
<b>Password</b>	(Required) The password associated with the username you provided.
<b>KDC Host</b>	(Required) The host supplying the session tickets.
<b>KDC Port</b>	(Required) The port you want to use for the KDC connection. By default, Tenable Security Center uses port 88.
<b>KDC Transport</b>	(Required) The method you want to use to connect to the KDC server. <div style="border: 1px solid blue; padding: 5px; margin-top: 10px;"><b>Note:</b> If you select UDP, you may need to edit the KDC Port. The KDC UDP pro-</div>



Option	Description
	toocol uses either port 88 or port 750.
<b>Realm</b>	(Required) The authentication domain, typically the domain name of the target (e.g., <i>example.com</i> ).
<b>Privilege Escalation</b>	The privilege escalation method you want to use to increase users' privileges after initial authentication. Your <b>Privilege Escalation</b> selection determines the specific options you must configure. For more information, see <a href="#">Privilege Escalation</a> .

## Password Options

The most effective credentialed scans are those with root privileges (enable privileges, for Cisco IOS). Since many sites do not permit a remote login as root for security reasons, a Nessus user account can invoke a variety of privilege escalation options including: su, sudo, su+sudo, DirectAuthorize (dzdo), PowerBroker (pbrun), k5login, and Cisco Enable.

The following table describes the additional options to configure when using **Password** as the authentication method for SSH credentials.

Option	Description
<b>Username</b>	(Required) The username for a user on the target system.
<b>Password</b>	(Required) The password associated with the username you provided.
<b>Privilege Escalation</b>	The privilege escalation method you want to use to increase users' privileges after initial authentication. Your <b>Privilege Escalation</b> selection determines the specific options you must configure. For more information, see <a href="#">Privilege Escalation</a> .

## Public Key Options

The following table describes the additional options to configure when using **Public Key** as the authentication method for SSH credentials.



Option	Description
<b>Username</b>	(Required) The username for a user on the host system.
<b>Private Key</b>	(Required) The RSA or DSA OpenSSH key file for the user.
<b>Passphrase</b>	The passphrase for the private key, if required.
<b>Privilege Escalation</b>	The privilege escalation method you want to use to increase users' privileges after initial authentication. Your <b>Privilege Escalation</b> selection determines the specific options you must configure. For more information, see <a href="#">Privilege Escalation</a> .

## Thycotic Secret Server Options

The following table describes the additional options to configure when using **Thycotic Secret Server** as the authentication method for SSH credentials.

Option	Description
<b>Username</b>	(Required) The username for a user on the target system.
<b>Thycotic elevate privileges with</b>	The privilege escalation method you want to use to increase users' privileges after initial authentication. Your selection for this setting determines the specific options you must configure. For more information, see <a href="#">Privilege Escalation</a> .
<b>Thycotic Secret Name</b>	The Secret Name value on the Thycotic server.
<b>Thycotic Secret Server URL</b>	(Required) The value you want Tenable Security Center to use when setting the transfer method, target, and target directory for the scanner. Find the value on the Thycotic server, in <b>Admin &gt; Configuration &gt; Application Settings &gt; Secret Server URL</b> .  For example, if you type <i>https://pw.mydomain.com/SecretServer</i> , Tenable Security Center determines it is an SSL connection, that <i>pw.mydomain.com</i> is the target address, and that <i>/SecretServer</i> is the root directory.
<b>Thycotic Login</b>	(Required) The username for a user on the Thycotic server.



Option	Description
<b>Name</b>	
<b>Thycotic Password</b>	(Required) The password associated with the <b>Thycotic Login Name</b> you provided.
<b>Thycotic Organization</b>	In cloud instances of Thycotic, the value that identifies the organization you want Tenable Security Center to target.
<b>Thycotic Domain</b>	The domain, if set for the Thycotic server.
<b>Verify SSL Certificate</b>	If enabled, Tenable Security Center verifies the SSL Certificate on the Thycotic server.  For more information about using self-signed certificates, see the Nessus custom_CA.inc documentation.
<b>Use Private Key</b>	If enabled, Tenable Security Center uses key-based authentication for SSH connections instead of password authentication.

## BeyondTrust Options

The following table describes the additional options to configure when using **BeyondTrust** as the authentication method for SSH credentials.

Option	Description
<b>Username</b>	The username to log in to the hosts you want to scan.
<b>BeyondTrust Host</b>	The BeyondTrust IP address or DNS address.
<b>BeyondTrust Port</b>	The port BeyondTrust is listening on.
<b>BeyondTrust API User</b>	The API user provided by BeyondTrust.
<b>BeyondTrust API Key</b>	The API key provided by BeyondTrust.



Option	Description
<b>Checkout Duration</b>	<p>The length of time, in minutes, that you want to keep credentials checked out in BeyondTrust. Configure the <b>Checkout duration</b> to exceed the typical duration of your Tenable Security Center scans. If a password from a previous scan is still checked out when a new scan begins, the new scan fails.</p> <div style="border: 1px solid green; padding: 5px;"><p><b>Tip:</b> Configure the password change interval in BeyondTrust so that password changes do not disrupt your Tenable Security Center scans. If BeyondTrust changes a password during a scan, the scan fails.</p></div>
<b>Use SSL</b>	<p>If enabled, Tenable Security Center uses SSL through IIS for secure communications. You must configure SSL through IIS in BeyondTrust before enabling this option.</p>
<b>Verify SSL Certificate</b>	<p>If enabled, Tenable Security Center validates the SSL certificate. You must configure SSL through IIS in BeyondTrust before enabling this option.</p>
<b>Use Private Key</b>	<p>If enabled, Tenable Security Center uses key-based authentication for SSH connections instead of password authentication.</p>
<b>Use Privilege Escalations</b>	<p>If enabled, Tenable Security Center uses BeyondTrust for privilege escalation.</p>

## Lieberman Options

The following table describes the additional options to configure when using **Lieberman** as the authentication method for SSH credentials.

Option	Description
<b>Username</b>	<p>The username for a user on the database.</p>
<b>Lieberman Host</b>	<p>The Lieberman IP address or DNS address.</p> <div style="border: 1px solid blue; padding: 5px;"><p><b>Note:</b> If your Lieberman installation is in a subdirectory, you must include the subdirectory path. For example, type <i>IP address or hostname/sub-</i></p></div>





Option	Description
	<code>directory path.</code>
<b>Lieberman Port</b>	The port Lieberman is listening on.
<b>Lieberman User</b>	The username for the Lieberman explicit user you want Tenable Security Center to use for authentication to the Lieberman Rapid Enterprise Defense (RED) API.
<b>Lieberman Password</b>	The password for the Lieberman explicit user.
<b>Use SSL</b>	When enabled, Tenable Security Center uses SSL through IIS for secure communications. You must configure SSL through IIS in Lieberman before enabling this option.
<b>Verify SSL Certificate</b>	When enabled, Tenable Security Center validates the SSL certificate. You must configure SSL through IIS in Lieberman before enabling this option.
<b>System Name</b>	The name for the database credentials in Lieberman.

## WALLIX Bastion Options

The following table describes the additional options to configure when using **WALLIX Bastion** as the authentication method for SSH credentials.

Option	Description	Required
WALLIX Host	The IP address for the WALLIX Bastion host.	yes
WALLIX Port	The port on which the WALLIX Bastion API communicates. By default, Tenable uses 443.	<b>yes</b>
Authentication Type	<b>Basic</b> authentication (with WALLIX Bastion user interface username and Password requirements) or <b>API Key</b> authentication (with username and WALLIX Bastion-generated API key require-	no



Option	Description	Required
	ments).	
WALLIX User	Your WALLIX Bastion user interface login user-name.	yes
WALLIX Password	Your WALLIX Bastion user interface login password. Used for <b>Basic</b> authentication to the API.	yes
WALLIX API Key	The API key generated in the WALLIX Bastion user interface. Used for <b>API Key</b> authentication to the API.	yes
Get Credential by Device Account Name	<p>The account name associated with a <b>Device</b> you want to log in to the target systems with.</p> <div style="border: 1px solid blue; padding: 5px;"><p><b>Note:</b> If your device has more than one account you must enter the specific device name for the account you want to retrieve credentials for. Failure to do this may result in credentials for the wrong account returned by the system.</p></div>	Required only if you have a target and/or device with multiple accounts.
HTTPS	<p>This is enabled by default.</p> <div style="border: 1px solid red; padding: 5px;"><p><b>Caution:</b> The integration fails if you disable <b>HTTPS</b>.</p></div>	yes
Verify SSL Certificate	This is disabled by default and is not supported in WALLIX Bastion PAM integrations.	no
Privilege Escalation	<p>This enables WALLIX Bastion Privileged Access Management (PAM). Use the drop-down menu to select the privilege elevation method. To bypass this function, leave this field set to <b>Nothing</b>.</p> <div style="border: 1px solid red; padding: 5px;"><p><b>Caution:</b> In your WALLIX Bastion account, the WALLIX Bastion super admin must have enabled "credential recovery" on your account for PAM to be enabled. Otherwise, your scan may not return</p></div>	Required if you wish to escalate privileges.



Option	Description	Required
	<p data-bbox="516 239 1195 352">any results. For more information, see your WALLIX Bastion documentation.</p> <p data-bbox="516 380 1195 768"><b>Note:</b> Multiple options for privilege escalation are supported, including <i>su</i>, <i>su+sudo</i> and <i>sudo</i>. For example, if you select <b>sudo</b>, more fields for <b>sudo user</b>, <b>Escalation Account Name</b>, and <b>Location of su and sudo</b> (directory) are provided and can be completed to support authentication and privilege escalation through WALLIX Bastion PAM. The <b>Escalation Account Name</b> field is then required to complete your privilege escalation.</p> <p data-bbox="516 795 1195 947"><b>Note:</b> For more information about supported privilege escalation types and their accompanying fields, see <a href="#">Privilege Escalation</a>.</p>	



## Privilege Escalation

Some SSH credential types support privilege escalation.

**Note:** BeyondTrust's PowerBroker (pbrun) and Centrify's DirectAuthorize (dzdo) are proprietary root task delegation methods for Unix and Linux systems.

**Tip:** Scans run using su+sudo allow the user to scan with a non-privileged account and then switch to a user with sudo privileges on the remote host. This is important for locations where remote privileged login is prohibited.

**Note:** Scans run using sudo vs. the root user do not always return the same results because of the different environmental variables applied to the sudo user and other subtle differences. For more information, see <https://www.sudo.ws/docs/man/sudo.man/>.

The following table describes the additional options to configure for privilege escalation.

Option	SSH Types	Description
<b>Escalation Username</b>	Arcon	The username for the account with elevated privileges.
	Kerberos	
	Password	
	Public Key	
	WALLIX Bastion	
<b>Escalation Password</b>	Kerberos	The password for the account with elevated privileges.
	Password	
	Public Key	
	WALLIX Bastion	
<b>Escalation Path</b>	Arcon	The directory path for the privilege escalation commands.
	Kerberos	



Option	SSH Types	Description
	Password Public Key WALLIX Bas- tion	
<b>Escalation Su User</b>	Arcon CyberArk Kerberos Password Public Key WALLIX Bas- tion	The username for the account with su privileges.
<b>Escalation Account Name</b>	Arcon CyberArk	The name parameter for the account with elevated privileges.  <b>Note:</b> For CyberArk credentials, the system uses the password associated with the CyberArk account name you provide for all scanned hosts.
<b>Escalation Account</b>	CyberArk	The username for the account with elevated privileges.
<b>Escalation sudo user</b>	CyberArk	The username for the account with sudo privileges.
<b>Location of dzdo (directory)</b>	CyberArk	The directory path for the dzdo command.
<b>Location of pbrun (directory)</b>	CyberArk	The directory path for the pbrun command.



Option	SSH Types	Description
Location of su (directory)	CyberArk	The directory path for the su command.
Location of su and sudo (directory)	CyberArk	The directory path for the su and sudo commands.
Location of sudo (directory)	CyberArk	The directory path for the sudo command.
su login	CyberArk	The username for the account with su privileges.
sudo login	CyberArk	The username for the account with sudo privileges.
Thycotic Escalation Account	Thycotic Secret Server	The name parameter for the Thycotic account with elevated privileges. <div style="border: 1px solid blue; padding: 5px; margin-top: 10px;"><b>Note:</b> The system uses the password associated with the Thycotic account name you provide for all scanned hosts.</div>



## Windows Credentials

Nessus has vulnerability checks that can use a Microsoft Windows domain account to find local information from a remote Windows host. For example, using credentials enables Nessus to determine if important security patches have been applied.

**Tip:** Using a non-administrator account will greatly affect the quality of the scan results. Often it makes sense to create a special Nessus user with administrative privileges that is used solely for scheduled scanning.

Configure the following options for Windows credentials, including options specific for your authentication method: [Arcon Options](#), [Centrify Options](#), [CyberArk Vault \(Legacy\) Options](#), [CyberArk Vault Options](#), [Hashicorp Vault Options](#), [Kerberos Options](#), [LM Hash Options](#), [NTLM Hash Options](#), [Password Options](#), [Thycotic Secret Server Options](#), [BeyondTrust Options](#), [Lieberman Options](#), and [WALLIX Bastion Options](#).

General Options	Description
<b>Name</b>	(Required) A name for the credential.
<b>Description</b>	A description for the credential.
<b>Tag</b>	A tag for the credential. For more information, see <a href="#">Tags</a> .

## Arcon Options

The following table describes the additional options to configure when using **Arcon** as the authentication method for Windows credentials.

Option	Description
<b>Arcon Host</b>	(Required) The Arcon IP address or DNS address. <div style="border: 1px solid #0070C0; padding: 5px;"><b>Note:</b> If your Arcon installation is in a subdirectory, you must include the subdirectory path. For example, type <i>IP address or hostname/ subdirectory path</i>.</div>
<b>Arcon Port</b>	(Required) The port on which Arcon listens. By default, Tenable Security Center uses port 444.



<b>API User</b>	(Required) The API user provided by Arcon.
<b>API Key</b>	(Required) The API key provided by Arcon.
<b>Authentication URL</b>	(Required) The URL Tenable Security Center uses to access Arcon.
<b>Password Engine URL</b>	(Required) The URL Tenable Security Center uses to access the passwords in Arcon.
<b>Username</b>	(Required) The username to log in to the hosts you want to scan.
<b>Checkout Duration</b>	<p>(Required) The length of time, in minutes, that you want to keep credentials checked out in Arcon. Configure the <b>Checkout Duration</b> to exceed the typical duration of your Tenable Security Center scans. If a password from a previous scan is still checked out when a new scan begins, the new scan fails.</p> <div style="border: 1px solid green; padding: 5px;"><p><b>Tip:</b> Configure the password change interval in Arcon so that password changes do not disrupt your Tenable Security Center scans. If Arcon changes a password during a scan, the scan fails.</p></div>
<b>Use SSL</b>	When enabled, Tenable Security Center uses SSL through IIS for secure communications. You must configure SSL through IIS in Arcon before enabling this option.
<b>Verify SSL Certificate</b>	When enabled, Tenable Security Center validates the SSL certificate. You must configure SSL through IIS in Arcon before enabling this option.

## Centrify Options

The following table describes the additional options to configure when using **Centrify** as the authentication method for Windows credentials.

Option	Description
--------	-------------





<b>Centrify Host</b>	<p>(Required) The Centrify IP address or DNS address.</p> <div style="border: 1px solid blue; padding: 5px;"><p><b>Note:</b> If your Centrify installation is in a subdirectory, you must include the subdirectory path. For example, type <i>IP address or hostname/subdirectory path</i>.</p></div>
<b>Centrify Port</b>	<p>(Required) The port on which Centrify listens. By default, Tenable Security Center uses port 443.</p>
<b>API User</b>	<p>(Required) The API user provided by Centrify.</p>
<b>API Key</b>	<p>(Required) The API key provided by Centrify.</p>
<b>Tenant</b>	<p>(Required) The Centrify tenant associated with the API. By default, Tenable Security Center uses <i>centrify</i>.</p>
<b>Authentication URL</b>	<p>(Required) The URL Tenable Security Center uses to access Centrify. By default, Tenable Security Center uses <i>/Security</i>.</p>
<b>Password Query URL</b>	<p>(Required) The URL Tenable Security Center uses to query the passwords in Centrify. By default, Tenable Security Center uses <i>/RedRock</i>.</p>
<b>Password Engine URL</b>	<p>(Required) The URL Tenable Security Center uses to access the passwords in Centrify. By default, Tenable Security Center uses <i>/ServerManage</i>.</p>
<b>Username</b>	<p>(Required) The username to log in to the hosts you want to scan.</p>
<b>Checkout Duration</b>	<p>(Required) The length of time, in minutes, that you want to keep credentials checked out in Centrify.</p> <p>Configure the <b>Checkout Duration</b> to exceed the typical duration of your Tenable Security Center scans so that password changes do not disrupt your Tenable Security Center scans. If Centrify changes a password during a scan, the scan fails. If a password from a previous scan is still checked out when a new scan begins, the new scan fails.</p>



<b>Use SSL</b>	When enabled, Tenable Security Center uses SSL through IIS for secure communications. You must configure SSL through IIS in Centrify before enabling this option.
<b>Verify SSL Certificate</b>	When enabled, Tenable Security Center validates the SSL certificate. You must configure SSL through IIS in Centrify before enabling this option.

## CyberArk Vault (Legacy) Options


The following table describes the options to configure when using **CyberArk Vault (Legacy)** as the authentication method for Windows credentials.

Option	Description
<b>Username</b>	The username for the target system.
<b>Domain</b>	The domain, if the username is part of a domain.
<b>Central Credential Provider URL Host</b>	The CyberArk Central Credential Provider IP/ DNS address.
<b>Central Credential Provider URL Port</b>	The port the CyberArk Central Credential Provider is listening on.
<b>Vault Username</b>	The username for the vault, if the CyberArk Central Credential Provider is configured for basic authentication.
<b>Vault Password</b>	The password for the vault, if the CyberArk Central Credential Provider is configured for basic authentication.
<b>Safe</b>	The safe on the CyberArk Central Credential Provider server that contains the credentials you want to retrieve.
<b>CyberArk Client Certificate</b>	The file that contains the PEM certificate used to communicate with the CyberArk host.
<b>CyberArk Client</b>	The file that contains the PEM private key for the client certificate.



Option	Description
<b>Certificate Private Key</b>	
<b>CyberArk Client Certificate Private Key Passphrase</b>	The passphrase for the private key, if required.
<b>AppID</b>	The AppID with CyberArk Central Credential Provider permissions to retrieve the target password.
<b>Folder</b>	The folder on the CyberArk Central Credential Provider server that contains the credentials you want to retrieve.
<b>PolicyID</b>	The PolicyID assigned to the credentials you want to retrieve.
<b>Vault Use SSL</b>	When enabled, Tenable Security Center uses SSL through IIS for secure communications. You must configure SSL through IIS in CyberArk Central Credential Provider before enabling this option.
<b>Vault Verify SSL</b>	<p>When enabled, Tenable Security Center validates the SSL certificate. You must configure SSL through IIS in CyberArk Central Credential Provider before enabling this option.</p> <p>For more information about using self-signed certificates, see <a href="#">Custom Plugin Packages for NASL and CA Certificate Upload</a>.</p>
<b>CyberArk Escalation Account Details Name</b>	The unique name of the credential you want to retrieve from CyberArk.



Option	Description
	
<b>CyberArk AIM Service URL</b>	The URL for the CyberArk AIM web service. By default, Tenable Security Center uses <code>/AIMWebservice/v1.1/AIM.asmx</code> .

## CyberArk Vault Options

The following table describes the additional options to configure when using **CyberArk Vault** as the authentication method for Windows credentials.

Option	Description	Required
CyberArk Host	The IP address or FQDN name for the CyberArk AIM Web Service. This can be the host, or the host with a custom URL added on in a single string.	yes
Port	The port on which the CyberArk API communicates. By default, Tenable uses 443.	yes
Appld	The Application ID associated with the CyberArk API connection.	yes
Client Certificate	The file that contains the PEM certificate used to communicate with the CyberArk host.	no
Client Certificate Private Key	The file that contains the PEM private key for the client certificate.	yes, if private key is applied



Option	Description	Required
Client Certificate Private Key Passphrase	The passphrase for the private key, if required.	yes, if private key is applied
Get credential by	<p>The method with which your CyberArk API credentials are retrieved. Can be <b>Username</b>, <b>Identifier</b>, or <b>Address</b>.</p> <p><b>Note:</b> The frequency of queries for <b>Username</b> is one query per target. The frequency of queries for <b>Identifier</b> is one query per chunk. This feature requires all targets have the same identifier.</p> <p><b>Note:</b> The <b>Username</b> option also adds the <b>Address</b> parameter of the API query and assigns the target IP of the resolved host to the <b>Address</b> parameter. This may lead to failure to fetch credentials if the CyberArk Account Details <b>Address</b> field contains a value other than the target IP address.</p>	yes
Username	(If <b>Get credential by</b> is <b>Username</b> ) The username of the CyberArk user to request a password from.	no
Safe	The CyberArk safe the credential should be retrieved from.	no
Address	The option should only be used if the Address value is unique to a single CyberArk account credential.	no
Account Name	(If <b>Get credential by</b> is <b>Identifier</b> ) The unique account name or identifier assigned to the CyberArk API credential.	no
Use SSL	If enabled, the scanner uses SSL through IIS for secure communications. Enable this option if CyberArk is configured to support SSL through IIS.	no
Verify SSL Certificate	If enabled, the scanner validates the SSL certificate. Enable this option if CyberArk is con-	no



Option	Description	Required
	figured to support SSL through IIS and you want to validate the certificate.	

## Hashicorp Vault Options

The following table describes the additional options to configure when using **Hashicorp Vault** as the authentication method for Windows credentials.

Option	Default Value	Required
<b>Hashicorp Host</b>	The Hashicorp Vault IP address or DNS address. <div style="border: 1px solid blue; padding: 5px;"><b>Note:</b> If your Hashicorp Vault installation is in a sub-directory, you must include the subdirectory path. For example, type <i>IP address or hostname/ sub-directory path</i>.</div>	yes
<b>Hashicorp Port</b>	The port on which Hashicorp Vault listens.	yes
<b>Authenticaton Type</b>	Specifies the authentication type for connecting to the instance: <b>App Role</b> or <b>Certificates</b> .  If you select <b>Certificates</b> , additional options for <b>Hashicorp Client Certificate</b> (Required) and <b>Hashicorp Client Certificate Private Key</b> (Required) appear. Select the appropriate files for the client certificate and private key.	yes
<b>Role ID</b>	The GUID provided by Hashicorp Vault when you configured your App Role.	yes
<b>Role Secret ID</b>	The GUID generated by Hashicorp Vault when you configured your App Role.	yes
<b>Authentication URL</b>	The path/subdirectory to the authentication endpoint. This is not the full URL. For example:  <code>/v1/auth/approle/login</code>	yes



<b>Namespace</b>	The name of a specified team in a multi-team environment.	no
<b>Hashicorp Vault Type</b>	The type of Hashicorp Vault secrets engine: <ul style="list-style-type: none"><li>• <b>KV1</b>—Key/Value Secrets Engine Version 1</li><li>• <b>KV2</b> —Key/Value Secrets Engine Version 2</li><li>• <b>AD</b>—Active Directory</li></ul>	yes
<b>KV Engine URL</b>	The URL Tenable Security Center uses to access the Hashicorp Vault secrets engine.  Example: /v1/path_to_secret. No trailing /	yes
<b>Username Source</b>	(Only displays if <b>Hashicorp Vault Type</b> is <b>KV1</b> or <b>KV2</b> ) Specifies if the username is input manually or pulled from Hashicorp Vault.	yes
<b>Username key</b>	(Only displays if <b>Hashicorp Vault Type</b> is <b>KV1</b> or <b>KV2</b> ) The name in Hashicorp Vault that usernames are stored under.	yes
<b>Password key</b>	(Only displays if <b>Hashicorp Vault Type</b> is <b>KV1</b> or <b>KV2</b> ) The key in Hashicorp Vault that passwords are stored under.	yes
<b>Secret Name</b>	The key secret you want to retrieve values for.	yes
<b>Use SSL</b>	When enabled, Tenable Security Center uses SSL for secure communications. You must configure SSL in Hashicorp Vault before enabling this option.	no
<b>Verify SSL</b>	When enabled, Tenable Security Center validates the SSL certificate. You must configure SSL in Hashicorp Vault before enabling this option.	no

## Kerberos Options



The following table describes the options to configure when using **Kerberos** as the authentication method for Windows credentials.

Option	Description
<b>Username</b>	The username for a user on the target system.
<b>Password</b>	The password associated with the username you provided.
<b>Domain</b>	The authentication domain, typically the domain name of the target (e.g., <i>example.com</i> ).
<b>KDC Host</b>	The host supplying the session tickets.
<b>KDC Port</b>	The port you want to use for the KDC connection. By default, Tenable Security Center uses port 88.
<b>KDC Transport</b>	The method you want to use to connect to the KDC server. <div style="border: 1px solid blue; padding: 5px; margin-top: 10px;"><b>Note:</b> If you select UDP, you may need to edit the <b>KDC Port</b>. The KDC UDP protocol uses either port 88 or port 750.</div>

## LM Hash Options

The following table describes the options to configure when using **LM Hash** as the authentication method for Windows credentials.

Option	Description
<b>Username</b>	The username for a user on the target system.
<b>Hash</b>	The LM hash you want to use.
<b>Domain</b>	The domain of the username, if required.

## NTLM Hash Options

The following table describes the options to configure when using **NTLM Hash** as the authentication method for Windows credentials.





Option	Description
Username	The username for a user on the target system.
Hash	The NTLM hash you want to use.
Domain	The domain of the username, if required.

## Password Options

The following table describes the options to configure when using **Password** as the authentication method for Windows credentials.

Option	Description
Username	The username for a user on the target system.
Password	The password associated with the username you provided.
Domain	The domain of the username, if required.

## Thycotic Secret Server Options

The following table describes the options to configure when using **Thycotic Secret Server** as the authentication method for Windows credentials.

Option	Description
Username	(Required) The username for a user on the target system.
Domain	The domain of the username, if set on the Thycotic server.
Thycotic Secret Name	The Secret Name value on the Thycotic server.
Thycotic Secret Server URL	(Required) The value you want Tenable Security Center to use when setting the transfer method, target, and target directory for the scanner. Find the value on the Thycotic server, in <b>Admin &gt; Configuration &gt; Application Settings &gt; Secret Server URL</b> .  For example, if you type <i>https://pw.mydomain.com/SecretServer</i> , Tenable



Option	Description
	Security Center determines it is an SSL connection, that <i>pw.mydomain.com</i> is the target address, and that <i>/SecretServer</i> is the root directory.
<b>Thycotic Login Name</b>	(Required) The username for a user on the Thycotic server.
<b>Thycotic Password</b>	(Required) The password associated with the <b>Thycotic Login Name</b> you provided.
<b>Thycotic Organization</b>	In cloud instances of Thycotic, the value that identifies which organization the Tenable Security Center query should target.
<b>Thycotic Domain</b>	The domain, if set for the Thycotic server.
<b>Use Private Key</b>	If enabled, Tenable Security Center uses key-based authentication for SSH connections instead of password authentication.
<b>Verify SSL Certificate</b>	If enabled, Tenable Security Center verifies the SSL Certificate on the Thycotic server.  For more information about using self-signed certificates, see <a href="#">Custom Plugin Packages for NASL and CA Certificate Upload</a> .

## BeyondTrust Options

The following table describes the options to configure when using **BeyondTrust** as the authentication method for Windows credentials.

Option	Description
<b>Username</b>	The username to log in to the hosts you want to scan.
<b>Domain</b>	The domain of the username, if required by BeyondTrust.
<b>BeyondTrust Host</b>	The BeyondTrust IP address or DNS address.
<b>BeyondTrust Port</b>	The port BeyondTrust is listening on.
<b>BeyondTrust</b>	The API user provided by BeyondTrust.



Option	Description
API User	
BeyondTrust API Key	The API key provided by BeyondTrust.
Checkout Duration	<p>The length of time, in minutes, that you want to keep credentials checked out in BeyondTrust. Configure the <b>Checkout duration</b> to exceed the typical duration of your Tenable Security Center scans. If a password from a previous scan is still checked out when a new scan begins, the new scan fails.</p> <div style="border: 1px solid green; padding: 5px;"><p><b>Tip:</b> Configure the password change interval in BeyondTrust so that password changes do not disrupt your Tenable Security Center scans. If BeyondTrust changes a password during a scan, the scan fails.</p></div>
Use SSL	If enabled, Tenable Security Center uses SSL through IIS for secure communications. You must configure SSL through IIS in BeyondTrust before enabling this option.
Verify SSL Certificate	If enabled, Tenable Security Center validates the SSL certificate. You must configure SSL through IIS in BeyondTrust before enabling this option.

## Lieberman Options

The following table describes the additional options to configure when using **Lieberman** as the authentication method for Windows credentials.

Option	Description
Username	The username for a user on the database.
Domain	The domain of the username, if required by Lieberman.
Lieberman Host	<p>The Lieberman IP address or DNS address.</p> <div style="border: 1px solid blue; padding: 5px;"><p><b>Note:</b> If your Lieberman installation is in a subdirectory, you must include the subdirectory path. For example, type <i>IP address or hostname/sub-</i></p></div>



Option	Description
	<code>directory path.</code>
<b>Lieberman Port</b>	The port Lieberman is listening on.
<b>Lieberman User</b>	The username for the Lieberman explicit user you want Tenable Security Center to use for authentication to the Lieberman Rapid Enterprise Defense (RED) API.
<b>Lieberman Password</b>	The password for the Lieberman explicit user.
<b>Use SSL</b>	When enabled, Tenable Security Center uses SSL through IIS for secure communications. You must configure SSL through IIS in Lieberman before enabling this option.
<b>Verify SSL Certificate</b>	When enabled, Tenable Security Center validates the SSL certificate. You must configure SSL through IIS in Lieberman before enabling this option.  For more information about using self-signed certificates, see <a href="#">Custom Plugin Packages for NASL and CA Certificate Upload</a> .
<b>System Name</b>	The name for the database credentials in Lieberman.

## WALLIX Bastion Options

The following table describes the additional options to configure when using **WALLIX Bastion** as the authentication method for Windows credentials.

Option	Description	Required
WALLIX Host	The IP address for the WALLIX Bastion host.	yes
WALLIX Port	The port on which the WALLIX Bastion API communicates. By default, Tenable uses 443.	yes
Authentication Type	<b>Basic</b> authentication (with WALLIX Bastion user interface username and Password require-	no



Option	Description	Required
	ments) or <b>API Key</b> authentication (with user-name and WALLIX Bastion-generated API key requirements).	
WALLIX User	Your WALLIX Bastion user interface login user-name.	yes
WALLIX Password	Your WALLIX Bastion user interface login password. Used for <b>Basic</b> authentication to the API.	yes
WALLIX API Key	The API key generated in the WALLIX Bastion user interface. Used for <b>API Key</b> authentication to the API.	yes
Get Credential by Device Account Name	<p>The account name associated with a <b>Device</b> you want to log in to the target systems with.</p> <div data-bbox="516 1003 1166 1234" style="border: 1px solid blue; padding: 5px;"><p><b>Note:</b> If your device has more than one account you must enter the specific device name for the account you want to retrieve credentials for. Failure to do this may result in credentials for the wrong account returned by the system.</p></div>	Required only if you have a target and/or device with multiple accounts.
HTTPS	<p>This is enabled by default.</p> <div data-bbox="516 1339 1166 1453" style="border: 1px solid red; padding: 5px;"><p><b>Caution:</b> The integration fails if you disable <b>HTTPS</b>.</p></div>	yes
Verify SSL Certificate	This is disabled by default and is not supported in WALLIX Bastion PAM integrations.	no



## Audit Files

The Tenable Nessus vulnerability scanner allows you to perform compliance audits of numerous platforms including (but not limited to) databases, Cisco, Unix, and Windows configurations as well as sensitive data discovery based on regex contained in audit files. Audit files are XML-based text files that contain the specific configuration, file permission, and access control tests to be performed. For more information, see [Manage Audit Files](#).

After you create an audit file, you can reference the audit file in a template-based Policy Compliance Auditing scan policy or a custom scan policy. For more information about compliance options in custom scan policies, see [Compliance Options](#).

For more information on compliance checks and creating custom audits, see the [Compliance Checks Reference](#).

## Template-Based Audit Files

You can add template-based audit files using templates embedded within Tenable Security Center. Tenable updates these templates regularly through the Tenable Security Center feed.

For more information, see [Add a Template-Based Audit File](#).

## Custom Audit Files

You can add custom audit files to upload any of the following:

- a Tenable-created audit file downloaded from the [Tenable downloads](#) page.
- a Security Content Automation Protocol (SCAP) Data Stream file downloaded from a SCAP repository (e.g., <https://nvd.nist.gov/ncp/repository>).

The file must contain full SCAP content (Open Vulnerability and Assessment Language (OVAL) and Extensible Configuration Checklist Description Format (XCCDF) content) or OVAL standalone content.

**Note:** XCCDF standalone content audit files lack automated checks and do not return scan results in Tenable Security Center.

- a custom audit file created or customized for a specific environment. For more information, see the [knowledge base](#) article.



For more information, see [Add a Custom Audit File](#).



## Add a Template-Based Audit File

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

You can add template-based audit files using templates embedded within Tenable Security Center. Tenable updates these templates regularly through the Tenable Security Center feed.

For more information, see [Audit Files](#).

To add a template-based audit file:

1. Log in to Tenable Security Center via the user interface.
2. Click **Scanning > Audit Files** (administrator users) or **Scans > Audit Files** (organizational users).

The **Audit Files** page appears.

3. Click **Add**

The **Audit File Templates** page appears.

4. In the **Common** section, click a template category tile.

The **Add Audit Template** page appears.

5. In the **Name** box, type a name for the audit file.
6. (Optional) In the **Description** box, type a description for the audit file.
7. (Optional) Edit the template-specific options if you do not want to use the default values.
8. Click **Submit**.

Tenable Security Center saves your configuration.

What to do next:

- Reference the audit file in a template-based Policy Compliance Auditing scan policy or a custom scan policy. For more information about compliance options in custom scan policies, see [Compliance Options](#).





## Add a Custom Audit File

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

You can add custom audit files to upload any of the following:

- a Tenable-created audit file downloaded from the [Tenable downloads](#) page.
- a Security Content Automation Protocol (SCAP) Data Stream file downloaded from a SCAP repository (e.g., <https://nvd.nist.gov/ncp/repository>).

The file must contain full SCAP content (Open Vulnerability and Assessment Language (OVAL) and Extensible Configuration Checklist Description Format (XCCDF) content) or OVAL standalone content.

**Note:** XCCDF standalone content audit files lack automated checks and do not return scan results in Tenable Security Center.

- a custom audit file created or customized for a specific environment. For more information, see the [knowledge base](#) article.

For more information, see [Audit Files](#).

Before you begin:

- Download or prepare the file you intend to upload.

To add a custom audit file or SCAP Data Stream file:

1. Log in to Tenable Security Center via the user interface.
2. Click **Scanning** > **Audit Files** (administrator users) or **Scans** > **Audit Files** (organizational users).

The **Audit Files** page appears.

3. Click **Add**

The **Audit File Templates** page appears.

4. In the **Other** section, click the **Advanced** tile.
5. In the **Name** box, type a descriptive name for the audit file.



6. In the **Description** box, type a description for the audit file.
7. Click **Choose File** and browse to the **Audit File** you want to upload.

The system uploads the file. If you uploaded a SCAP Data Stream file, additional options appear.

8. If you uploaded a Data Stream file with full SCAP content, continue configuring options for the file:
  - a. If you uploaded SCAP 1.2 content or later, in the **Data Stream Name** box, select the Data Stream identifier found in the SCAP 1.2 Data Stream content.
  - b. In the **Benchmark Type** box, select the operating system that the SCAP content targets.
  - c. In the **Benchmark Name** box, select the benchmark identifier found in the SCAP XCCDF component.
  - d. In the **Profile** box, select the benchmark profile identifier found in the SCAP XCCDF component.
9. Click **Submit**.

Tenable Security Center saves your configuration.

What to do next:

- Reference the audit file in a template-based Policy Compliance Auditing scan policy or a custom scan policy. For more information about compliance options in custom scan policies, see [Compliance Options](#).



## Manage Audit Files

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information, see [Audit Files](#).

To manage your audit files:

1. Log in to Tenable Security Center via the user interface.
2. Click **Scans > Audit Files**.

The **Audit Files** page appears.

3. To filter the audit files that appear on the page, apply a filter as described in [Apply a Filter](#).
4. To add an audit file, see [Add a Template-Based Audit File](#) or [Add a Custom Audit File](#).

5. To view details for an audit file:

- a. Right-click the row for the audit file.

The actions menu appears.

-or-

Select the check box for the audit file.

The available actions appear at the top of the table.

- b. Click **View**.

The **View Audit File** page appears.

6. To edit or replace an audit file:

- a. Right-click the row for the audit file.

The actions menu appears.

-or-

Select the check box for the audit file.



The available actions appear at the top of the table.

- b. Click **Edit**.

The **Edit Audit File** page appears.

- c. To edit the name or description, type a new **Name** or **Description**.
- d. To replace the audit file, click the delete button (✖) next to the file and upload a new audit file.
- e. Click **Submit**.

Tenable Security Center saves your configuration.

## 7. To share or revoke access to an audit file:

- a. Right-click the row for the audit file.

The actions menu appears.

-or-

Select the check box for the audit file.

The available actions appear at the top of the table.

- b. Click **Share**.
- c. Share or revoke access for each group in your organization.
- d. Click **Submit**.

Tenable Security Center saves your configuration.

## 8. To export an audit file:

- a. Right-click the row for the audit file.

The actions menu appears.

-or-

Select the check box for the audit file.

The available actions appear at the top of the table.



- b. Click **Export**.

Tenable Security Center exports the audit file.

9. To delete an audit file:

- a. Right-click the row for the audit file.

The actions menu appears.

-or-

Select the check box for the audit file.

The available actions appear at the top of the table.

- b. Click **Delete**.

A confirmation window appears.

- c. Click **Delete**.

Tenable Security Center deletes the audit file.



## Scan Zones

*Scan zones* are areas of your network that you want to target in an active scan, associating an IP address or range of IP addresses with one or more scanners in your deployment. You must create scan zones in order to run active scans in Tenable Security Center.

For more information, see [Add a Scan Zone](#), [View Your Scan Zones](#), [Edit a Scan Zone](#), and [Delete a Scan Zone](#).

Option	Description
<b>Name</b>	A name for the scan zone.
<b>Description</b>	(Optional) A description for the scan zone.
<b>Ranges</b>	One or more IP addresses that you want the scan zone to target. Supported formats: <ul style="list-style-type: none"><li>• a comma-separated list of IP addresses and/or CIDR addresses.</li><li>• a newline-separated list of IP addresses and/or CIDR addresses.</li><li>• a hyphenated range of IP addresses (e.g., 192.0.2.0-192.0.2.25).</li></ul>
<b>Scanners</b>	One or more scanners that you want to use to scan the <b>Ranges</b> in this scan zone. <div style="border: 1px solid blue; padding: 5px; margin-top: 10px;"><b>Note:</b> Do not choose scanners that cannot reach the areas of your network identified in the <b>Ranges</b>. Similarly, consider the quality of the network connection between the scanners you choose and the <b>Ranges</b>.</div>

## Best Practices

Tenable recommends pre-planning your scan zone strategy to efficiently target discrete areas of your network. If configured improperly, scan zones prevent scanners from reaching their targets. Consider the following best practices:

- It is simplest to configure and manage a small number of scan zones with large ranges.
- It is simplest to target ranges (versus large lists of individual IP addresses).



- If you use Nessus Manager for agent management, do not target Nessus Manager in any scan zone ranges.


## Overlapping Scan Zones

In some cases, you may want to configure overlapping scan zones to ensure scanning coverage or redundancy.

**Note:** Do not configure overlapping scan zones without pre-planning your scan zone and **Distribution Method** strategy.

Two or more scan zones are redundant if they target the same area of your network. If Tenable Security Center executes a scan with redundant scan zones, it first attempts the scan using the narrowest, most specific scan zone.

In this example, the red numbers represent specific IP addresses on your network. The grey circles represent the network coverage of individual scan zones.



See the following table to understand the primary and redundant scan zones for the IP addresses in this example.



IP Address	Primary Scan Zone	Redundant Scan Zones
1	Scan Zone A	None.
2	Scan Zone B	Scan Zone A.
3	Scan Zone C	Scan Zone B, then Scan Zone A.
4	Scan Zone C	Scan Zone A.
5	Scan Zone D	Scan Zone A.
6	Scan Zone E	Scan Zone A.
7	Scan Zone F	Scan Zone E, then Scan Zone A.





## Add a Scan Zone

**Required User Role:** Administrator

For more information about scan zone options, see [Scan Zones](#).

To add a scan zone:

1. Log in to Tenable Security Center via the user interface.
2. Click **Resources > Scan Zones**.  
The **Scan Zones** page appears.
3. At the top of the table, click **Add**.  
The **Add Scan Zone** page appears.
4. In the **Name** box, type a name for the scan zone.
5. In the **Description** box, type a description for the scan zone.
6. In the **Ranges** box, type one or more IP addresses, CIDR addresses, or ranges to target with the scan zone.
7. In the **Scanners** box, choose one or more scanners to associate with the scan zone.
8. Click **Submit**.

Tenable Security Center saves your configuration.

What to do next:

- Configure scan zone-related organization settings, as described in [Organizations](#).
- Configure an active scan that targets your scan zone, as described in [Add an Active Scan](#).



## View Your Scan Zones

**Required User Role:** Administrator

For more information, see [Scan Zones](#).

To view a list of configured scan zones:

1. Log in to Tenable Security Center via the user interface.
2. Click **Resources > Scan Zones**.

The **Scan Zones** page appears.

3. View details about each scan zone.
  - **Name** —The name of the scan zone.
  - **Status** —The status of the scan zone.

Scan Zone Status	Description
All Scanners Available	All of the scanners in the scan zone are <b>Working</b> .
<i>x</i> / <i>y</i> Scanners Available	Only some of the scanners in the scan zone are <b>Working</b> .
No Scanners Available	None of the scanners in the scan zone are <b>Working</b> .

For information about **Working** and other scanner statuses, see [Tenable Nessus Scanner Statuses](#).

- **Scanners** —The number of Tenable Nessus scanners in the scan zone.
- **Last Modified** —The date and time the scan zone was last modified.



## Edit a Scan Zone

**Required User Role:** Administrator

For more information about scan zone options, see [Scan Zones](#).

To edit a scan zone:

1. Log in to Tenable Security Center via the user interface.
2. Click **Resources > Scan Zones**.

The **Scan Zones** page appears.

3. Right-click the row for the scan zone you want to edit.

The actions menu appears.

-or-

Select the check box for the scan zone you want to edit.

The available actions appear at the top of the table.

4. Click **Edit**.

The **Edit Scan Zone** page appears.

5. Modify the following scan zone options. For more information, see [Scan Zones](#).

- **Name**
- **Description**
- **Ranges**
- **Scanners**

6. Click **Submit**.

Tenable Security Center saves your configuration.



## Delete a Scan Zone

**Required User Role:** Administrator

For more information, see [Scan Zones](#).

Before you begin:

- Confirm that no scans target the scan zone you want to delete. Tenable Security Center scans may fail if you delete an actively targeted scan zone.

To delete a scan zone:

1. Log in to Tenable Security Center via the user interface.
2. Click **Resources > Scan Zones**.

The **Scan Zones** page appears.

3. Select the scan zone you want to delete:

To delete a single scan zone:

- a. In the table, right-click the row for the scan zone you want to delete.

The actions menu appears.

- b. Click **Delete**.

To delete multiple scan zones:

- a. In the table, select the check box for each scan zone you want to delete.

The available actions appear at the top of the table.

- b. At the top of the table, click **Delete**.

A confirmation window appears.

4. Click **Delete**.

Tenable Security Center deletes the scan zone.



---

## Scan Policies

---

*Scan policies* contain plugin settings and advanced directives for active scans.

When an administrator user creates a scan policy, the policy is available to all organizations. When an organizational user creates a scan policy, the scan policy is available only to their organization. Users with the appropriate permissions can use scan policies in an active scan, modify policy options, and more. For more information about user permissions, see [User Roles](#).

For more information, see:

- [Add a Scan Policy](#)
- [Scan Policy Templates](#)
- [Scan Policy Options](#)
- [View Your Scan Policies](#)
- [View Scan Policy Details](#)
- [Edit a Scan Policy](#)
- [Share or Revoke Access to a Scan Policy](#)
- [Export a Scan Policy](#)
- [Import a Scan Policy](#)
- [Copy a Scan Policy](#)
- [Delete a Scan Policy](#)



## Add a Scan Policy

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

You can create template-based or custom scan policies for your active scans. When you create a custom scan policy, you can configure any scan policy option. When you configure a template-based scan policy, you can configure the options included for the template type.

For more information, see [Scan Policies](#) and [Active Scans](#).

To add a template-based scan policy:

1. Log in to Tenable Security Center via the user interface.
2. Click **Scanning > Policies** (administrator users) or **Scans > Policies** (organizational users).

The **Policies** page appears.

3. At the top of the table, click **Add**.

The **Add Policy** page appears.

4. In the **Template** section, click a policy template. For more information, see [Scan Policy Templates](#).

The policy template page appears.

5. Configure the options described in [Scan Policy Options](#).

6. Click **Submit**.

Tenable Security Center saves your configuration.

To add a custom scan policy:

1. Log in to Tenable Security Center via the user interface.
2. Click **Scanning > Policies** (administrator users) or **Scans > Policies** (organizational users).

The **Policies** page appears.

3. At the top of the table, click **Add**.



The **Add Policy** page appears.

4. In the **Custom** section, click **Advanced Scan**.

The **Advanced Scan** page appears.

5. Configure the options described in [Scan Policy Options](#).
6. Click **Submit**.

Tenable Security Center saves your configuration.

What to do next:

- Reference the scan policy in an active scan configuration, as described in [Add an Active Scan](#).



## Scan Policy Templates

Tenable Security Center provides scan policy templates with pre-configured plugin settings and advanced directives for active scans. You can configure a Tenable-provided template or you can create a fully customized scan policy from all of the available scan policy options in Tenable Security Center.

Each Tenable-provided scan policy template contains a different set of scan policy options. You can only modify the settings included for that scan policy template type.

Custom scan policies, such as Advanced Scan, contain all scan policy options. You can modify any scan policy options for custom scans.

For more information, see [Scan Policies](#) and [Scan Policy Options](#).

Template	Description
Common	
Advanced Agent Scan	<p>The most configurable scan type. You can configure this scan template to match any policy. This template has the same default settings as the basic scan template, but it allows for additional configuration options.</p> <div style="border: 1px solid #0070C0; padding: 5px;"><p><b>Note:</b> Advanced scan templates allow you to scan more deeply using custom configuration, such as faster or slower checks, but misconfigurations can cause asset outages or network saturation. Use the advanced templates with caution.</p></div>
Advanced Scan	<p>The most configurable scan type. You can configure this scan template to match any policy. This template has the same default settings as the basic scan template, but it allows for additional configuration options.</p>
Basic Network Scan	<p>Performs a full system scan that is suitable for any host. Use this template to scan an asset or assets with all of Nessus's plugins enabled. For example, you can perform an internal vulnerability scan on your organization's systems.</p>
Credentialed Patch Audit	<p>Authenticates hosts and enumerates missing updates.</p> <p>Use this template with credentials to give Tenable Security Center direct</p>





	access to the host, scan the target hosts, and enumerate missing patch updates.
Web Application Tests	Scan for published and unknown web vulnerabilities.
<b>Compliance Configuration</b>	
Internal PCI Network Scan	<p>Performs an internal PCI DSS (11.2.1) vulnerability scan.</p> <p>This template creates scans that you can use to satisfy internal (PCI DSS 11.2.1) scanning requirements for ongoing vulnerability management programs that satisfy PCI compliance requirements. You can use these scans for ongoing vulnerability management and to perform rescans until passing or clean results are achieved. You can provide credentials to enumerate missing patches and client-side vulnerabilities.</p> <div style="border: 1px solid blue; padding: 5px;"><p><b>Note:</b> While the PCI DSS requires you to provide evidence of passing or "clean" scans on at least a quarterly basis, you must also perform scans after any significant changes to your network (PCI DSS 11.2.3).</p></div>
PCI Quarterly External Scan	<p>Performs quarterly external scans as required by PCI.</p> <p>You can use this template to simulate an external scan (PCI DSS 11.2.2) to meet PCI DSS quarterly scanning requirements. However, you cannot submit the scan results from this template to Tenable for PCI Validation. Only Tenable Vulnerability Management customers can submit their PCI scan results to Tenable for PCI ASV validation.</p>
Policy Compliance Auditing	<p>Audits system configurations against a known baseline.</p> <p>The compliance checks can audit against custom security policies, such as password complexity, system settings, or registry values on Windows operating systems. For Windows systems, the compliance audits can test for a large percentage of anything that can be described in a Windows policy file. For Unix systems, the compliance audits test for running processes, user security policy, and content of files.</p>
SCAP and OVAL Auditing	Audits systems using SCAP and OVAL definitions.



	<p>The National Institute of Standards and Technology (NIST) Security Content Automation Protocol (SCAP) is a set of policies for managing vulnerabilities and policy compliance in government agencies. It relies on multiple open standards and policies, including OVAL, CVE, CVSS, CPE, and FDCC policies.</p> <ul style="list-style-type: none"><li>• SCAP compliance auditing requires sending an executable to the remote host.</li><li>• Systems running security software (for example, McAfee Host Intrusion Prevention), may block or quarantine the executable required for auditing. For those systems, you must make an exception for either the host or the executable sent.</li><li>• When using the <b>SCAP and OVAL Auditing</b> template, you can perform Linux and Windows <b>SCAP CHECKS</b> to test compliance standards as specified in NIST's Special Publication 800-126.</li></ul>
<b>Other</b>	
2022 Threat Landscape Restrospective (TLR)	Detects vulnerabilities featured in Tenable's 2022 Threat Landscape Retrospective report.
Active Directory Starter Scan	<p>Scans for misconfigurations in Active Directory.</p> <div style="border: 1px solid blue; padding: 5px;"><p><b>Note:</b> Active Directory Starter Scans require ADSI credentials. For more information, see <a href="#">Miscellaneous</a>.</p></div> <p>Use this template to check Active Directory for Kerberoasting, Weak Kerberos encryption, Kerberos pre-authentication validation, non-expiring account passwords, unconstrained delegation, null sessions, Kerberos KRBTGT, dangerous trust relationships, Primary Group ID integrity, and blank passwords.</p>
CISA Alerts AA22-011A and AA22-047A	Performs remote and local checks for vulnerabilities from CISA alerts AA22-011A and AA22-047A.



ContiLeaks	Performs remote and local checks for ContiLeaks vulnerabilities.
GHOST (glibc) Detection	Performs local checks to detect vulnerabilities related to CVE-2015-0235.
Host Discovery	<p>Performs a simple scan to discover live hosts and open ports.</p> <p>Launch this scan to see what hosts are on your network and associated information such as IP address, FQDN, operating systems, and open ports, if available. After you have a list of hosts, you can choose what hosts you want to target in a specific vulnerability scan.</p> <p>Tenable recommends that organizations who do not have a passive network monitor, such as Nessus Network Monitor, run this scan weekly to discover new assets on your network.</p> <div style="border: 1px solid blue; padding: 5px;"><b>Note:</b> Assets identified by discovery scans do not count toward your license.</div>
Intel AMT Security Bypass Detection	Performs remote and local checks for CVE-2017-5689.
Log4Shell	Detects the Log4Shell vulnerability (CVE-2021-44228) in Apache Log4j via local checks.
Log4Shell Remote Checks	Detects the Log4Shell vulnerability (CVE-2021-44228) in Apache Log4j via remote checks.
Log4Shell Vulnerability Ecosystem	Detects the Log4Shell vulnerability (CVE-2021-44228) in Apache Log4j via local and remote checks. This template is dynamic and is regularly updated with new plugins as third-party vendors patch their software.
Malware Scan	<p>Scans for malware on Windows and Unix systems.</p> <p>Tenable Security Center detects malware using a combined allow list and block list approach to monitor known good processes, alert on known bad processes, and identify coverage gaps between the two by flagging unknown processes for further inspection.</p>
PrintNightmare	Performs local checks for CVE-2021-34527, the PrintNightmare Windows Print Spooler vulnerability.



ProxyLogon: MS Exchange	Performs remote and local checks to detect Microsoft Exchange Server vulnerabilities related to CVE-2021-26855, CVE-2021-26857, CVE-2021-26858, and CVE-2021-27065.
Ransomware Ecosystem	Performs local and remote checks for common ransomware vulnerabilities.
Solarigate	Detects SolarWinds Solorigate vulnerabilities using remote and local checks.
Spectre and Melt- down Detection	Performs remote and local checks for CVE-2017-5753, CVE-2017-5715, and CVE-2017-5754.
WannaCry Ransomware Detection	Scans for the WannaCry ransomware (MS17-010).
Zerologon Remote Scan	Detects Microsoft Netlogon elevation of privilege vulnerability (Zerologon).



# Scan Policy Options

Scan policy options specify granular configurations for your active scans.

When you create a custom scan policy, you can configure any scan policy option. When you configure a template-based scan policy, you can configure the options included for the template type.

For more information about Tenable-provided scan policy templates, see [Scan Policy Templates](#).

- [Setup Options](#)
- [Advanced Options](#)
- [Host Discovery Options](#)
- [Port Scanning Options](#)
- [Service Discovery Options](#)
- [Assessment Options](#)
- [Brute Force Options](#)
- [Malware Options](#)
- [SCADA Options](#)
- [Web Applications Options](#)
- [Windows Options](#)
- [Report Options](#)
- [Authentication Options](#)
- [Compliance Options](#)
- [Plugins Options](#)

## Setup Options

Option	Description
Name	A unique name for the policy.



Option	Description
Description	(Optional) A description for the policy.
Tag	A tag for the policy. For more information, see <a href="#">Tags</a> .

## Advanced Options

Option	Description
<b>General Settings</b>	
<b>Enable safe checks</b>	Tenable Nessus attempts to identify remote vulnerabilities by interpreting banner information and attempting to exercise a vulnerability. When <b>Enable safe checks</b> is enabled, the second step is skipped. This is not as reliable as a full probe, but is less likely to negatively impact a targeted system.
<b>Stop scanning hosts that become unresponsive during the scan</b>	During a scan, hosts may become unresponsive after a period of time. Enabling this setting stops scan attempts against hosts that stop sending results.
<b>Automatically accept detected SSH disclaimer prompts</b>	<p>When enabled, if a credentialed scan tries to connect via SSH to a FortiOS host that presents a disclaimer prompt, the scanner provides the necessary text input to accept the disclaimer prompt and continue the scan.</p> <p>The scan initially sends a bad ssh request to the target in order to retrieve the supported authorization methods. This allows you to determine how to connect to the target, which is helpful when you configure a custom ssh banner and then try to determine how to connect to the host.</p> <p>When disabled, credentialed scans on hosts that present a disclaimer prompt fail because the scanner cannot connect to the device and accept the disclaimer. The error appears in the plugin output.</p>
<b>Performance Options</b>	



Option	Description
<b>Slow down the scan when network congestion is detected</b>	When Tenable Nessus detects congestion during a scan, it will slow the speed of the scan in an attempt to ease the burden on the affected segment(s).
<b>Use Linux kernel congestion detection</b>	Use Linux kernel congestion detection during the scan to help alleviate system lockups on the Tenable Nessus scanner server.
<b>Network timeout (in seconds)</b>	Determines the amount of time, in seconds, to determine if there is an issue communicating over the network.
<b>Max simultaneous checks per host</b>	<p>This setting limits the maximum number of checks a Tenable Nessus scanner will perform against a single host at one time. The default value of this option is 5 simultaneous checks per host.</p> <p>Type an integer greater than 0. If you enter <b>0</b>, enter a negative integer, or delete the value in the field, Tenable Security Center does not perform any checks and scans will not complete.</p>
<b>Max simultaneous hosts per scan</b>	<p>This setting limits the maximum number of hosts that a single Tenable Nessus scanner will scan at the same time. The default value of this option is 30 hosts per scan.</p> <p>If the scan is using a zone with multiple scanners, each scanner will accept up to the amount specified in the <b>Max simultaneous hosts per scan</b> option. For example, if the <b>Max simultaneous hosts per scan</b> is set to 5 and there are 5 scanners per zone, each scanner will accept 5 hosts to scan, allowing a total of 25 hosts to be scanned between the 5 scanners.</p> <p>If you set <b>Max Simultaneous hosts per scan</b> to more than the Nessus scanner's <a href="#">max_hosts</a> value, the following message appears in the scanner's <code>nessusd.messages</code>: <i>Tried to raise the maximum hosts number - 150. Using 100. Change 'max_hosts' in the server configuration if you believe this is incorrect.</i> You can ignore this message; Tenable Security</p>



Option	Description
	Center send scans to the scanner into <a href="#">scan chunks</a> of up to eight IPs and will not reach the scanner's <b>max_hosts</b> , which must be nine or greater.
<b>Max number of concurrent TCP sessions per host</b>	<p>Specifies the maximum number of established TCP sessions for a single host.</p> <p>This TCP throttling option also controls the number of packets per second the SYN scanner sends, which is 10 times the number of TCP sessions. For example, if this option is set to 15, the SYN scanner sends 150 packets per second at most.</p> <p>Type an integer between 1-2000. If you leave the box empty or enter <b>0</b>, Tenable Security Center does not enforce a limit.</p>
<b>Max number of concurrent TCP sessions per scan</b>	<p>This setting limits the maximum number of TCP sessions established by any of the active scanners during a scan.</p> <p>Type an integer between 1-2000. If you leave the box empty or enter <b>0</b>, Tenable Security Center does not enforce a limit.</p>
<b>Unix find command Options</b>	
<b>Exclude Filepath</b>	<p>A plain text file containing a list of filepaths to exclude from all plugins that search using the <code>find</code> command on Unix systems.</p> <p>In the file, enter one filepath per line, formatted per patterns allowed by the Unix <code>find</code> command <code>-path</code> argument. For more information, see the <code>find</code> command <a href="#">man page</a>.</p>
<b>Exclude Filesystem</b>	<p>A plain text file containing a list of filesystems to exclude from all plugins that search using the <code>find</code> command on Unix systems.</p> <p>In the file, enter one filesystem per line, using filesystem types supported by the Unix <code>find</code> command <code>-fstype</code> argument. For more information, see the <code>find</code> command <a href="#">man page</a>.</p>
<b>Include Filepath</b>	<p>A plain text file containing a list of filepaths to include from all plugins that search using the <code>find</code> command on Unix systems.</p>





Option	Description
	<p>In the file, enter one filepath per line, formatted per patterns allowed by the Unix <code>find</code> command <code>-path</code> argument. For more information, see the <code>find</code> command <a href="#">man page</a>.</p> <p>Including filepaths increases the locations that are searched by plugins, which extends the duration of the scan. Make your inclusions as specific as possible.</p> <div data-bbox="472 583 1479 737" style="border: 1px solid green; padding: 5px;"><p><b>Tip:</b> Avoid having the same filepaths in <b>Include Filepath</b> and <b>Exclude Filepath</b>. This conflict may result in the filepath being excluded from the search, though results may vary by operating system.</p></div>
<b>Debug Settings</b>	
<b>Always Report SSH Commands</b>	<p>When enabled, Tenable Security Center generates a report of all the commands run over SSH on the host in a machine-readable format. You can view the reported commands under plugin 168017.</p> <div data-bbox="472 1010 1479 1087" style="border: 1px solid blue; padding: 5px;"><p><b>Note:</b> The setting does not function correctly if you disable plugin 168017.</p></div>
<b>Enumerate Launched Plugins</b>	<p>Shows a list of plugins that were launched during the scan. You can view the list in scan results under plugin 112154.</p>
<b>Stagger scan start</b>	
<b>Maximum delay (minutes)</b>	<p>(Agents 8.2 and later) If set, each agent in the agent group delays starting the scan for a random number of minutes, up to the specified maximum. Staggered starts can reduce the impact of agents that use a shared resource, such as virtual machine CPU.</p> <p>If the maximum delay you set exceeds your scan window, Tenable shortens your maximum delay to ensure that agents begin scanning at least 30 minutes before the scan window closes.</p>

## Host Discovery Options



Option	Description
<b>Ping the remote host</b>	When enabled, Tenable Nessus attempts to ping the hosts in the scan to determine if the host is alive or not.
<b>General Settings</b> (available when <b>Ping the remote host</b> is enabled)	
<b>Test the local Tenable Nessus host</b>	This option allows you to include or exclude the local Tenable Nessus host from the scan. This is used when the Tenable Nessus host falls within the target network range for the scan.
<b>Use fast network discovery</b>	When Tenable Nessus pings a remote IP address and receives a reply, it performs extra checks to make sure that it is not a transparent proxy or a load balancer that would return noise but no result (some devices answer to every port 1- 65535 even when there is no service behind the device). Such checks can take some time, especially if the remote host is firewalled. If <b>Use fast network discovery</b> is enabled, Tenable Nessus does not perform these checks.
<b>Ping Methods</b> (available when <b>Ping the remote host</b> is enabled)	
<b>ARP</b>	Ping a host using its hardware address via Address Resolution Protocol (ARP). This only works on a local network.
<b>TCP</b>	Ping a host using TCP.
<b>Destination ports</b>	Destination ports can be configured to use specific ports for TCP ping. This option specifies the list of ports that are checked via TCP ping. Type one of the following: <ul style="list-style-type: none"><li>• a single port</li><li>• a comma-separated list of ports</li><li>• built-in</li></ul> For more information about which ports built-in specifies, see the <a href="#">knowledge base</a> article.
<b>ICMP</b>	Ping a host using the Internet Control Message Protocol (ICMP).



Option	Description
<b>Assume ICMP unreachable means the host is down</b>	<p>When a ping is sent to a host that is down, its gateway may return an ICMP unreachable message. When enabled, this option considers this to mean the host is dead. This is to help speed up discovery on some networks.</p> <p>Some firewalls and packet filters use this same behavior for hosts that are up but are connecting to a port or protocol that is filtered. With this option enabled, this leads to the scan considering the host is down when it is indeed up.</p>
<b>Maximum number of retries</b>	<p>(If you enabled <b>ICMP</b>) Allows you to specify the number of attempts to try to ping the remote host. The default is two attempts.</p>
<b>UDP</b>	<p>Ping a host using the User Datagram Protocol (UDP).</p> <div data-bbox="418 829 1479 1024" style="border: 1px solid green; padding: 5px;"><p><b>Tip:</b> UDP is a stateless protocol, meaning that communication is not performed with handshake dialogues. UDP-based communication is not always reliable, and because of the nature of UDP services and screening devices, they are not always remotely detectable.</p></div>
<b>Fragile Devices</b>	
<b>Scan Network Printers</b>	<p>Instructs the Tenable Nessus scanner not to scan network printers if unselected. Since many printers are prone to denial of service conditions, Tenable Nessus can skip scanning them once identified. This is recommended if scanning is performed on production networks.</p>
<b>Scan Novell Network hosts</b>	<p>Instructs the Tenable Nessus scanner not to scan Novell Network hosts if unselected. Since many Novell Network hosts are prone to denial of service conditions, Tenable Nessus can skip scanning them once identified. This is recommended if scanning is performed on production networks.</p>
<b>Scan Operational Technology devices</b>	<p>When enabled, Tenable Security Center performs a full scan of Operational Technology (OT) devices such as programmable logic controllers (PLCs) and remote terminal units (RTUs) that monitor environmental factors and the activity and state of machinery.</p> <p>When disabled, Tenable Security Center uses ICS/ SCADA Smart Scanning to</p>



Option	Description
	identify OT devices cautiously and stops scanning them once they are discovered.
<b>Wake-on-LAN</b>	
<b>List of MAC addresses</b>	Wake on Lan (WOL) packets will be sent to the hosts listed, one on each line, in an attempt to wake the specified host(s) during a scan.
<b>Boot time wait (in minutes)</b>	The number of minutes Tenable Nessus will wait to attempt a scan of hosts sent a WOL packet.

## Port Scanning Options

Option	Description
<b>Ports</b>	
<b>Consider unscanned ports as closed</b>	If a port is not scanned with a selected port scanner (for example, out of the range specified), the scanner will consider it closed.
<b>Port scan range</b>	<p>Specifies a keyword (<b>default</b>) or a custom port range that you want the scanner to target.</p> <ul style="list-style-type: none"><li>• Type <b>default</b> to instruct the scanners to scan approximately 4,790 commonly used ports. The list of ports can be found in the <code>nessus-services</code> file.</li><li>• Type <b>all</b> to instruct the scanner to scan all 65,536 ports, including port 0.</li><li>• Type a custom port range to instruct the scanners to scan the custom range of ports. Type a custom port range as a comma-separated list of ports or port ranges. For example, <b>21,23,25,80,110</b> or <b>1-1024,8080,9000-9200</b>.</li></ul> <p>Tenable Security Center applies the custom range to the protocols you specify in the <b>Local Port Enumerators</b> section. If you want to</p>



Option	Description
	scan both TCP and UDP, you can specify a split range specific to each protocol. For example, if you want to scan a different range of ports for TCP and UDP in the same policy, type <b>T:1-1024,U:300-500</b> . You can also specify a set of ports to scan for both protocols, as well as individual ranges for each separate protocol. For example, <b>1-1024,T:1024-65535,U:1025</b> .
<b>Local Port Enumerators</b>	
<b>SSH (netstat)</b>	When enabled, the scanner uses netstat to check for open ports from the local machine. It relies on the netstat command being available via an SSH connection to the target. This scan is intended for Linux-based systems and requires authentication credentials.
<b>WMI (netstat)</b>	When enabled, the scanner uses netstat to determine open ports while performing a WMI-based scan.  In addition, the scanner: <ul style="list-style-type: none"><li>• Ignores any custom range specified in the <b>Port Scan Range</b> setting.</li><li>• Continues to treat unscanned ports as closed if the <b>Consider unscanned ports as closed</b> setting is enabled.</li></ul> If any port enumerator (netstat or SNMP) is successful, the port range becomes <i>all</i> .
<b>SNMP</b>	When enabled, if the appropriate credentials are provided by the user, the scanner can better test the remote host and produce more detailed audit results. For example, there are many Cisco router checks that determine the vulnerabilities present by examining the version of the returned SNMP string. This information is necessary for these audits.
<b>Only run network port scanners if local port enumeration</b>	If a local port enumerator runs, all network port scanners will be disabled for that asset.



Option	Description
failed	
<b>Verify open TCP ports found by local port enumerators</b>	When enabled, if a local port enumerator (for example, WMI or netstat) finds a port, the scanner also verifies that the port is open remotely. This approach helps determine if some form of access control is being used (for example, TCP wrappers or a firewall).
<b>Network Port Scanners</b>	
<b>TCP</b>	<p>Use the built-in Tenable Nessus TCP scanner to identify open TCP ports on the targets, using a full TCP three-way handshake. TCP scans are only possible if you are using Linux or FreeBSD. On Windows or macOS, the scanner does not do a TCP scan and instead uses the SYN scanner to avoid performance issues native to those operating systems. If you enable this option, you can also set the <b>Override Automatic Firewall Detection</b> option.</p> <div style="border: 1px solid blue; padding: 5px;"><p><b>Note:</b> On some platforms (for example, Windows and Mac OS X), if the operating system is causing serious performance issues using the TCP scanner, Tenable Nessus launches the SYN scanner instead.</p></div>
<b>SYN</b>	<p>Use the built-in Tenable Nessus SYN scanner to identify open TCP ports on the target hosts. SYN scans do not initiate a full TCP three-way handshake. The scanner sends a SYN packet to the port, waits for SYN-ACK reply, and determines the port state based on a response or lack of response.</p> <p>If you enable this option, you can also set the <b>Override Automatic Firewall Detection</b> option.</p>
<b>Override automatic firewall detection</b>	Rely on local port enumeration first before relying on network port scans.
<b>UDP</b>	<p>This option engages the built-in Tenable Nessus UDP scanner to identify open UDP ports on the targets.</p> <p>Due to the nature of the protocol, it is generally not possible for a port scanner to tell the difference between open and filtered UDP ports. Enabling the</p>



Option	Description
	UDP port scanner may dramatically increase the scan time and produce unreliable results. Consider using the netstat or SNMP port enumeration options instead if possible.

## Service Discovery Options

The **Service Discovery** tab specifies how the scanner looks for services running on the target's ports.

Option	Description
<b>Probe all ports to find services</b>	<p>When enabled, the scanner attempts to map each open port with the service that is running on that port, as defined by the <b>Port scan range</b> option.</p> <p><b>Caution:</b> In some rare cases, probing might disrupt some services and cause unforeseen side effects.</p>
<b>Search for SSL/TLS services</b>	<p>Controls how the scanner tests SSL-based services.</p> <p><b>Caution:</b> Testing for SSL capability on all ports may be disruptive for the tested host.</p>
<b>Search for SSL/TLS on</b>	<p>Specifies which ports on target hosts the scanner searches for SSL/TLS services.</p> <p>This setting has two options:</p> <ul style="list-style-type: none"><li>• <b>Known SSL/TLS ports</b></li><li>• <b>All ports</b></li></ul>
<b>Search for DTLS on</b>	<p>Specifies which ports on target hosts the scanner searches for DTLS services.</p> <p>This setting has the following options:</p> <ul style="list-style-type: none"><li>• <b>None</b></li><li>• <b>Known SSL/TLS ports</b></li></ul>



Option	Description
	<ul style="list-style-type: none"><li>• All TCP ports</li></ul>
Identify certificates expiring within x days	Identifies SSL certificates that age out within the specified timeframe. Type a value to set a timeframe (in days).
Enumerate all SSL/TLS ciphers	When Tenable Security Center performs an SSL scan, it tries to determine the SSL ciphers used by the remote server by attempting to establish a connection with each different documented SSL cipher, regardless of what the server says is available.
Enable CRL checking (connects to the Internet)	Direct Tenable Nessus to check SSL certificates against known Certificate Revocation Lists (CRL). Enabling this option makes a connection and query one or more servers on the internet.

## Assessment Options

The **Assessment** tab specifies how the scanner tests for information during the scan.

Value	Description
<b>Accuracy</b>	
Override normal accuracy	In some cases, Tenable Nessus cannot remotely determine whether a flaw is present or not. If report paranoia is set to <b>Paranoid</b> then a flaw is reported every time, even when there is a doubt about the remote host being affected. Conversely, a paranoia setting of <b>Avoid false alarms</b> will cause Tenable Nessus to not report any flaw whenever there is a hint of uncertainty about the remote host. <b>Normal</b> is a middle ground between these two settings.
Perform thorough tests (may disrupt your network or impact	Causes various plugins to use more aggressive settings. For example, when looking through SMB file shares, a plugin can analyze 3 directory levels deep instead of its default of 1. This could cause much more network traffic and analysis in some cases. Note that by being more thorough, the scan will be more intrusive and is more likely to disrupt the network, while potentially providing





Value	Description
scan speed)	better audit results.
<b>Antivirus</b>	
Antivirus definition grace period (in days)	This option determines the delay in the number of days of reporting the software as being outdated. The valid values are between 0 (no delay, default) and 7.
<b>SMTP</b>	
Third party domain	Tenable Nessus attempts to send spam through each SMTP device to the address listed in this option. This third party domain address must be outside the range of the site being scanned or the site performing the scan. Otherwise, the test may be aborted by the SMTP server.
From address	The test messages sent to the SMTP server(s) will appear as if they originated from the address specified in this option.
To Address	Tenable Nessus attempts to send messages addressed to the mail recipient listed in this option. The postmaster address is the default value since it is a valid address on most mail servers.

## Brute Force Options

The **Brute Force** tab specifies how the scanner tests for information against SCADA systems.

Additionally, if Hydra is installed on the same host as a Tenable Nessus server linked to Tenable Security Center, the Hydra section is enabled. Hydra extends brute force login testing for the following services: Asterisk, AFP, Cisco AAA, Cisco auth, Cisco enable, CVS, Firebird, FTP, HTTP-FORM-GET, HTTP-FORM-POST, HTTP-GET, HTTP-HEAD, HTTP-PROXY, HTTPS-FORM-GET, HTTPS-FORM-POST, HTTPS-GET, HTTPS-HEAD, HTTP-Proxy, ICQ, IMAP, IRC, LDAP, MS-SQL, MYSQL, NCP, NNTP, Oracle Listener, Oracle SID, Oracle, PC-Anywhere, PCNFS, POP3, POSTGRES, RDP, Rexec, Rlogin, Rsh, S7-300, SAP/R3, SIP, SMB, SMTP, SMTP Enum, SNMP, SOCKS5, SSH (v1 and v2), Subversion, Teamspeak (TS2), Telnet, VMware-Auth, VNC and XMPP.



Option	Description
<b>General Settings</b>	
<b>Only use credentials provided by the user</b>	In some cases, Tenable Nessus can test default accounts and known default passwords. This can cause the account to be locked out if too many consecutive invalid attempts trigger security protocols on the operating system or application. By default, this setting is enabled to prevent Tenable Nessus from performing these tests.
<b>Oracle Database</b>	
<b>Test default Oracle accounts (slow)</b>	Test for known default accounts in Oracle software.
<b>Hydra</b>	
<b>Always enable Hydra (slow)</b>	Enables Hydra whenever the scan is performed.
<b>Logins file</b>	A file that contains user names that Hydra will use during the scan.
<b>Passwords file</b>	A file that contains passwords for user accounts that Hydra will use during the scan.
<b>Number of parallel tasks</b>	The number of simultaneous Hydra tests that you want to execute. By default, this value is <i>16</i> .
<b>Timeout (in seconds)</b>	The number of seconds per login attempt.
<b>Try empty passwords</b>	If enabled, Hydra will additionally try user names without using a password.
<b>Try login as password</b>	If enabled, Hydra will additionally try a user name as the corresponding password.
<b>Stop brute forcing after the first success</b>	If enabled, Hydra will stop brute forcing user accounts after the first time an account is successfully accessed.



Option	Description
<b>Add accounts found by other plugins to the login file</b>	If disabled, only the user names specified in the logins file will be used for the scan. Otherwise, additional user names discovered by other plugins will be added to the logins file and used for the scan.
<b>PostgreSQL database name</b>	The database that you want Hydra to test.
<b>SAP R3 Client ID (0 - 99)</b>	The ID of the SAP R3 client that you want Hydra to test.
<b>Windows accounts to test</b>	Can be set to <b>Local accounts</b> , <b>Domain Accounts</b> , or <b>Either</b> .
<b>Interpret passwords as NTLM hashes</b>	If enabled, Hydra will interpret passwords as NTLM hashes.
<b>Cisco login password</b>	This password is used to login to a Cisco system before brute forcing enable passwords. If no password is provided here, Hydra will attempt to login using credentials that were successfully brute forced earlier in the scan.
<b>Web page to brute force</b>	Type a web page that is protected by HTTP basic or digest authentication. If a web page is not provided here, Hydra will attempt to brute force a page discovered by the Tenable Nessus web crawler that requires HTTP authentication.
<b>HTTP proxy test website</b>	If Hydra successfully brute forces an HTTP proxy, it will attempt to access the website provided here via the brute forced proxy.
<b>LDAP DN</b>	The LDAP Distinguish Name scope that Hydra will authenticate against.

## Malware Options

The **Malware** tab specifies options for DNS Resolution, hash, and allowlist files and file system scanning.



Option	Description
<b>Malware Scan Settings</b>	
<b>Malware scan</b>	When enabled, displays the <b>General Settings</b> , <b>Hash and Allowlist Files</b> , and <b>File System Scanning</b> sections.
<b>General Settings</b> (available when <b>Malware scan</b> is enabled)	
<b>Disable DNS Resolution</b>	Checking this option will prevent Tenable Nessus from using the cloud to compare scan findings against known malware.
<b>Hash and Allowlist Files</b> (available when <b>Malware scan</b> is enabled)	
<b>Custom Netstat IP Threat List</b>	<p>A text file that contains a list of known bad IP addresses that you want to detect.</p> <p>Each line in the file must begin with an IPv4 address. Optionally, you can add a description by adding a comma after the IP address, followed by the description. You can also use hash-delimited comments (e.g., #) in addition to comma-delimited comments.</p> <div data-bbox="511 1050 1479 1125" style="border: 1px solid #0070C0; padding: 5px;"><b>Note:</b> Tenable does not detect private IP ranges in the text file.</div>
<b>Provide your own list of known bad MD5/SHA1/SHA256 hashes</b>	<p>Additional known bad MD5 hashes can be uploaded via a text file that contains one MD5 hash per line.</p> <p>If you want to add a description for each hash, type a comma after the hash, followed by the description. If any matches are found when scanning a target and a description was provided for the hash, the description will show up in the scan results.</p>
<b>Provide your own list of known good MD5/SHA1/SHA256 hashes</b>	<p>Additional known good MD5 hashes can be uploaded via a text file that contains one MD5 hash per line.</p> <p>If you want to add a description for each hash, type a comma after the hash, followed by the description. If any matches are found when scanning a target and a description was provided for the hash, the description will show up in the scan results.</p>



<b>Hosts file allowlist</b>	Tenable Nessus checks system hosts files for signs of a compromise (e.g., Plugin ID 23910). This option allows you to upload a file containing a list of IPs and hostnames that will be ignored by Tenable Nessus during a scan. Include one IP address and hostname (formatted identically to your hosts file on the target) per line in a regular text file.
<b>File System Scanning</b> (available when <b>Malware scan</b> is enabled)	
<b>Scan file system</b>	Turning on this option allows you to scan system directories and files on host computers.  <b>Caution:</b> Enabling this setting in scans targeting 10 or more hosts could result in performance degradation.
<b>Directories</b> (available when <b>File System Scanning</b> is enabled)	
<b>Scan %Systemroot%</b>	Enable file system scanning to scan %Systemroot%.
<b>Scan %ProgramFiles%</b>	Enable file system scanning to scan %ProgramFiles%.
<b>Scan %ProgramFiles (x86)%</b>	Enable file system scanning to scan %ProgramFiles(x86)%.
<b>Scan %ProgramData%</b>	Enable file system scanning to scan %ProgramData%.
<b>Scan User Profiles</b>	Enable file system scanning to scan user profiles.
<b>Custom Filescan Directories</b>	A custom file that lists directories for malware file scanning. List each directory on one line.  <b>Caution:</b> Root directories such as C:\ or D:\ are not accepted.
<b>Yara Rules Files</b>	A .yar file containing the YARA rules to be applied in the scan. You can only upload one file per scan, so include all rules in a single file. For more information, see <a href="https://yara.readthedocs.io">yara.readthedocs.io</a> .

## SCADA Options

The **SCADA** tab specifies how the scanner tests for information against SCADA systems.



Option	Description
<b>Modbus/TCP Coil Access</b>	
<b>Start at register</b> <b>End at register</b>	These options are available for commercial users. This drop-down box item is dynamically generated by the SCADA plugins available with the commercial version of Tenable Nessus. Modbus uses a function code of 1 to read coils in a Modbus slave. Coils represent binary output settings and are typically mapped to actuators. The ability to read coils may help an attacker profile a system and identify ranges of registers to alter via a write coil message. The defaults for this are 0 for the <b>Start at register</b> value and 16 for the <b>End at register</b> value.
<b>ICCP/COTP TSAP Addressing Weakness</b>	
<b>Start COTP TSAP</b> <b>Stop COTP TSAP</b>	The ICCP/COTP TSAP Addressing menu determines a Connection Oriented Transport Protocol (COTP) Transport Service Access Points (TSAP) value on an ICCP server by trying possible values. The start and stop values are set to 8 by default.

## Web Applications Options

The **Web Applications** tab specifies how the scanner tests for information against web server applications.

Value	Description
<b>Web Application Settings</b>	
<b>Scan web applications</b>	When enabled, displays the <b>General Settings</b> , <b>Web Crawler</b> , and <b>Application Test Settings</b> sections.
<b>General Settings</b> (available when <b>Scan web applications</b> is enabled)	
<b>Use a custom User-Agent</b>	Specifies which type of web browser Tenable Nessus will impersonate while scanning.
<b>Web Crawler</b> (available when <b>Scan web applications</b> is enabled)	
<b>Start crawling from</b>	The URL of the first page that will be tested. If multiple pages are required, use a colon delimiter to separate them (e.g., <code>/:/php4:/base</code> ).



Value	Description
<b>Excluded pages (regex)</b>	Enable exclusion of portions of the web site from being crawled. For example, to exclude the /manual directory and all Perl CGI, set this option to: <code>(^/manual) (\.p(?:\?.*)?\$)</code> . Tenable Nessus supports POSIX regular expressions for string matching and handling, as well as Perl-compatible regular expressions (PCRE).
<b>Maximum pages to crawl</b>	The maximum number of pages to crawl.
<b>Maximum depth to crawl</b>	Limit the number of links Tenable Nessus will follow for each start page.
<b>Follow dynamically generated pages</b>	When enabled, Tenable Nessus will follow dynamic links and may exceed the parameters set above.
<b>Application Test Settings</b> (available when <b>Scan web applications</b> is enabled)	
<b>Enable generic web application tests</b>	Enables the <b>Application Test Settings</b> options.
<b>Abort web application tests if HTTP login fails</b>	If Tenable Nessus cannot login to the target via HTTP, then do not run any web application tests.
<b>Try all HTTP Methods</b>	This option will instruct Tenable Nessus to also use POST requests for enhanced web form testing. By default, the web application tests will only use GET requests, unless this option is enabled. Generally, more complex applications use the POST method when a user submits data to the application. This setting provides more thorough testing, but may considerably increase the time required. When selected, Tenable Nessus will test each script/variable with both GET and POST requests. This setting provides more thorough testing, but may considerably increase the time required.
<b>Attempt HTTP</b>	When performing web application tests, attempt to bypass filtering mech-



Value	Description
<b>Parameter Pollution</b>	anisms by injecting content into a variable while supplying the same variable with valid content as well. For example, a normal SQL injection test may look like <code>/target.cgi?a='&amp;b=2</code> . With HTTP Parameter Pollution (HPP) enabled, the request may look like <code>/target.cgi?a='&amp;a=1&amp;b=2</code> .
<b>Test embedded web servers</b>	Embedded web servers are often static and contain no customizable CGI scripts. In addition, embedded web servers may be prone to crash or become non-responsive when scanned. Tenable recommends scanning embedded web servers separately from other web servers using this option.
<b>Test more than one parameter at a time per form</b>	<p>This option manages the combination of argument values used in the HTTP requests. The default, without checking this option, is testing one parameter at a time with an attack string, without trying non-attack variations for additional parameters. For example, Tenable Nessus attempts <code>/test.php?arg1=XSS&amp;b=1&amp;c=1</code> where <i>b</i> and <i>c</i> allows other values, without testing each combination. This is the quickest method of testing with the smallest result set generated.</p> <p>This drop-down box has five selections:</p> <ul style="list-style-type: none"><li>• <b>One value</b> —This tests one parameter at a time with an attack string, without trying non-attack variations for additional parameters. For example, Tenable Nessus attempts <code>/test.php?arg1=XSS&amp;b=1&amp;c=1</code> where <i>b</i> and <i>c</i> allows other values, without testing each combination. This is the quickest method of testing with the smallest result set generated.</li><li>• <b>Some pairs</b> —This form of testing will randomly check a combination of random pairs of parameters. This is the fastest way to test multiple parameters.</li><li>• <b>All pairs (slower but efficient)</b> —This form of testing is slightly slower but more efficient than the one value test. While testing multiple parameters, it will test an attack string, variations for a single variable and then use the first value for all other variables. For example, Tenable Nessus attempts <code>/test.php?arg1=XSS&amp;b=1&amp;c=1</code> and then cycles</li></ul>





Value	Description
	<p>through the variables so that one is given the attack string, one is cycled through all possible values (as discovered during the mirror process) and any other variables are given the first value. In this case, Tenable Nessus will never test for <code>/test.php?a=XSS&amp;b=3&amp;c=3&amp;d=3</code> when the first value of each variable is <code>1</code>.</p> <ul style="list-style-type: none"><li>• <b>Some combinations</b> —This form of testing will randomly check a combination of three or more parameters. This is more thorough than testing only pairs of parameters. Note that increasing the amount of combinations by three or more increases the web application test time.</li><li>• <b>All combinations</b> (extremely slow) —This method of testing will do a fully exhaustive test of all possible combinations of attack strings with valid input to variables. Where All-pairs testing seeks to create a smaller data set as a tradeoff for speed, all combinations makes no compromise on time and uses a complete data set of tests. This testing method may take a long time to complete.</li></ul>
<b>Do not stop after the first flaw is found per web page</b>	<p>This option determines when a new flaw is targeted. This applies at the script level; finding an XSS flaw will not disable searching for SQL injection or header injection, but you will have at most one report for each type on a given port, unless thorough tests is set. Note that several flaws of the same type (e.g., XSS, SQLi, etc.) may be reported sometimes, if they were caught by the same attack. The drop-down has four options:</p> <ul style="list-style-type: none"><li>• <b>Per CGI</b> —As soon as a flaw is found on a CGI by a script, Tenable Nessus switches to the next known CGI on the same server, or if there is no other CGI, to the next port/server. This is the default option.</li><li>• <b>Per port</b> (faster) —As soon as a flaw is found on a web server by a script, Tenable Nessus stops and switches to another web server on a different port.</li><li>• <b>Per parameter</b> (slow) —As soon as one type of flaw is found in a parameter of a CGI (e.g., XSS), Tenable Nessus switches to the next para-</li></ul>



Value	Description
	<p>meter of the same CGI, or the next known CGI, or to the next port/server.</p> <ul style="list-style-type: none"><li>• <b>Look for all flaws</b> (slower) —Perform extensive tests regardless of flaws found. This option can produce a very verbose report and is not recommend in most cases.</li></ul>
<b>URL for Remote File Inclusion</b>	During Remote File Inclusion (RFI) testing, this option specifies a file on a remote host to use for tests. By default, Tenable Nessus will use a safe file hosted by Tenable for RFI testing. If the scanner cannot reach the Internet, using an internally hosted file is recommended for more accurate RFI testing.
<b>Maximum run time (minutes)</b>	This option manages the amount of time in minutes spent performing web application tests. This option defaults to 60 minutes and applies to all ports and CGIs for a given web site. Scanning the local network for web sites with small applications will typically complete in under an hour, however web sites with large applications may require a higher value.

## Windows Options

The **Windows** tab specifies basic Windows SMB domain options.

Option	Description
<b>General Settings</b>	
<b>Request information about the SMB Domain</b>	When enabled, Tenable Nessus queries domain users instead of local users.
<b>User Enumeration Methods</b>	
<b>SAM Registry</b>	When enabled, Tenable Nessus enumerates users via the Security Account Manager (SAM) registry.
<b>ADSI Query</b>	When enabled, Tenable Nessus enumerates users via Active Directory Service Interfaces (ADSI). To use ADSI, you must also configure



Option	Description
	<a href="#">ADSI authentication</a> options.
<b>WMI Query</b>	When enabled, Tenable Nessus enumerates users via Windows Management Interface (WMI).
<b>RID Brute Forcing</b>	When enabled, Tenable Nessus enumerates users via relative identifier (RID) brute forcing. Enabling this setting enables the <b>Enumerate Domain User</b> and <b>Enumerate Local User</b> options.
<b>Enumerate Domain Users</b> (available when <b>RID Brute Forcing</b> is enabled)	
<b>Start UID</b>	1000
<b>End UID</b>	1200
<b>Enumerate Local Users</b> (available when <b>RID Brute Forcing</b> is enabled)	
<b>Start UID</b>	1000
<b>End UID</b>	1200

## Report Options

The **Report** tab specifies information to include in the scan's report.

Option	Description
<b>Processing</b>	
<b>Override normal verbosity</b>	Determines the verbosity of the detail in the output of the scan results: <ul style="list-style-type: none"><li>• <b>Normal</b> —Provides the standard level of plugin activity in the report.</li><li>• <b>Quiet</b> —Provides less information about plugin activity in the report to minimize impact on disk space.</li><li>• <b>Verbose</b> —Provides more information about plugin activity in the report. When this option is selected, the output includes the informational plugins 56310, 64582, and 58651.</li></ul>
<b>Show missing</b>	Show patches in the report that have not been applied but have been



Option	Description
patches that have been superseded	superseded by a newer patch if enabled.
Hide results from plugins initiated as a dependency	If a plugin is only run due to it being a dependency of a selected plugin, hide the results if enabled.
<b>Output</b>	
Designate hosts by their DNS name	When possible, designate hosts by their DNS name rather than IP address in the reports.
Display hosts that respond to ping	When enabled, show a list of hosts that respond to pings sent as part of the scan.
Display unreachable hosts	Display a list of hosts within the scan range that were not able to be reached during the scan, if enabled.
Display Unicode characters	When enabled, Unicode characters appear in plugin output such as usernames, installed application names, and SSL certificate information. <div style="border: 1px solid blue; padding: 5px; margin-top: 10px;"><b>Note:</b> Plugin output may sometimes incorrectly parse or truncate strings with Unicode characters. If this issue causes problems with regular expressions in plugins or custom audits, disable this setting and scan again.</div>
Generate SCAP XML Results	Generate a SCAP XML results file as a part of the report output for the scan.

## Authentication Options

The **Authentication** tab specifies authentication options during a scan.

Option	Description
<b>Authentication</b>	
Type	Specifies the type of authentication you want scanners to use for cre-



Option	Description
	<p>denialed access to scan targets. Credentialed access gathers more complete data about a target.</p> <ul style="list-style-type: none"><li>• <a href="#">Host</a></li><li>• <a href="#">Database Credentials</a></li><li>• <a href="#">Miscellaneous</a></li><li>• <a href="#">Plaintext Authentication</a></li><li>• <a href="#">Patch Management</a></li></ul>
<b>SNMP</b>	
<b>UDP Port</b> <b>Additional UDP port # 1</b> <b>Additional UDP port # 2</b> <b>Additional UDP port # 3</b>	<p>This is the UDP port that will be used when performing certain SNMP scans. Up to four different ports may be configured, with the default port being <i>161</i>.</p>
<b>SSH</b>	
<b>known_hosts file</b>	<p>If an SSH known_hosts file is provided for the scan policy, Tenable Nessus will only attempt to log in to hosts defined in this file. This helps to ensure that the same username and password you are using to audit your known SSH servers is not used to attempt a login to a system that may not be under your control.</p>
<b>Preferred port</b>	<p>This option is set to direct the scan to connect to a specific port if SSH is known to be listening on a port other than the default of 22.</p>
<b>Client version</b>	<p>Specifies which type of SSH client to impersonate while performing scans.</p>
<b>Attempt least priv-</b>	<p>Enables or disables dynamic privilege escalation. When enabled, if the</p>



Option	Description
<b>ilege (experimental)</b>	<p>scan target credentials include privilege escalation, Tenable Nessus first attempts to run commands without privilege escalation. If running commands without privilege escalation fails, Tenable Nessus retries the commands with privilege escalation.</p> <p>Plugins 102095 and 102094 report whether plugins ran with or without privilege escalation.</p> <div data-bbox="451 583 1479 699" style="border: 1px solid #0056b3; padding: 5px;"><b>Note:</b> Enabling this option may increase the time required to perform scans by up to 30%.</div>
<b>Windows</b>	
<b>Never send credentials in the clear</b>	By default, Windows credentials are not sent to the target host in the clear.
<b>Do not use NTLMv1 authentication</b>	<p>When disabled, it is theoretically possible to trick Tenable Nessus into attempting to log in to a Windows server with domain credentials via the NTLM version 1 protocol. This provides the remote attacker with the ability to use a hash obtained from Tenable Nessus. This hash can be potentially cracked to reveal a username or password. It may also be used to directly log in to other servers.</p> <p>Because NTLMv1 is an insecure protocol, this option is enabled by default.</p>
<b>Start the Remote Registry service during the scan</b>	This option tells Tenable Nessus to start the Remote Registry service on computers being scanned if it is not running. This service must be running in order for Tenable Nessus to execute some Windows local check plugins.
<b>Enable administrative shares during the scan</b>	This option will allow Tenable Nessus to access certain registry entries that can be read with administrator privileges.
<b>Start the Server</b>	When enabled, the scanner temporarily enables the Windows Server ser-



Option	Description
<b>service during the scan</b>	<p>vice, which allows the computer to share files and other devices on a network. The service is disabled after the scan completes.</p> <p>By default, Windows systems have the Windows Server service enabled, which means you do not need to enable this setting. However, if you disable the Windows Server service in your environment, and want to scan using SMB credentials, you must enable this setting so that the scanner can access files remotely.</p>
<b>Plaintext Authentication</b>	
<b>Perform patch audits over telnet</b>	<p>When enabled, Tenable Security Center uses telnet to connect to the host device for patch audits.</p> <p><b>Note:</b> This protocol is sent in cleartext and could contain unencrypted usernames and passwords.</p>
<b>Perform patch audits over rsh</b>	<p>When enabled, Tenable Security Center permits patch audits over a rsh connection.</p> <p><b>Note:</b> This protocol is sent in cleartext and could contain unencrypted usernames and passwords.</p>
<b>Perform patch audits over rexec</b>	<p>When enabled, Tenable Security Center permits patch audits over a rexec connection.</p> <p><b>Note:</b> This protocol is sent in cleartext and could contain unencrypted usernames and passwords.</p>
<b>HTTP</b>	
<b>Login method</b>	<p>Specify whether the login action is performed via a GET or POST request.</p>
<b>Re-authenticate delay (seconds)</b>	<p>The delay between authentication attempts, in seconds.</p> <p><b>Tip:</b> A time delay can help prevent triggering brute force lockout mechanisms.</p>
<b>Follow 30x redir-</b>	<p>If a 30x redirect code is received from a web server, this directs Tenable</p>



Option	Description
<b>actions (# of levels)</b>	Nessus to follow the link provided or not.
<b>Invert authenticated regex</b>	The regex pattern you want Tenable Security Center to look for on the login page that, if found, denies authentication.  <b>Tip:</b> Tenable Security Center can attempt to match a given string, such as Authentication failed.
<b>Use authenticated regex on HTTP headers</b>	When enabled, Tenable Security Center searches the HTTP response headers for a given regex pattern instead of searching the body of a response to better determine authentication state.
<b>Case insensitive authenticated regex</b>	When enabled, Tenable Security Center ignores case in regex.

## Compliance Options

The **Compliance** tab specifies compliance the audit files to reference in a scan policy. The options available depend on the type of audit file selected.

For more information, see [Audit Files](#) and [Configure Compliance Options](#).

Option	Description
<b>Generic SSH Escalation command</b>	(Generic SSH audits only) The command to use for accomplishing the privilege escalation. This is similar to the enable command for Cisco devices.
<b>Generic SSH Escalation success check</b>	(Generic SSH audits only) A regular expression that must match after the escalation has succeeded. This can be the prompt or any other message notifying the success of privilege escalation.

## Plugins Options

The **Plugins** tab specifies which plugins are used during the policy's Tenable Nessus scan. You can enable or disable plugins in the plugin family view or in the plugin view for more granular control.





For more information, see [Configure Plugin Options](#).

**Caution:** The Denial of Service plugin family contains plugins that could cause outages on network hosts if the **Safe Checks** option is not enabled, but it also contains useful checks that do not cause any harm. The Denial of Service plugin family can be used in conjunction with **Safe Checks** to ensure that any potentially dangerous plugins are not run. However, Tenable does not recommend enabling the Denial of Service plugin family in production environments.



## Configure Compliance Options

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

You can configure compliance options within a scan policy to reference one or more audit files in a template-based **Policy Compliance Auditing** scan policy or a custom scan policy.

For more information, see [Audit Files](#), [Scan Policies](#), and [Scan Policy Options](#).

To configure compliance options for a scan policy:

1. Begin configuring a scan policy, as described in [Add a Scan Policy](#).

2. In the left navigation bar, click **Compliance**.

The **Compliance** options appear.

3. Click **+ Add Audit File**.

The **Select a Type** drop-down box appears.

4. In the **Select a Type** drop-down box, select the type of audit file you want to reference in the scan policy.

The **Select an Audit File** drop-down box appears.

5. In the **Select an Audit File** drop-down box, select the name of the audit file you want to reference in the scan policy.

6. Click the  button.

Tenable Security Center applies the audit file to the scan policy.

7. If required, configure additional options for the audit file you applied to the scan policy. For more information, see [Compliance Options](#).



## Configure Plugin Options

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

You can configure plugin options within a scan policy to enable or disable plugins at the plugin family level or individual plugin level.

**Note:** When Tenable adds new plugins to Tenable Security Center, Tenable Security Center automatically enables the new plugins if the entire plugin family they belong to is enabled in your scan policy template.

To configure plugin options at the plugin family level:

1. Begin configuring a scan, policy as described in [Add a Scan Policy](#).
2. In the left navigation bar, click **Plugins**.

The **Plugins** page appears with the plugin family view displayed.

3. In the **Status** column, view the plugin family status and the number of enabled plugins within the plugin family:
  - **Enabled** —All plugins in the family are enabled. The scan targets the parameters in the plugins.
  - **Disabled** —All plugins in the family are disabled. The scan does not target the parameters in the plugins.

**Note:** Disabling a plugin family reduces the time and resources required to run the scan.

- **Mixed** —The plugin family contains a combination of **Enabled** and **Disabled** plugins.

Mixed plugin families have a padlock icon that is locked or unlocked:

- **Locked** - New plugins added to the plugin family via plugin feed updates will be *disabled* automatically in the policy.
- **Unlocked** - New plugins added to the plugin family via plugin feed updates will be *enabled* automatically in the policy.

4. In the **Total** column, view the number of plugins in the family.



5. To enable or disable all plugins in the family, click the **Status** box.
6. To filter the plugin families listed on the page, use the **Select a Filter** drop-down box to build and apply a filter.

The **Total** column becomes the **Matched** column and indicates the number of plugins in the family that match the current filter.

7. To hide all disabled plugin families, click **Hide Disabled**.
8. If you hid all disabled plugin families and you want to show them again, click **Show All**.
9. To sort the plugin families listed on the page, click the **Status**, **Plugin Family**, or **Total** column title.
10. To enable or disable all of the plugin families displayed on the page, click **Enable Shown** or **Disable Shown**.

Tenable Security Center enables or disables all plugins within the plugin families shown on the page, not just the number of plugins in the **Total** or **Matched** column. For more granular control, set plugin statuses in the plugin view.

11. To enable or disable individual plugins within a family, click the plugin family name to access the plugin view.

The plugin view appears.

To configure plugin options at the individual plugin level:

1. Begin configuring a scan policy as described in [Add a Scan Policy](#).
2. Click **Plugins** in the left navigation bar.

The **Plugins** page appears.

3. Click the plugin family name.

The plugin view appears.

4. In the **Status** column, view the plugin status:



- **Enabled** —The plugin is enabled. The scan targets the parameters in the plugins.
- **Disabled** —The plugin is disabled. The scan does not target the parameters in the plugins.

Disabling a plugin family reduces the time and resources required to run the scan.

5. In the **Plugin ID** column, click the information icon to display the plugin details.
6. To enable or disable a plugin, click the **Status** box.
7. To filter the plugins listed on the page, use the **Select a Filter** drop-down box to build and apply a filter.
8. To hide all disabled plugins, click **Hide Disabled**.
9. If you hid all disabled plugins and you want to show them again, click **Show All**.
10. To sort the plugins listed on the page, click the **Status**, **Plugin Name**, or **Plugin ID** column title.
11. To enable or disable all of the plugins displayed on the page, click **Enable Shown** or **Disable Shown**.  
  
Tenable Security Center enables or disables all plugins shown on the page.
12. To return to the plugin family view, click the **Back** option.
13. To view the plugins in a different family, click the drop-down box and select a different plugin family.



## Host

Tenable Security Center can use SNMPv3 credentials to scan remote systems that use an encrypted network management protocol (including network devices). Tenable Security Center uses these credentials to scan for patch auditing or compliance checks.

You can configure SNMPv3 options in scan policies, as described in [Authentication Options](#) and [Add a Scan Policy](#).

## SNMPv3 Options

Option	Description	Default
Username	The username for the SNMPv3 account that Tenable Security Center uses to perform checks on the target system.	-
Port	(Required) The TCP port that SNMPv3 listens on for communications from Tenable Security Center.	161
Security Level	The security level for SNMP: <ul style="list-style-type: none"><li>• <b>No authentication and no privacy</b></li><li>• <b>Authentication without privacy</b></li><li>• <b>Authentication and privacy</b></li></ul>	Authentication and privacy
Authentication algorithm	The algorithm the remote service supports: <b>MD5</b> or <b>SHA1</b> .	SHA1
Authentication password	The password associated with the <b>Username</b> .	-
Privacy algorithm	The encryption algorithm to use for SNMP traffic: <b>AES</b> or <b>DES</b> .	AES
Privacy password	A password used to protect encrypted SNMP communication.	-



## Miscellaneous

Tenable Security Center supports the following additional authentication methods:

- [ADSI](#)
- [F5](#)
- [IBMiSeries](#)
- [Red Hat Enterprise Virtualization \(RHEV\)](#)
- [Netapp API](#)
- [Palo Alto Networks PAN-OS](#)
- [VMware ESX SOAP API](#)
- [VMware vCenter SOAP API](#)
- [X.509](#)

You can configure these authentication methods in scan policies, as described in [Authentication Options](#) and [Add a Scan Policy](#).

### ADSI

ADSI allows Tenable Security Center to query an ActiveSync server to determine if any Android or iOS-based devices are connected. Using the credentials and server information, Tenable Security Center authenticates to the domain controller (not the Exchange server) to directly query it for device information. These settings are required for mobile device scanning and Active Directory Starter Scans.

Tenable Security Center supports obtaining the mobile information from Exchange Server 2010 and 2013 only.

Option	Description	Default
Domain Controller	(Required) The name of the domain controller for ActiveSync.	-
Domain	(Required) The name of the NetBIOS domain for ActiveSync.	-



Option	Description	Default
Domain Admin	(Required) The domain administrator's username.	-
Domain Password	(Required) The domain administrator's password.	-

## F5

Option	Description	Default
Username	(Required) The username for the scanning F5 account that Tenable Security Center uses to perform checks on the target system.	-
Password	(Required) The password for the F5 user.	-
Port	(Required) The TCP port that F5 listens on for communications from Tenable Security Center.	443
HTTPS	When enabled, Tenable Security Center connects using secure communication (HTTPS).  When disabled, Tenable Security Center connects using standard HTTP.	enabled
Verify SSL Certificate	When enabled, Tenable Security Center verifies that the SSL certificate on the server is signed by a trusted CA.  <b>Tip:</b> If you are using a self-signed certificate, disable this setting.	enabled

## IBMiSeries

Option	Description	Default
Username	(Required) The username for the IBMiSeries account that Tenable Security Center uses to perform checks on the target system.	-
Password	(Required) The password for the IBMiSeries user.	-





## Red Hat Enterprise Virtualization (RHEV)

Option	Description	Default
Username	(Required) The username for RHEV account that Tenable Security Center uses to perform checks on the target system.	-
Password	(Required) The password for the RHEV user.	-
Port	(Required) The TCP port that the RHEV server listens on for communications from Tenable Security Center.	443
Verify SSL Certificate	When enabled, Tenable Security Center verifies that the SSL certificate on the server is signed by a trusted CA.  <b>Tip:</b> If you are using a self-signed certificate, disable this setting.	enabled

## Netapp API

Option	Description	Default
Username	(Required) The username for the Netapp API account with HTTPS access that Tenable Security Center uses to perform checks on the target system.	-
Password	(Required) The password for the Netapp API user.	-
vFiler	The vFiler nodes to scan for on the target systems.  To limit the audit to a single vFiler, type the name of the vFiler.  To audit for all discovered Netapp virtual filers (vFilers) on target systems, leave the field blank.	-
Port	(Required) The TCP port that Netapp API listens on for communications from Tenable Security Center.	443

## Palo Alto Networks PAN-OS



Option	Description	Default
Username	(Required) The username for the PAN-OS account that Tenable Security Center uses to perform checks on the target system.	-
Password	(Required) The password for the PAN-OS user.	-
Port	(Required) The TCP port that PAN-OS listens on for communications from Tenable Security Center.	443
Verify SSL Certificate	When enabled, Tenable Security Center verifies that the SSL certificate on the server is signed by a trusted CA.  <b>Tip:</b> If you are using a self-signed certificate, disable this setting.	enabled

## VMware ESX SOAP API

For more information about configuring VMWare ESX SOAP API, see [Configure vSphere Scanning](#).

Tenable Security Center can access VMware servers through the native VMware SOAP API.

Option	Description	Default
Username	(Required) The username for the ESXi server account that Tenable Security Center uses to perform checks on the target system.	-
Password	(Required) The password for the ESXi user.	-
Do not verify SSL Certificate	Do not validate the SSL certificate for the ESXi server.	disabled

## VMware vCenter SOAP API

For more information about configuring VMWare vCenter SOAP API, see [Configure vSphere Scanning](#).



Tenable Security Center can access vCenter through the native VMware vCenter SOAP API. If available, Tenable Security Center uses the vCenter REST API to collect data in addition to the SOAP API.

**Note:** The SOAP API requires a vCenter admin account with read and write permissions. The REST API requires a vCenter admin account with read permissions, and a VMware vSphere Lifecycle manager account with read permissions.

Option	Description	Default
vCenter Host	(Required) The name of the vCenter host.	-
vCenter Port	(Required) The TCP port that vCenter listens on for communications from Tenable Security Center.	443
Username	(Required) The username for the vCenter server account with admin read/write access that Tenable Security Center uses to perform checks on the target system.	-
Password	(Required) The password for the vCenter server user.	-
HTTPS	When enabled, Tenable Security Center connects using secure communication (HTTPS). When disabled, Tenable Security Center connects using standard HTTP.	enabled
Verify SSL Certificate	When enabled, Tenable Security Center verifies that the SSL certificate on the server is signed by a trusted CA. <b>Tip:</b> If you are using a self-signed certificate, disable this setting.	enabled

## X.509

Option	Description	Default
Client Certificate	(Required) The client certificate.	-
Client Key	(Required) The client private key.	-
Password	(Required) The passphrase for the client private key.	-
CA Certificate to Trust	(Required) The trusted Certificate Authority's (CA) digital certificate.	-



## Plaintext Authentication

**Caution:** Tenable does not recommend plaintext credentials. Instead, use encrypted authentication methods when possible.

If a secure method of performing credentialed checks is not available, you can configure Tenable Security Center to perform checks over unsecure protocols using plaintext authentication settings.

Tenable Security Center supports the following plaintext authentication methods:

- [telnet/rsh/rexec](#)
- [NNTP](#)
- [FTP](#)
- [POP2](#)
- [POP3](#)
- [IMAP](#)
- [IPMI](#)
- [HTTP](#)

You can configure plaintext authentication options in scan policies, as described in [Authentication Options](#) and [Add a Scan Policy](#).

### telnet/rsh/rexec

Tenable Security Center performs patch auditing on non-Windows targets only.

Setting	Description	Default
Username	(Required) The username for the telnet, rsh, or rexec account that Tenable Security Center uses to perform checks on the target system.	-
Password (Unsafe!)	(Required) The password for the telnet, rsh, or rexec user.	-

### NNTP



Setting	Description	Default
Username	(Required) The username for the NNTP account that Tenable Security Center uses to perform checks on the target system.	-
Password	(Required) The password for the NNTP user.	-

## FTP

Setting	Description	Default
Username	(Required) The username for the FTP account that Tenable Security Center uses to perform checks on the target system.	-
Password	(Required) The password for the FTP user.	-

## POP2

Setting	Description	Default
Username	(Required) The username for the POP2 account that Tenable Security Center uses to perform checks on the target system.	-
Password	(Required) The password for the POP2 user.	-

## POP3

Setting	Description	Default
Username	(Required) The username for the POP3 account that Tenable Security Center uses to perform checks on the target system.	-
Password	(Required) The password for the POP3 user.	-

## IMAP

Setting	Description	Default
Username	(Required) The username for the IMAP account that Tenable	-



	Security Center uses to perform checks on the target system.	
Password	(Required) The password for the IMAP user.	-

## IPMI

Setting	Description	Default
Username	(Required) The username for the IPMI account that Tenable Security Center uses to perform checks on the target system.	-
Password (Sent in Clear)	(Required) The password for the IPMI user.	-

## HTTP

Setting	Description	Default
Authentication Method	(Required) The authentication method. <ul style="list-style-type: none"><li>• <b>Automatic authentication</b></li><li>• <b>Basic/Digest authentication</b></li><li>• <b>HTTP login form</b> —Controls the start location of authenticated testing of a custom web-based application.</li><li>• <b>HTTP cookies import</b> —Tenable Security Center uses cookies imported from another piece of software (such as a web browser or web proxy) to facilitate web application testing by using when attempting to access a web application.</li></ul>	HTTP Login Form
Username	(Required) The username for the HTTP account that Tenable Security Center uses to perform checks on the target system.	-
Password	(Required) The password for the HTTP user.	-



Setting	Description	Default
Login page	(Required) The absolute path to the application login page. For example, /login.html.	–
Login submission page	(Required) The action parameter for the form method. For example, for <form method="POST" name="auth_form" action="/login.php">, use /login.php.	–
Login parameters	(Required) The authentication parameters (for example, login=%USER%&password=%PASS%).  Tenable Security Center replaces the %USER% and %PASS% keywords with values supplied on the Login configurations drop-down menu.  <b>Tip:</b> If needed, you can provide additional parameters, such as a group name or other information required for authentication.	–
Check authentication on page	(Required) The absolute path of a protected web page that requires authentication. For example, /admin.html.	–
Regex to verify successful authentication	(Required) The regex pattern you want Tenable Security Center to look for on the login page to validate authentication.  <b>Tip:</b> Tenable Security Center can attempt to match a given string, such as Authentication successful.	–
Cookies file	(Required) A cookie file in Netscape cookies.txt format.	–



# Patch Management

Tenable Security Center can leverage credentials for patch management systems to perform patch auditing on systems for which credentials may not be available to Nessus Professional or managed scanners.

Tenable Security Center supports:

- [Dell KACE K1000](#)
- [HCL BigFix](#)
- [Microsoft System Center Configuration Manager \(SCCM\)](#)
- [Microsoft Windows Server Update Services \(WSUS\)](#)
- [Red Hat Satellite Server](#)
- [Symantec Altiris](#)

You can configure patch management options in scan policies, as described in [Authentication Options](#) and [Add a Scan Policy](#).

IT administrators are expected to manage the patch monitoring software and install any agents required by the patch management system on their systems.

**Note:** If the credential check sees a system but it is unable to authenticate against the system, it uses the data obtained from the patch management system to perform the check. If Tenable Security Center is able to connect to the target system, it performs checks on that system and ignores the patch management system output.

**Note:** The data returned to Tenable Security Center by the patch management system is only as current as the most recent data that the patch management system has obtained from its managed hosts.

## Scanning with Multiple Patch Managers

If you provide multiple sets of credentials to Tenable Security Center for patch management tools, Tenable Security Center uses all of them.

If you provide credentials for a host and for one or more patch management systems, Tenable Security Center compares the findings between all methods and report on conflicts or provide a sat-





ified finding. Use the Patch Management Windows Auditing Conflicts plugins to highlight patch data differences between the host and a patch management system.

## Dell KACE K1000

KACE K1000 is available from Dell to manage the distribution of updates and hotfixes for Linux, Windows, and macOS systems. Tenable Security Center can query KACE K1000 to verify whether or not patches are installed on systems managed by KACE K1000 and display the patch information through the Tenable Security Center user interface.

Tenable Security Center supports KACE K1000 versions 6.x and earlier.

KACE K1000 scanning uses the following Tenable plugins: 76867, 76868, 76866, and 76869.

Option	Description	Default
Server	(Required) The KACE K1000 IP address or system name.	-
Database Port	(Required) The TCP port that KACE K1000 listens on for communications from Tenable Security Center.	3306
Organization Database Name	(Required) The name of the organization component for the KACE K1000 database (e.g., ORG1).	ORG1
Database Username	(Required) The username for the KACE K1000 account that Tenable Security Center uses to perform checks on the target system.	R1
K1000 Database Password	(Required) The password for the KACE K1000 user.	-

## HCL BigFix

HCL Bigfix is available to manage the distribution of updates and hotfixes for desktop systems. Tenable Security Center can query HCL Bigfix to verify whether or not patches are installed on systems managed by HCL Bigfix and display the patch information.

Package reporting is supported by RPM-based and Debian-based distributions that HCL Bigfix officially supports. This includes Red Hat derivatives such as RHEL, CentOS, Scientific Linux, and Oracle Linux, as well as Debian and Ubuntu. Other distributions may also work, but unless HCL Bigfix officially supports them, there is no support available.



For local check plugins to trigger, only RHEL, CentOS, Scientific Linux, Oracle Linux, Debian, Ubuntu, and Solaris are supported. Plugin 160250 must be enabled.

Tenable Security Center supports HCL Bigfix 9.5 and later and 10.x and later.

HCL Bigfix scanning uses the following Tenable plugins: 160247, 160248, 160249, 160250, and 160251.

Option	Description	Default
Web Reports Server	(Required) The name of HCL Bigfix Web Reports server.	-
Web Reports Port	(Required) The TCP port that the HCL Bigfix Web Reports server listens on for communications from Tenable Security Center.	-
Web Reports Username	(Required) The username for the HCL Bigfix Web Reports administrator account that Tenable Security Center uses to perform checks on the target system.	-
Web Reports Password	(Required) The password for the HCL Bigfix Web Reports administrator user.	-
HTTPS	When enabled, Tenable Security Center connects using secure communication (HTTPS).  When disabled, Tenable Security Center connects using standard HTTP.	Enabled
Verify SSL certificate	When enabled, Tenable Security Center verifies that the SSL certificate on the server is signed by a trusted CA.  <b>Tip:</b> If you are using a self-signed certificate, disable this setting.	Enabled

## HCL Bigfix Server Configuration

In order to use these auditing features, you must make changes to the HCL Bigfix server. You must import a custom analysis into HCL Bigfix so that detailed package information is retrieved and made available to Tenable Security Center.

From the HCL BigFix Console application, import the following .bes files.



## BES file:

```
<?xml version="1.0" encoding="UTF-8"?>
<BES xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xsi:noNamespaceSchemaLocation="BES.xsd">
  <Analysis>
    <Title>Tenable</Title>
    <Description>This analysis provides SecurityCenter with the data it needs for vulnerability reporting. </Description>
    <Relevance>true</Relevance>
    <Source>Internal</Source>
    <SourceReleaseDate>2013-01-31</SourceReleaseDate>
    <MIMEField>
      <Name>x-fixlet-modification-time</Name>
      <Value>Thu, 13 May 2021 21:43:29 +0000</Value>
    </MIMEField>
    <Domain>BESC</Domain>
    <Property Name="Packages - With Versions (Tenable)" ID="74"><![CDATA[if (exists true whose (if true then repository) else false)) then unique values of (lpp_name of it & "|" & version of it as string & "|" & "fileset" tecture of operating system) of filesets of products of object repository else if (exists true whose (if true then anpackage) else false)) then unique values of (name of it & "|" & version of it as string & "|" & "deb" & "|" & it & "|" & architecture of operating system) of packages whose (exists version of it) of debianpackages else if whose (if true then (exists rpm) else false)) then unique values of (name of it & "|" & version of it as string & "|" & architecture of it & "|" & architecture of operating system) of packages of rpm else if (exists true whose (exists ips image) else false)) then unique values of (full name of it & "|" & version of it as string & "|" & architecture of operating system) of latest installed packages of ips image else if (exists true whose (if true pkgdb) else false)) then unique values of (pkginst of it & "|" & version of it & "|" & "pkg10") of pkginfos of pk<\/CDATA><\/Property>
    <Property Name="Tenable AIX Technology Level" ID="76">current technology level of operating system<\/Property>
    <Property Name="Tenable Solaris - Showrev -a" ID="77"><![CDATA[if ((operating system as string as lowercase "SunOS 5.10" as lowercase) AND (exists file "/var/opt/BESClient/showrev_patches.b64")) then lines of file "/var/opt/BESClient/showrev_patches.b64" else "<\/CDATA><\/Property>
  <\/Analysis>
<\/BES>
```

## BES file:

```
<?xml version="1.0" encoding="UTF-8"?>
<BES xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xsi:noNamespaceSchemaLocation="BES.xsd">
  <Task>
    <Title>Tenable - Solaris 5.10 - showrev -a Capture</Title>
    <Description><![CDATA[&lt;enter a description of the task here&gt; ]]></Description>
    <GroupRelevance JoinByIntersection="false">
      <SearchComponentPropertyReference PropertyName="OS" Comparison="Contains">
        <SearchText>SunOS 5.10</SearchText>
        <Relevance>exists (operating system) whose (it as string as lowercase contains "SunOS 5.10" as lowercase)</Relevance>
      <\/SearchComponentPropertyReference>
    <\/GroupRelevance>
    <Category><\/Category>
    <Source>Internal</Source>
    <SourceID><\/SourceID>
    <SourceReleaseDate>2021-05-12</SourceReleaseDate>
    <SourceSeverity><\/SourceSeverity>
    <CVENames><\/CVENames>
    <SANSID><\/SANSID>
    <MIMEField>
      <Name>x-fixlet-modification-time</Name>
      <Value>Thu, 13 May 2021 21:50:58 +0000</Value>
    <\/MIMEField>
  <\/Task>
<\/BES>
```



```
</MIMEField>
<Domain>BESC</Domain>
<DefaultAction ID="Action1">
  <Description>
    <PreLink>Click </PreLink>
    <Link>here</Link>
    <PostLink> to deploy this action.</PostLink>
  </Description>
  <ActionScript MIMETYPE="application/x-sh"><![CDATA[#!/bin/sh
/usr/bin/showrev -a > /var/opt/BESClient/showrev_patches
/usr/sfw/bin/openssl base64 -in /var/opt/BESClient/showrev_patches -out /var/opt/BESClient/showrev_
patches.b64
]]></ActionScript>
</DefaultAction>
</Task>
</BES>
```

## Microsoft System Center Configuration Manager (SCCM)

Microsoft System Center Configuration Manager (SCCM) is available to manage large groups of Windows-based systems. Tenable Security Center can query the SCCM service to verify whether or not patches are installed on systems managed by SCCM and display the patch information through the scan results.

Tenable Security Center connects to the server that is running the SCCM site (e.g., credentials must be valid for the SCCM service, so the selected user must have privileges to query all the data in the SCCM MMC). This server may also run the SQL database, or the database and the SCCM repository can be on separate servers. When leveraging this audit, Tenable Security Center must connect to the SCCM server via WMI and HTTPS.

SCCM scanning uses the following Tenable plugins: 57029, 57030, 73636, and 58186.

**Note:** SCCM patch management plugins support SCCM 2007, SCCM 2012, SCCM 2016, and SCCM 2019.

Credential	Description	Default
Server	(Required) The SCCM IP address or system name.	-
Domain	(Required) The name of the SCCM server's domain.	-
Username	(Required) The username for the SCCM user account that Tenable Security Center uses to perform checks on the target system. The user account must have privileges to query all data in	-



Credential	Description	Default
	the SCCM MMC.	
Password	(Required) The password for the SCCM user with privileges to query all data in the SCCM MMC.	-

## Windows Server Update Services (WSUS)

Windows Server Update Services (WSUS) is available from Microsoft to manage the distribution of updates and hotfixes for Microsoft products. Tenable Security Center can query WSUS to verify whether or not patches are installed on systems managed by WSUS and display the patch information through the Tenable Security Center user interface.

WSUS scanning uses the following Tenable plugins: 57031, 57032, and 58133.

Option	Description	Default
Server	(Required) The WSUS IP address or system name.	-
Port	(Required) The TCP port that Microsoft WSUS listens on for communications from Tenable Security Center.	8530
Username	(Required) The username for the WSUS administrator account that Tenable Security Center uses to perform checks on the target system.	-
Password	(Required) The password for the WSUS administrator user.	-
HTTPS	When enabled, Tenable Security Center connects using secure communication (HTTPS).  When disabled, Tenable Security Center connects using standard HTTP.	Enabled
Verify SSL Certificate	When enabled, Tenable Security Center verifies that the SSL certificate on the server is signed by a trusted CA.  <b>Tip:</b> If you are using a self-signed certificate, disable this setting.	Enabled



## Red Hat Satellite Server

Red Hat Satellite is a systems management platform for Linux-based systems. Tenable Security Center can query Satellite to verify whether or not patches are installed on systems managed by Satellite and display the patch information.

Although not supported by Tenable, the Red Hat Satellite plugin also works with Spacewalk Server, the Open Source Upstream Version of Red Hat Satellite. Spacewalk can manage distributions based on Red Hat (RHEL, CentOS, Fedora) and SUSE. Tenable supports the Satellite server for Red Hat Enterprise Linux.

Satellite scanning uses the following Tenable plugins: 84236, 84235, 84234, 84237, and 84238.

Option	Description	Default
Satellite Server	(Required) The Red Hat Satellite IP address or system name.	-
Port	(Required) The TCP port that Red Hat Satellite listens on for communications from Tenable Security Center.	443
Username	(Required) The username for the Red Hat Satellite account that Tenable Security Center uses to perform checks on the target system.	-
Password	(Required) The password for the Red Hat Satellite user.	-
Verify SSL Certificate	When enabled, Tenable Security Center verifies that the SSL certificate on the server is signed by a trusted CA.  <b>Tip:</b> If you are using a self-signed certificate, disable this setting.	Enabled

## Red Hat Satellite 6 Server

Red Hat Satellite 6 is a systems management platform for Linux-based systems. Tenable Security Center can query Satellite to verify whether or not patches are installed on systems managed by Satellite and display the patch information.

Although not supported by Tenable, the Red Hat Satellite 6 plugin also works with Spacewalk Server, the Open Source Upstream Version of Red Hat Satellite. Spacewalk can manage



distributions based on Red Hat (RHEL, CentOS, Fedora) and SUSE. Tenable supports the Satellite server for Red Hat Enterprise Linux.

Red Hat Satellite 6 scanning uses the following Tenable plugins: 84236, 84235, 84234, 84237, 84238, 84231, 84232, and 84233.

Option	Description	Default
Satellite Server	(Required) The Red Hat Satellite 6 IP address or system name.	-
Port	(Required) The TCP port that Red Hat Satellite 6 listens on for communications from Tenable Security Center.	443
Username	(Required) The username for the Red Hat Satellite 6 account that Tenable Security Center uses to perform checks on the target system.	-
Password	(Required) The password for the Red Hat Satellite 6 user.	-
HTTPS	When enabled, Tenable Security Center connects using secure communication (HTTPS).  When disabled, Tenable Security Center connects using standard HTTP.	Enabled
Verify SSL Certificate	When enabled, Tenable Security Center verifies that the SSL certificate on the server is signed by a trusted CA.  <b>Tip:</b> If you are using a self-signed certificate, disable this setting.	Enabled

## Symantec Altiris

Altiris is available from Symantec to manage the distribution of updates and hotfixes for Linux, Windows, and macOS systems. Tenable Security Center has the ability to use the Altiris API to verify whether or not patches are installed on systems managed by Altiris and display the patch information through the Tenable Security Center user interface.



Tenable Security Center connects to the Microsoft SQL server that is running on the Altiris host. When leveraging this audit, if the MSSQL database and Altiris server are on separate hosts, Tenable Security Center must connect to the MSSQL database, not the Altiris server.

Altiris scanning uses the following Tenable plugins: 78013, 78012, 78011, and 78014.

Credential	Description	Default
Server	(Required) The Altiris IP address or system name.	-
Database Port	(Required) The TCP port that Altiris listens on for communications from Tenable Security Center.	5690
Database Name	(Required) The name of the MSSQL database that manages Altiris patch information.	Symantec_CMDB
Database Username	(Required) The username for the Altiris MSSQL database account that Tenable Security Center uses to perform checks on the target system. Credentials must be valid for a MSSQL database account with the privileges to query all the data in the Altiris MSSQL database.	-
Database Password	(Required) The password for the Altiris MSSQL database user.	-
Use Windows Authentication	When enabled, use NTLMSSP for compatibility with older Windows Servers.  When disabled, use Kerberos.	Enabled





## View Your Scan Policies

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information, see [Scan Policies](#).

To view a list of configured scan policies:

1. Log in to Tenable Security Center via the user interface.
2. Click **Scanning > Policies** (administrator users) or **Scans > Policies** (organizational users).

The **Policies** page appears.

3. View details about each scan policy.
  - **Name** —The name of the scan policy.
  - **Tag** —The tag applied to the scan policy.
  - **Type** —The name of the template used to add the scan policy.
  - **Group** —The group associated with the scan policy.
  - **Owner** —The username for the user associated with the scan policy.
  - **Last Modified** —The date and time the scan policy was last modified.



## View Scan Policy Details

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

You can view details for individual scan policies. For more information, see [Scan Policies](#).

To view details of a scan policy:

1. Log in to Tenable Security Center via the user interface.
2. Click **Scanning > Policies** (administrator users) or **Scans > Policies** (organizational users).

The **Policies** page appears.

3. Right-click the row for the scan policy you want to view.

The actions menu appears.

-or-

Select the check box for the scan policy you want to view.

The available actions appear at the top of the table.

4. Click **View**.

The **View Policy** page appears.

Section	Action
<b>General</b>	<p>View general information for the scan policy.</p> <ul style="list-style-type: none"><li>• <b>Name</b> —The name of the scan policy.</li><li>• <b>Description</b> —The description for the scan policy.</li><li>• <b>Tag</b> —The tag applied to the scan policy.</li><li>• <b>Type</b> —The name of the template used to add the scan policy.</li><li>• <b>Created</b> —The date and time the scan policy was added.</li><li>• <b>Last Modified</b> —The date and time the scan policy was last modified.</li></ul>



Section	Action
	<ul style="list-style-type: none"><li>• <b>Owner</b> —The username for the user associated with the scan policy.</li><li>• <b>Group</b> —The group associated with the scan policy.</li><li>• <b>ID</b> —The scan policy ID.</li></ul>
<b>Configuration</b>	(Template-based policies only) View a summary of options configured for the scan policy. For more information, see <a href="#">Scan Policy Options</a> .
Options tabs	View all of the options configured for the scan policy. The tabs displayed depend on the scan policy type. For more information, see <a href="#">Scan Policy Options</a> .



## Edit a Scan Policy

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information, see [Scan Policies](#).

To edit a scan policy:

1. Log in to Tenable Security Center via the user interface.
2. Click **Scanning > Policies** (administrator users) or **Scans > Policies** (organizational users).

The **Policies** page appears.

3. Right-click the row for the scan policy you want to edit.

The actions menu appears.

-or-

Select the check box for the scan policy you want to edit.

The available actions appear at the top of the table.

4. Click **More > Edit**.

The **Edit Policy** page appears.

5. Modify the scan policy. For more information, see [Scan Policy Options](#).

6. Click **Submit**.

Tenable Security Center saves your configuration.



## Share or Revoke Access to a Scan Policy

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can share or revoke access to a scan policy to allow or restrict access to a user group. When you share a scan policy with a user group, users in the group with the appropriate permissions can use the policy in an active scan, modify policy options, and more.

For more information, see [Scan Policies](#). For more information about user groups, see [Groups](#).

To share or revoke access to a scan policy:

1. Log in to Tenable Security Center via the user interface.
2. Click **Scanning > Policies** (administrator users) or **Scans > Policies** (organizational users).

The **Policies** page appears.

3. Right-click the row for the scan policy for which you want to share or revoke access.

The actions menu appears.

-or-

Select the check box for the scan policy for which you want to share or revoke access.

The available actions appear at the top of the table.

4. Click **Share**.

The **Share Policy** window appears.

5. In the **Share Policy** window, select the groups for which you want to share or revoke access to the scan policy.

6. Click **Submit**.

Tenable Security Center saves your configuration.



## Export a Scan Policy

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

**Note:** Exported scan policies are not backwards-compatible. If you are running Tenable Security Center 6.0.0 or later and you export a scan policy, you can only import the scan policy into another instance of Tenable Security Center 6.0.0 or later.

You can export a scan policy as a .nessus file and import it to another Tenable Security Center to use in an active scan configuration.

In some cases, Tenable Support may also ask you to export a scan policy for troubleshooting.

**Note:** Exported scan policy files do not include audit files or credentials. You can re-configure audit files and credentials you want to use with the scan policy on the Tenable Security Center where you import the scan policy. For more information, see [Audit Files](#) and [Credentials](#).

For more information, see [Scan Policies](#).

Before you begin:

- Add a scan policy, as described in [Add a Scan Policy](#).
- Confirm your **PHP Serialization Mode** setting is set to **PHP Serialization ON**. For more information, see [Security Settings](#).

To export a scan policy:

1. Log in to Tenable Security Center via the user interface.
2. Click **Scanning > Policies** (administrator users) or **Scans > Policies** (organizational users).

The **Policies** page appears.

3. To export a single scan policy:
  - a. In the table, right-click the row for the scan policy you want to export.

The actions menu appears.

To export multiple scan policies:



- a. In the table, select the check box for each scan policy you want to export.

The available actions appear at the top of the table.

4. Click **Export**.

Tenable Security Center exports the scan policy as a .xml file.

What to do next:

- Do any of the following:
  - Import the scan policy into another Tenable Security Center, as described in [Import a Scan Policy](#).
  - If Tenable Support requested a scan policy file for troubleshooting, share the scan policy file with Tenable Support.



## Import a Scan Policy

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

You can import a .nessus scan policy file from Tenable Nessus or from another Tenable Security Center to use in an active scan configuration. For more information, see [Scan Policies](#).

**Note:** Imported scan policies do not include audit files or credentials. For more information, see [Audit Files](#) and [Credentials](#).

Before you begin:

- Ensure your **PHP Serialization Mode** setting is **PHP Serialization ON**. For more information, see [Security Settings](#).
- Do one of the following:
  - Export a scan policy from another Tenable Security Center, as described in [Export a Scan Policy](#).
  - Export a scan policy from Tenable Nessus. For more information, see [Policies](#) in the *Tenable Nessus User Guide*.

To import a scan policy:

1. Log in to Tenable Security Center via the user interface.
2. Click **Scanning > Policies** (administrator users) or **Scans > Policies** (organizational users).  
The **Policies** page appears.
3. At the top of the table, click **Upload Policy**.  
The **Upload Policy** page appears.
4. In the **Name** box, type a name for the scan policy.
5. (Optional) In the **Description** box, type a description for the scan policy.
6. (Optional) In the **Tag** box, type or select a tag for the scan policy.
7. Click **Choose File** and browse to the .nessus scan policy file you want to import.





8. Click **Submit**.

Tenable Security Center imports the scan policy.

What to do next:

- (Optional) Modify the scan policy settings, as described in [Edit a Scan Policy](#).
- (Optional) Configure audit files and credentials you wish to reference with the scan policy, as described in [Add a Custom Audit File](#) and [Add Credentials](#).
- Reference the scan policy in an active scan configuration, as described in [Add an Active Scan](#).



## Copy a Scan Policy

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information, see [Scan Policies](#).

To create a copy of a scan policy:

1. Log in to Tenable Security Center via the user interface.
2. Click **Scanning > Policies** (administrator users) or **Scans > Policies** (organizational users).

The **Policies** page appears.

3. To copy a single scan policy:
  - a. In the table, right-click the row for the scan policy you want to copy.

The actions menu appears.

To copy multiple scan policies:

- a. In the table, select the check box for each scan policy you want to copy.

The available actions appear at the top of the table.

4. Click **Copy**.

Tenable Security Center copies the scan policy. The copy appears, named **Copy of *PolicyName***.



## Delete a Scan Policy

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information, see [Scan Policies](#).

**Note:** If you delete a scan policy referenced by an active scan, Tenable Security Center disables the scan. For more information, see [Scan Result Statuses](#).

Before you begin:

- If any active scans reference the scan policy you intend to delete, update the active scans to use a different scan policy, as described in [Manage Active Scans](#).

To delete a scan policy:

1. Log in to Tenable Security Center via the user interface.
2. Click **Scanning > Policies** (administrator users) or **Scans > Policies** (organizational users).

The **Policies** page appears.

3. In the table, right-click the row for the scan policy you want to delete.

The actions menu appears.

4. Click **Delete**.

A confirmation window appears.

5. Click **Delete**.

Tenable Security Center deletes the scan policy.

To delete multiple scan policies:

1. Log in to Tenable Security Center via the user interface.
2. Click **Scanning > Policies** (administrator users) or **Scans > Policies** (organizational users).

The **Policies** page appears.

3. In the table, select the check box for each scan policy you want to delete.



The available actions appear at the top of the table.

4. At the top of the table, click **Delete**.

A confirmation window appears.

5. Click **Delete**.

Tenable Security Center deletes the scan policies.



## Agent Scanning

To perform agent scanning, Tenable Security Center fetches agent scan results from agent-capable Tenable Nessus Manager or Tenable Vulnerability Management instances. Using Tenable Nessus Agents for scanning reduces network usage and allows devices to maintain their scan schedules even when disconnected from the network. Tenable Security Center fetches these results for review with other acquired information about the host and network.

You can configure one or both methods of fetching agent scan results in Tenable Security Center:

- *Agent scans* fetch results from agent scans you add and launch in Tenable Security Center. When you add an agent scan in Tenable Security Center, Tenable Security Center creates a corresponding agent scan in an instance of Tenable Nessus Manager or Tenable Vulnerability Management that you linked to Tenable Security Center. When you launch an agent scan in Tenable Security Center, Tenable Security Center launches the corresponding scan in Tenable Nessus Manager or Tenable Vulnerability Management, then imports the results into Tenable Security Center.

You can create agent scans in Tenable Security Center using the Advanced Agent Scan template. For more information, see [Scan Policy Templates](#).

For more information, see [Agent Scans](#).

- *Agent synchronization jobs* fetch results from agent scans you previously created and launched in Tenable Nessus Manager or Tenable Vulnerability Management.

Agent synchronization jobs can fetch results from agent scans configured in Tenable Nessus Manager or Tenable Vulnerability Management using any agent scan template.

For more information, see [Agent Synchronization Jobs](#).

To configure agent scanning:

1. Configure Tenable Nessus Agents in either Tenable Nessus Manager or Tenable Vulnerability Management, as described in [Deployment Workflow](#) in the *Tenable Nessus Agent Deployment and User Guide*.
2. Add your agent-capable Tenable Nessus Manager or Tenable Vulnerability Management instance as a Tenable Nessus scanner in Tenable Security Center, as described in [Tenable](#)



---

### [Nessus Scanners.](#)

3. Add one or more agent repositories in Tenable Security Center, as described in [Add a Repository](#).
4. Do one or both of the following:
  - Add an agent scan using the Basic Agent Scan or Advanced Agent Scan template in Tenable Security Center, as described in [Add an Agent Scan](#).
  - Add an agent synchronization job in Tenable Security Center, as described in [Add an Agent Synchronization Job](#).

What to do next:

- View scan results, as described in [Scan Results](#).
- View vulnerability data by unique Agent ID, as described in [Vulnerability Analysis](#).



---

## Agent Scans

---

*Agent scans* fetch results from agent scans you add and launch in Tenable Security Center. When you add an agent scan in Tenable Security Center, Tenable Security Center creates a corresponding agent scan in an instance of Tenable Nessus Manager or Tenable Vulnerability Management that you linked to Tenable Security Center. When you launch an agent scan in Tenable Security Center, Tenable Security Center launches the corresponding scan in Tenable Nessus Manager or Tenable Vulnerability Management, then imports the results into Tenable Security Center.

You can create agent scans in Tenable Security Center using the Advanced Agent Scan template. For more information, see [Scan Policy Templates](#).

For more information about agent scanning in Tenable Security Center, see [Agent Scanning](#).

The **Agent Scans** page displays a list of all available agent scans. Tenable Security Center shares newly created agent scan import schedules to everyone within the same user group when users have the appropriate permissions.

When more than one agent scan result is ready on Tenable Vulnerability Management or Tenable Nessus Manager, the scan results queue for import to Tenable Security Center.

For more information about agent scans, see:

- [Add an Agent Scan](#)
- [Agent Scan Settings](#)
- [Manage Agent Scans](#)



## Add an Agent Scan

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can create agent scans in Tenable Security Center using the Advanced Agent Scan template. For more information, see [Scan Policy Templates](#).

For more information, see [Agent Scans](#) and [Agent Scan Settings](#).

Before you begin:

- Confirm you understand the complete agent scanning configuration process, as described in [Agent Scanning](#).
- (Optional) Configure an Advanced Agent Scan policy template, as described in [Add a Scan Policy](#).

To add an agent scan:

1. Log in to Tenable Security Center via the user interface.
2. Click **Scans > Agent Scans**.  
The **Agent Scans** page appears.
3. At the top of the table, click **Add**.  
The **Add Agent Scan** page appears.
4. Click **General**.
5. Type a **Name** for the scan.
6. (Optional) Type a **Description** for the scan.
7. (Optional) To reference an Advanced Agent Scan policy in the scan:
  - a. Click **Custom Policy** to enable the toggle.
  - b. In the **Policy** drop-down menu, select the Advanced Agent Scan policy.
8. Select an **Agent Scanner**.





9. Select one or more **Agent Groups**.
10. Select a **Scan Window**.
11. (Optional) Select a **Schedule** for the scan.
12. Click **Settings**.
13. Select an **Import Repository** for the scan.
14. (Optional) Click **Post Scan**.
  - If you want to configure automatic report generation, click **Add Report**. For more information, see [Add a Report to a Scan](#).
15. Click **Submit**.

Tenable Security Center saves your configuration.

What to do next:

- View scan results, as described in [Scan Results](#).
- View vulnerability data by unique Agent ID, as described in [Vulnerability Analysis](#).



## Manage Agent Scans

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information about agent scans, see [Agent Scans](#).

To manage agent scans:

1. Log in to Tenable Security Center via the user interface.
2. Click **Scans > Agent Scans**.

The **Agent Scans** page appears.

3. To filter the scans that appear on the page, apply a filter as described in [Apply a Filter](#).
4. To start or pause a scan, see [Start or Pause a Scan](#).

5. To view details for a scan:

- a. Right-click the row for the scan.

The actions menu appears.

-or-

Select the check box for the scan.

The available actions appear at the top of the table.

- b. Click **View**.

The **View Agent Scan** page appears.

6. To edit a scan:

- a. Right-click the row for the scan.

The actions menu appears.

-or-

Select the check box for the scan.



The available actions appear at the top of the table.

- b. Click **Edit**.

The **Edit Agent Scan** page appears.

- c. Modify the scan options. For more information, see [Agent Scan Settings](#).
- d. Click **Submit**.

Tenable Security Center saves your configuration.

## 7. To delete a scan:

- a. Right-click the row for the scan.

The actions menu appears.

-or-

Select the check box for the scan.

The available actions appear at the top of the table.

- b. Click **Delete**.

Tenable Security Center deletes the scan.

## 8. To delete multiple scans:

- a. In the table, select the check box for each scan you want to delete.

The available actions appear at the top of the table.

- b. At the top of the table, click **Delete**.

A confirmation window appears.

- c. Click **Delete**.

Tenable Security Center deletes the scans.



## Start or Pause a Scan

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

To start or pause an active scan, agent scan, or agent synchronization job:

1. Log in to Tenable Security Center.
2. Click one of the following:
  - **Scans > Active Scans** (to manage active scans)
  - **Scans > Agent Synchronization Jobs** (to manage agent synchronization jobs)
  - **Scans > Agent Scans** (to manage agent scans)
  - **Scans > Scan Results** (to manage a scan from the results page).
3. Do one of the following:
  - To pause the scan or synchronization job, select the check box for the scan or synchronization job, and click **Pause** at the top of the table.
  - To start the scan or synchronization job, select the check box for the scan or synchronization job, and click **Launch** at the top of the table.



# Agent Scan Settings

For more information, see [Agent Scans](#).

- [General Options](#)
- [Settings Options](#)
- [Post Scan Options](#)

## General Options

Parameter	Description	Default
<b>General</b>		
<b>Name</b>	The scan name associated with the scan's results. This may be any name or phrase (for example, <b>SystemA</b> , <b>DMZ Scan</b> , or <b>Daily Scan of the Web Farm</b> ).	--
<b>Description</b>	Descriptive information related to the scan.	--
<b>Custom Policy</b>	When enabled, select an agent scan policy to apply to the scan. For more information, see <a href="#">Scan Policy Templates</a> .  When disabled, the scan uses a Tenable Nessus or Tenable Vulnerability Management Basic Agent Scan template. For more information, see <a href="#">Agent Scan and Policy Templates</a> in the <i>Tenable Nessus Agent Deployment and User Guide</i> and <a href="#">Tenable-Provided Agent Templates</a> in the <i>Tenable Vulnerability Management User Guide</i> .	Disabled
<b>Policy</b>	(If <b>Custom Policy</b> is enabled) The name of the agent scan policy.	--
<b>Agent Scanner</b>	The Agent-enabled scanner from which to retrieve agent results.	--
<b>Agent Groups</b>	Specifies the agent group or groups in Tenable Nessus Manager you want the scan to target. For more information, see	--



Parameter	Description	Default
	<a href="#">Agent Groups</a> in the <i>Tenable Nessus User Guide</i> .	
<b>Scan Window</b>	<p>Specifies the amount of time Tenable Security Center waits before fetching the results of the agent scan: <b>15 minutes, 30 minutes, 1 hour, 3 hours, 6 hours, 12 hours, or 1 day</b>.</p> <p>If Tenable Security Center fetches results for the scan before the scan completes, Tenable Security Center displays the results available at the time the scan window expired. The agent scan continues to run in Tenable Vulnerability Management or Tenable Nessus Manager during the scan window specified in Tenable Vulnerability Management or Tenable Nessus Manager, even if the scan window in Tenable Security Center expires.</p> <div style="border: 1px solid blue; padding: 5px;"><p><b>Note:</b> To view complete agent scan result data in Tenable Security Center, Tenable recommends setting a <b>Scan Window</b> value that allows your agent scans to complete before Tenable Security Center fetches the results.</p></div>	1 hour
<b>Schedule</b>		
<b>Schedule</b>	<p>The frequency you want Tenable Security Center to fetch agent scan results: <b>Now, Remediation, Once, Daily, Weekly, Monthly, or On Demand</b>.</p> <div style="border: 1px solid blue; padding: 5px;"><p><b>Note:</b> If you schedule your scan to repeat monthly, Tenable recommends setting a start date no later than the 28th day. If you select a start date that does not exist in some months (e.g., the 29th), Tenable Security Center cannot run the scan on those days.</p></div> <div style="border: 1px solid green; padding: 5px;"><p><b>Tip:</b> Retrieve agent scan results as close to the completion time of the scan as possible to most accurately display within Tenable Security Center when the scan discovered the vulnerability results.</p></div>	On Demand



## Settings Options

Parameter	Description	Default
<b>Import Repository</b>	<p>Specifies the repository where you want the agent scan results to import. Select an agent repository to receive scan data.</p> <div style="border: 1px solid #0070C0; padding: 5px;"><p><b>Note:</b> You cannot import agent scan data to a non-agent repository.</p></div>	--

## Post Scan Options

These options determine what actions occur immediately before and after the agent scan completes.

Option	Description	Default
<b>Add Report</b>	<p>This option provides a list of reports available to the user to run when the agent scan data import completes. For more information, see <a href="#">Add a Report to a Scan</a>.</p>	--



---

## Agent Synchronization Jobs

---

*Agent synchronization jobs* fetch results from agent scans you previously created and launched in Tenable Nessus Manager or Tenable Vulnerability Management. Agent synchronization jobs can fetch results from agent scans configured in Tenable Nessus Manager or Tenable Vulnerability Management using any agent scan template. For more information about agent scanning in Tenable Security Center, see [Agent Scanning](#).

The **Agent Synchronization Jobs** page displays a list of all available agent synchronization jobs. Tenable Security Center shares newly created agent scan import schedules to everyone within the same user group when users have the appropriate permissions.

When more than one agent scan result is ready on Tenable Nessus Manager, the scan results queue for import to Tenable Security Center.

For more information about agent synchronization jobs, see:

- [Add an Agent Synchronization Job](#)
- [Agent Synchronization Job Settings](#)
- [Manage Agent Synchronization Jobs](#)





## Add an Agent Synchronization Job

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information about agent synchronization jobs, see [Agent Synchronization Jobs](#). For more information about agent synchronization job options, see [Agent Synchronization Job Settings](#).

Before you begin:

- Confirm you understand the complete agent scanning configuration process, as described in [Agent Scanning](#).

To add an agent synchronization job:

1. Log in to Tenable Security Center via the user interface.
2. Click **Scans > Agent Synchronization Jobs**.  
The **Agent Synchronization Jobs** page appears.
3. At the top of the table, click **Add**.  
The **Add Agent Synchronization Job** page appears.
4. Click **General**.
5. Type a **Name** for the agent synchronization job.
6. (Optional) Type a **Description** for the agent synchronization job.
7. Select an **Agent Scanner**.
8. Type an **Agent Scan Name Filter**.
9. (Optional) If you want to limit the scan results fetched by Tenable Security Center, enable **Scan Result Threshold** and select a date and time to specify the oldest scan results you want Tenable Security Center to fetch.
10. (Optional) Select a **Schedule** for the agent synchronization job.
11. Click **Settings**.
12. Select an **Import Repository** for the agent synchronization job.



13. (Optional) Click **Post Scan**.

- If you want to configure automatic report generation, click **Add Report**. For more information, see [Add a Report to a Scan](#).
- If you previously added an email address to your account profile and you want to configure email notifications, enable or disable **E-Mail Me on Launch** or **E-Mail Me on Completion**.

14. Click **Submit**.

Tenable Security Center saves your configuration.

What to do next:

- View scan results, as described in [Scan Results](#).
- View vulnerability data by unique Agent ID, as described in [Vulnerability Analysis](#).



## Manage Agent Synchronization Jobs

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information, see [Agent Synchronization Jobs](#).

To manage agent synchronization jobs:

1. Log in to Tenable Security Center via the user interface.
2. Click **Scans > Agent Synchronization Jobs**.

The **Agent Synchronization Jobs** page appears.

3. To filter the agent synchronization jobs that appear on the page, apply a filter as described in [Apply a Filter](#).
4. To start or pause an agent synchronization job, see [Start or Pause a Scan](#).
5. To view details for an agent synchronization job:
  - a. Right-click the row for the agent synchronization job.  
The actions menu appears.  
  
-or-  
  
Select the check box for the agent synchronization job.  
  
The available actions appear at the top of the table.
  - b. Click **View**.  
  
The **View Agent Synchronization Job** page appears.
6. To edit an agent synchronization job:
  - a. Right-click the row for the agent synchronization job.  
The actions menu appears.  
  
-or-



---

Select the check box for the agent synchronization job.

The available actions appear at the top of the table.

- b. Click **Edit**.

The **Edit Agent Synchronization Job** page appears.

- c. Modify the agent synchronization job options. For more information, see [Agent Synchronization Job Settings](#).
- d. Click **Submit**.

Tenable Security Center saves your configuration.

## 7. To copy an agent synchronization job:

- a. Right-click the row for the agent synchronization job.

The actions menu appears.

-or-

Select the check box for the agent synchronization job.

The available actions appear at the top of the table.

- b. Click **Copy**.

Tenable Security Center creates a copy of the agent synchronization job.

## To copy multiple agent synchronization jobs:

- a. In the table, select the check box for each agent synchronization job you want to copy.

The available actions appear at the top of the table.

- b. At the top of the table, click **Copy**.

Tenable Security Center creates a copy of the agent synchronization job.

## 8. To delete an agent synchronization job:

- a. Right-click the row for the agent synchronization job.

The actions menu appears.



-or-

Select the check box for the agent synchronization job.

The available actions appear at the top of the table.

- b. Click **Delete**.

Tenable Security Center deletes the agent synchronization job.

To delete multiple agent synchronization jobs:

- a. In the table, select the check box for each agent synchronization job you want to delete.

The available actions appear at the top of the table.

- b. At the top of the table, click **Delete**.

A confirmation window appears.

- c. Click **Delete**.

Tenable Security Center deletes the scans.



# Agent Synchronization Job Settings

For more information, see [Agent Synchronization Jobs](#).

- [General Options](#)
- [Settings Options](#)
- [Post Scan Options](#)

## General Options

Option	Description
<b>Name</b>	The agent synchronization job name associated with the scan's results. This may be any name or phrase (e.g., <b>SystemA</b> , <b>DMZ Scan</b> , <b>Daily Scan of the Web Farm</b> , etc.).
<b>Description</b>	A description for the agent synchronization job.
<b>Agent Scanner</b>	The agent-capable scanner from which you want Tenable Security Center to retrieve agent results.
<b>Agent Scan Name Filter</b>	<p>A filter for agent scan results to retrieve from the Tenable Nessus Agent-enabled scanner. Filters can use the specific name of the result(s) to retrieve or an asterisk (*) or question mark (?) for all or part of the scan result name(s) to retrieve. You can find the available agent scans retrieved from the selected scanner on the Scan page of the user logged in to the Nessus server.</p> <p>You can click the <b>Preview Filter</b> button to view results that match the filter.</p>
<b>Scan Result Threshold</b>	<p>Specifies whether Tenable Security Center fetches all or some agent scan results from the agent-capable scanner.</p> <ul style="list-style-type: none"><li>• When disabled, Tenable Security Center fetches all agent scan results.</li><li>• When enabled, Tenable Security Center restricts the agent scan results it fetches.</li></ul> <div style="border: 1px solid blue; padding: 5px;"><p><b>Note:</b> You cannot modify the Scan Result Threshold after initial creation of the agent synchronization job.</p></div>



Option	Description
	After you create the agent synchronization job, the <b>Edit Agent Synchronization Job</b> and <b>View Agent Synchronization Job</b> pages display the <b>Last Fetched</b> date to indicate when Tenable Security Center performed the most recent successful agent synchronization job.
<b>Select Date and Time</b>	When <b>Scan Result Threshold</b> is enabled, specifies the oldest agent scan results you want Tenable Security Center to fetch.
<b>Schedule</b>	<p>The frequency you want Tenable Security Center to fetch agent scan results. Select <b>Now</b>, <b>Once</b>, <b>Daily</b>, <b>Weekly</b>, <b>Monthly</b>, <b>On Demand</b>, or <b>Dependent</b> to create an agent scan result retrieval template that you can launch manually at any time. The other time frames allow you to retrieve agent scan results at specified times and intervals.</p> <p>Tenable recommends retrieving agent scan results as close to the completion time of the scan as possible to most accurately display within Tenable Security Center when the scan discovered the vulnerability results. For more information about how Tenable Security Center determines vulnerability discovery dates, see <a href="#">Vulnerability Discovered</a>.</p> <div style="border: 1px solid blue; padding: 5px;"><p><b>Note:</b> If you schedule your scan to repeat monthly, Tenable recommends setting a start date no later than the 28th day. If you select a start date that does not exist in some months (e.g., the 29th), Tenable Security Center cannot run the scan on those days.</p></div>

## Settings Options

Parameter	Description
<b>Import Repository</b>	<p>Specifies the agent repository where you want the agent scan results to import.</p> <div style="border: 1px solid blue; padding: 5px;"><p><b>Note:</b> You cannot import agent scan data to a non-agent repository.</p></div>

## Post Scan Options



These options determine what actions occurs immediately before and after the agent synchronization job completes. The table below describes the post agent synchronization job options available to users:

Option	Description
<b>Add Report</b>	<p>This option provides a list of reports available to the user to run when the agent scan data import completes.</p> <p>The initial choices are to click the group and owner of the report to present a list of valid report options. Next, click the report from the list that can be searched using the text search box. When hovering over a report name, you can select the information icon to display the name and description of the report. You can base the generated report on the current scan's results or the results in the Cumulative database.</p> <p>Selecting the check mark causes the report to launch once the agent synchronization job completes. Selecting the <b>X</b> removes the changes. Once added, you can modify or delete the report information.</p>





## Freeze Windows

You can set a freeze window in Tenable Security Center to specify a time frame when you do not want Tenable Security Center to scan specific targets. This prevents remediation or ad-hoc scans from scanning assets during undesired time frames, such as during production hours. For more information about what happens to in-progress scans at the start of a freeze window, see the [knowledge base](#) article.

Freeze windows are organizational and affect all scans in the creating user's organization. Only users with the Manage Freeze Windows permission can add, edit, or delete freeze windows.

**Note:** If you configure a freeze window in Tenable Security Center, it will not stop Agent scans. To stop Agent scans, configure a freeze window in each Tenable Nessus Manager.

For more information, see [Add a Freeze Window](#), [Edit a Freeze Window](#), and [Delete a Freeze Window](#).

Option	Description
<b>Name</b>	A name for the freeze window.
<b>Description</b>	(Optional) A description for the freeze window.
<b>Enabled</b>	<p>When enabled, Tenable Security Center does not scan any assets that are affected by the freeze window. If a scan does not include any assets outside of the freeze window, then the scan will abort.</p> <p>When disabled, Tenable Security Center scans all assets as scheduled.</p>
<b>Targets</b>	<p>Specifies the targets you do not want to scan during the freeze window.</p> <ul style="list-style-type: none"><li>• <b>All Systems</b> —Tenable Security Center does not scan any assets.</li><li>• <b>Assets</b> —Tenable Security Center does not scan specific Tenable-provided or user-defined asset lists.</li><li>• <b>IPs</b> —Tenable Security Center does not scan specific IP addresses.</li><li>• <b>Mixed</b> —Tenable Security Center does not scan a combination of</li></ul>



Option	Description
	<p>IP addresses and/or Tenable-provided or user-defined asset lists.</p> <div data-bbox="493 363 1479 596" style="border: 1px solid blue; padding: 5px;"><p><b>Note:</b> If you select an <b>Import Repository</b> later in the configuration, Tenable Security Center applies your <b>Target</b> selections only to scans configured with that import repository. Scans configured with other import repositories still run and scan targeted assets, regardless of your freeze window <b>Targets</b> selection.</p></div>
<b>Assets</b>	If you selected <b>Assets</b> or <b>Mixed</b> as the <b>Targets</b> , specifies one or more Tenable-provided or user-defined asset lists that you do not want to scan during the freeze window.
<b>IPs</b>	If you selected <b>IPs</b> or <b>Mixed</b> as the <b>Targets</b> , specifies one or more asset IP addresses that you do not want to scan during the freeze window.
<b>ImportRepository</b>	<p>(Optional) If you selected <b>Assets</b>, <b>IPs</b>, or <b>Mixed</b> as your <b>Targets</b>, specifies whether you want to restrict the freeze window to apply to scans configured with a specific import repository.</p> <ul data-bbox="537 1150 1442 1356" style="list-style-type: none"><li>• If you select a repository, Tenable Security Center applies the freeze window to scans with the repository configured.</li><li>• If you do not select a repository, Tenable Security Center does not restrict the freeze by repository.</li></ul>
<b>Starts On</b> <b>Frequency</b> <b>Repeat Every</b> <b>Repeat On</b>	Specifies a schedule for the freeze window.



## Add a Freeze Window

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information about configuration options, see [Freeze Windows](#).

To add a freeze window:

1. Log in to Tenable Security Center via the user interface.
2. Click **Scans > Freeze Windows**.

The **Freeze Windows** page appears.

3. At the top of the table, click **Add**.

The **Add Freeze Window** page appears.

4. In the **Name** box, type a name for the freeze window.
5. In the **Description** box, type a description for the freeze window.
6. Confirm the **Enabled** toggle is enabled.
7. In the **Targets** drop-down box, select a target: **All Systems**, **Assets**, **IPs**, or **Mixed**.

Additional options appear based on the targets you specified.

8. In the **Assets** and/or **IPs** boxes, select or type targets for the freeze window.
9. (Optional) If you selected **Assets** or **Mixed** as the **Targets** and you want to restrict the freeze window by scan repository, in the **Repository** section, select a repository.
10. Modify the **Starts On**, **Frequency**, **Repeat Every**, and **Repeat On** options to set the schedule for the freeze window.
11. Click **Submit**.

Tenable Security Center saves your configuration.



## Edit a Freeze Window

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information, see [Freeze Windows](#).

To edit a freeze window:

1. Log in to Tenable Security Center via the user interface.
2. Click **Scans > Freeze Windows**.

The **Freeze Windows** page appears.

3. Right-click the row for the freeze window you want to edit.

The actions menu appears.

-or-

Select the check box for the freeze window you want to edit.

The available actions appear at the top of the table.

4. Click **Edit**.

The **Edit Freeze Window** page appears.

5. To disable the freeze window, click the **Enabled** slider.
6. To edit the freeze window settings, modify options described in [Edit a Freeze Window](#).
7. Click **Submit**.

Tenable Security Center saves your configuration.



---

## Delete a Freeze Window

---

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information, see [Freeze Windows](#).

To delete a freeze window:

1. Log in to Tenable Security Center via the user interface.
2. Click **Scans > Freeze Windows**.

The **Freeze Windows** page appears.

3. To delete a single freeze window:
  - a. In the table, right-click the row for the freeze window you want to delete.

The actions menu appears.

To delete multiple freeze windows:

- a. In the table, select the check box for each freeze window you want to delete.

The available actions appear at the top of the table.

4. Click **Delete**.

A confirmation window appears.

5. Click **Delete**.

Tenable Security Center deletes the freeze window.



---

## Tags

---

You can use tags in Tenable Security Center to label assets, policies, credentials, or queries with a custom descriptor to improve filtering and object management. For example, you could add a tag named **East Coast Employees** to label all of your assets in that geographic area.

After you create a tag and apply it to an object, the tag is visible to all users who can view or modify that object. However, tags are not shared across object types.

For more information, see [Add a Tag](#) and [Remove or Delete a Tag](#).



## Add a Tag

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information, see [Tags](#).

To add a tag:

1. Log in to Tenable Security Center.
2. Navigate to the assets, policies, credentials, or queries page:
  - Click **Assets** > **Assets**.
  - Click **Scanning** > **Policies** (administrator users) or **Scans** > **Policies** (organizational users).
  - Click **Scanning** > **Credentials** (administrator users) or **Scans** > **Credentials** (organizational users).
  - Click **Analysis** > **Queries**.

3. Right-click the row for the asset, policy, credential, or query you want to tag.

The actions menu appears.

-or-

Select the check box for the asset, policy, credential, or query you want to tag.

The available actions appear at the top of the table.

4. Click **Edit**.
5. In the **Tag** drop-box, select an existing tag or type a new tag.
6. Click **Submit**.

The tag appears, applied to the asset, policy, credential, or query.



## Remove or Delete a Tag

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

You can remove a tag from an asset, policy, credential, or query to stop associating that object with the tag. To completely delete a tag from Tenable Security Center, you must remove the tag from all assets, policies, credentials, or queries. For more information, see [Tags](#).

To remove a tag or completely delete a tag from Tenable Security Center:

1. Log in to Tenable Security Center via the user interface.
2. Navigate to the assets, policies, credentials, or queries page:
  - Click **Assets > Assets**.
  - Click **Scanning > Policies** (administrator users) or **Scans > Policies** (organizational users).
  - Click **Scanning > Credentials** (administrator users) or **Scans > Credentials** (organizational users).
  - Click **Analysis > Queries**.
3. In the table, right-click the row for the asset, policy, credential, or query where you want to remove the tag.

The actions menu appears.

4. Click **Edit**.
5. In the **Tag** drop-box, remove the tag from the asset, policy, credential, or query.
6. Click **Submit**.

Tenable Security Center removes the tag from the asset, policy, credential, or query.

7. (Optional) If you want to delete the tag from Tenable Security Center, repeat steps 2 through 6 until you have removed all uses of the tag for the object type.

Tenable Security Center deletes the tag.





## Analyze Data

See the following sections to analyze and respond to Tenable Security Center data.

Analysis Tool	Description
<a href="#">Scan Results</a>	View a table of scan results from active and agent scans.
<a href="#">Dashboards</a>	View graphical summaries of scans, scan results, and system activity.
<a href="#">Solutions Analysis</a>	View recommended solutions for all vulnerabilities on your network.
<a href="#">Vulnerability Analysis</a>	View a table of cumulative or mitigated vulnerability data.
<a href="#">Event Analysis</a>	View a table of Tenable Log Correlation Engine security event data.
<a href="#">Mobile Analysis</a>	View a table of vulnerability data discovered by scanning an ActiveSync, Apple Profile Manager, AirWatch, Good, or MobileIron MDM server.
<a href="#">Reports</a>	Create custom or template-based reports to export Tenable Security Center data for further analysis.
<a href="#">Assurance Report Cards</a>	Create ARCs to develop security program objectives and assess your organization's security posture.

You can use [Filters](#) and [Queries](#) to manipulate the data you see in analysis tools and save views for later access. You can perform [Workflow Actions](#) (alerting, ticketing, accepting risk, recasting risk) from some analysis tools.

If you are licensed for Tenable Lumin, you can synchronize Tenable Security Center with Tenable Lumin to take advantage of Cyber Exposure features, as described in [Tenable Lumin Synchronization](#). For more information, contact your Tenable representative.



# Dashboards

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

Administrator users can view Tenable-provided **Overview** and **LCE Overview** dashboards. For more information, see [Overview Dashboard](#) and [LCE Overview Dashboard](#).

Organizational users can configure custom or template-based *dashboards* that contain *dashboard components*, which display vulnerability, event, ticket, user, and alert data for analysis. When viewing vulnerability or event data, you can drill into the underlying dataset for further evaluation.

**Tip:** Tenable provides many dashboard templates (for example, the VPR Summary dashboard). For a complete index of Tenable-provided dashboard templates, see the [Tenable Security Center Dashboards](#) blog.

Dashboards allow you to organize similar dashboard components to streamline your analysis. Instead of creating a single dashboard with several dozen dashboard components, you can create several dashboards that group similar dashboard components together. For example, you can create two separate dashboards to view active scanning data and passive scanning data.

**Note:** Dashboards display vulnerability, event, and other scan data. Tenable recommends configuring several data sources to optimize the data you see in dashboards. For more information, see [Scanning Overview](#).

**Tip:** Tenable Security Center automatically refreshes dashboard data once per day. To refresh all dashboard components on demand as an organizational user, click **Refresh All**.

For more information, see:

- [View a Dashboard](#)
- [Add a Template-Based Dashboard](#)
- [Add a Custom Dashboard](#)
- [Import a Dashboard](#)
- [Manage Dashboards](#)
- [Manage Dashboard Components](#)



## Dashboard Options

Option	Description
<b>General</b>	
<b>Name</b>	The name of the dashboard.
<b>Description</b>	(Optional) A description for the dashboard.
<b>Layout</b>	The number and arrangement of dashboard columns.



## View a Dashboard

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information, see [Dashboards](#).

To view a dashboard:

1. Log in to Tenable Security Center via the user interface.
2. Click **Dashboard > Dashboard**.

The **Dashboards** page appears, displaying your default dashboard.

3. If you want to switch to a different dashboard:
  - a. In the upper-right corner of the page, click the **Switch Dashboard** drop-down box.
  - b. Click the dashboard you want to view.

The dashboard appears.

If you are an organizational user, you can:

- Add a dashboard component to the dashboard in view, as described in [Add a Template-Based Dashboard Component](#) or [Add a Custom Dashboard Component](#).
- Manage dashboard components on the dashboard in view, as described in [Manage Dashboard Components](#).
- Edit the dashboard settings for the dashboard in view, as described in [Edit Settings for a Dashboard](#).
- Share or revoke access to the dashboard in view, as described in [Share or Revoke Access to a Dashboard](#).
- Create a report from the dashboard in view:



- a. In the upper-right corner of the page, click the **Options** drop-down box.
- b. Click **Send to Report**.

For more information about reports, see [Reports](#).

- Delete the dashboard in view, as described in [Delete a Dashboard](#).
- Customize the table, as described in [Interact with a Customizable Table](#).



# Overview Dashboard

Tenable provides the **Overview** dashboard to administrator users by default. For more information, see [View a Dashboard](#).

Widget	Action
<b>Licensing Status</b> How close am I to hitting my license limit?	View a graph of your total license size compared to your total currently active IP addresses.
<b>Repository Statistics</b> How am I using my repositories?	View information about your repositories: <ul style="list-style-type: none"><li>• <b>Name</b> —The name of the repository.</li><li>• <b>Vuln Count</b> —The number of vulnerability instances in the repository.<div data-bbox="683 926 1479 1079" style="border: 1px solid green; padding: 5px;"><p><b>Tip:</b> A vulnerability instance is a single instance of a vulnerability appearing on an asset, identified uniquely by plugin ID, port, and protocol.</p></div></li><li>• <b>Last Update</b> —The date and time of the most recent scan that updated the repository data.</li><li>• <b>IP/Device Count</b> —The number of IP addresses in the repository counting toward your Tenable Security Center license.</li><li>• <b>Type</b> —The repository type.</li><li>• <b>Data Format</b> —The type of data stored in the repository: <b>IPv4</b>, <b>IPv6</b>, <b>Mobile</b>, or <b>Agent</b>.</li></ul>
<b>System Status</b> Is the Tenable Security Center job daemon running?	<ul style="list-style-type: none"><li>• View the status of the job daemon, which powers the job queue.</li><li>• To change the status of the job daemon, click <b>Start</b> or <b>Stop</b>.</li></ul> <p>Tenable Security Center changes the status of the job</p>



Widget	Action
	daemon.
<p><b>Scanner Status</b></p> <p>What is the status of my scanners?</p>	<p>View information about your scanners:</p> <ul style="list-style-type: none"><li>• <b>Name</b> —The name of the scanner or instance.</li><li>• <b>Type</b> —The type of connection: <b>Passive</b> or <b>Active</b>.</li><li>• <b>Status</b> —The status of the scanner or instance.</li></ul>
<p><b>Latest Plugins</b></p> <p>What plugins were most recently changed in a feed update?</p>	<p>View information about the latest plugin changes in feed updates.</p> <ul style="list-style-type: none"><li>• <b>ID</b> —The plugin ID.</li><li>• <b>Name</b> —The name of the plugin.</li><li>• <b>Family</b> —The plugin family.</li><li>• <b>Type</b> —The plugin type.</li><li>• <b>Date</b> —The date and time of the feed update that contained the plugin change.</li></ul>



## Health Overview Dashboard

Tenable provides the **Health Overview** dashboard to administrator users by default. For more information, see [View a Dashboard](#).

Widget	Action
<p><b>Application Configuration Health</b></p> <p>What is the health of my application configuration?</p>	<p>View information about the health of your application with the following checks:</p> <ul style="list-style-type: none"><li>• <b>License Expiration Warning</b> —When a Tenable Security Center license expires, you may not be able to update plugins, receive Feed updates or access the tool.</li><li>• <b>Percent Licenses Used</b> —When a Tenable Security Center console reaches its license limit, scans of additional assets will not be imported.</li><li>• <b>SMTP Configured</b> —If misconfigured, invalid SMTP settings will prevent Tenable Security Center from being able to send emails notifying users of events.</li><li>• <b>Maximum Recommended LCE Imports Per Day (200)</b> —Tenable Log Correlation Engine job imports should be managed to reduce impact on other scan imports.</li><li>• <b>Maximum Recommended NNM Imports Per Day (200)</b> —Nessus Network Monitor job imports should be managed to reduce impact on other scan imports.</li><li>• <b>Maximum Recommended Nessus Scanners (250)</b> —You may experience degraded performance when a large quantity of Nessus Scanners are attached to Tenable Security Center.</li><li>• <b>Maximum Recommended Repositories (200)</b> —You may experience degraded performance when a large quantity of Repositories are configured in Tenable Security Center. See the <a href="#">Tenable Security Center Large Enterprise Deployment Guide</a> for more information.</li></ul>





Widget	Action
	<ul style="list-style-type: none"><li>• <b>Maximum Recommended Scan Zones (100)</b>—You may experience degraded performance when a large quantity of Scan Zones are configured in Tenable Security Center. See the <a href="#">Tenable Security Center Large Enterprise Deployment Guide</a> for more information.</li><li>• <b>Passive Activation Code Configured</b> (Requires Tenable Security Center+ license)—Tenable Security Center+ consoles should have a passive activation code applied. This allows usage of Nessus Network Monitor Sensors for more than Asset Discovery.</li></ul>
<b>Repository Size Warning</b>  What is the size of each of my repositories?	View information about the size of your repositories.
<b>Job Queue Health Summary</b>  What is the health of my job queue?	View information about the health of your job queue: <ul style="list-style-type: none"><li>• <b>Job Delay</b>—Jobs that have been delayed by more than an hour since their scheduled run time.</li><li>• <b>Pending Jobs</b>—Jobs that are scheduled to run in the future. If too many jobs are scheduled, you may experience delays in processing vulnerability data, generating reports, or other processes.</li></ul>
<b>Refine Scan Zone Scope</b>  What is the size of each of my scan zones?	View information about the size of your scan zones.
<b>Job Queue Delay</b>	View information about delays in the job queue.



Widget	Action
<b>Details</b>  Why were there delays in the job queue?	
<b>Scan Zones with Overlap</b>  Do I have scan zones that overlap each other?	View information about the size of your scan zones, and whether they have overlapping boundaries.
<b>Non-Working Scanners</b>  Are there any non-working scanners in my configuration?	View information about non-working scanners in your scan zones.
<b>Maximum Recommended Scanners in a Zone</b>  What is the maximum number of scanners I should have in my scan zones?	View information about the maximum suggested number of scanners for each of your scan zones.
<b>Nessus Agent Managers as Network Scanners</b>  Are there any Nessus Agent Managers being used as Network Scanners?	View a list of Nessus Agent Managers currently configured to use as Network Scanners.
<b>Degraded Scan Zones</b>  Which scan zones have	View information about scan zones with non-working scanners.



Widget	Action
non-working scanners?	
<b>Nessus Agent Managers Not Using API Authentication</b>  Are there any Nessus Agent Managers not configured to use API authentication?	View a list of Nessus Agent Managers not configured to use API keys.



## LCE Overview Dashboard

Tenable provides the **LCE Overview** dashboard to administrator users by default. For more information, see [View a Dashboard](#).

Widget	Action
<p><b>LCE Status</b></p> <p>What is the status of my Tenable Log Correlation Engine servers?</p>	<p>View information about your Tenable Log Correlation Engine server:</p> <ul style="list-style-type: none"><li>• <b>Name</b> —The name of the Tenable Log Correlation Engine server.</li><li>• <b>Status</b> —The status of the Tenable Log Correlation Engine server.</li></ul>
<p><b>LCE Client Status</b></p> <p>What is the status of my Tenable Log Correlation Engine clients?</p>	<p>View information about your Tenable Log Correlation Engine clients:</p> <ul style="list-style-type: none"><li>• <b>Client IP</b> —The IP address of the Tenable Log Correlation Engine client.</li><li>• <b>LCE</b> —The Tenable Log Correlation Engine server associated with the Tenable Log Correlation Engine client.</li><li>• <b>Last Update</b> —The date and time of the most recent Tenable Log Correlation Engine client import to Tenable Security Center.</li><li>• <b>Status</b> —The status of the Tenable Log Correlation Engine client.</li></ul>



## Set a Dashboard as Your Default Dashboard

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information, see [Dashboards](#).

To set a dashboard as your default dashboard:

1. Log in to Tenable Security Center via the user interface.
2. Click **Dashboard > Dashboard**.

The **Dashboards** page appears, displaying your default dashboard.

3. If you want to switch to a different dashboard:
  - a. In the upper-right corner of the page, click the **Switch Dashboard** drop-down box.
  - b. Click the dashboard you want to view.

The dashboard appears.

4. In the upper-right corner of the page, click the **Options** drop-down box.
5. Click **Set as Default**.

The system sets the dashboard as your default.



## Add a Template-Based Dashboard

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can add a dashboard by configuring a Tenable-provided dashboard template. To add a custom dashboard instead, see [Add a Custom Dashboard](#). To import a dashboard, see [Import a Dashboard](#).

For more information, see [Dashboards](#) and [Dashboard and Component Templates](#).

To add a template-based dashboard:

1. Log in to Tenable Security Center via the user interface.

2. Click **Dashboard > Dashboard**.

The **Dashboards** page appears.

3. In the upper-right corner of the page, click the **Options** drop-down button.

4. Click **Add Dashboard**

The **Dashboard Templates** page appears.

5. In the **Common** section, click a template category tile.

The **Add Dashboard Template** page appears.

6. Click a template.

The **Add Dashboard Template** page updates to reflect the template you selected.

7. Modify the dashboard template:

- To edit the dashboard name, click the name box and edit the name.
- To edit the dashboard description, click the **Description** box and edit the description.
- To restrict the target data displayed in the dashboard, click the **Targets** drop-down box.
- To edit the dashboard refresh schedule, click the **Schedule** link.

8. Click **Add**.

Tenable Security Center saves your configuration and the **Dashboards** page appears.



9. In the upper-right corner of the page, click the **Switch Dashboard** drop-down box.
10. Click the name of the dashboard you just created.

The page for the dashboard appears.

What to do next:

- Add dashboard components, as described in [Add a Template-Based Dashboard Component](#) or [Add a Custom Dashboard Component](#).



## Add a Custom Dashboard

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can add a fully customized dashboard. To add a dashboard from a Tenable-provided template instead, see [Add a Template-Based Dashboard](#).

For more information, see [Dashboards](#).

To add a custom dashboard:

1. Log in to Tenable Security Center via the user interface.
2. Click **Dashboard > Dashboard**.

The **Dashboards** page appears.

3. In the upper-right corner of the page, click the **Options** drop-down button.
4. Click **Add Dashboard**

The **Dashboard Templates** page appears.

5. In the **Other** section, click the **Advanced** tile.
6. In the **Name** box, type a name for the dashboard.
7. In the **Description** box, type a description for the dashboard.
8. In the **Layout** section, select the layout you want to use for the dashboard.
9. Click **Submit**.

Tenable Security Center saves your configuration and the **Dashboards** page appears.

10. In the upper-right corner of the page, click the **Switch Dashboard** drop-down box.
11. Click the name of the dashboard you just created.

The page for the dashboard appears.

What to do next:





- Add dashboard components, as described in [Add a Template-Based Dashboard Component](#) or [Add a Custom Dashboard Component](#).



## Dashboard and Component Templates

Tenable Security Center provides a selection of dashboards and dashboard component templates. You can configure a Tenable-provided dashboard template or you can create a fully customized dashboard. For more information, see [Dashboards](#) and [Custom Dashboard Component Options](#).

For a complete index of Tenable-provided report templates, see the [Tenable Security Center Dashboards](#) blog.

Template	Description
<b>Common</b>	
<b>Compliance &amp; Configuration Assessment</b>	Dashboards that aid with configuration, change, and compliance management.
<b>Discovery &amp; Detection</b>	Dashboards that aid in trust identification, rogue detection, and new device discovery.
<b>Executive</b>	Dashboards that provide operational insight and metrics geared towards executives.
<b>Monitoring</b>	Dashboards that provide intrusion monitoring, alerting, and analysis.
<b>Security Industry Trends</b>	Dashboards related to trends, reports, and analysis from industry leaders.
<b>Threat Detection &amp; Vulnerability Assessments</b>	Dashboards that aid with identifying vulnerabilities and potential threats.
<b>Other (Dashboards)</b>	
<b>Advanced</b>	A custom dashboard with no pre-configured settings.
<b>Import</b>	Import a dashboard. For more information, see <a href="#">Import a Dashboard</a> .
<b>Other (Dashboard Components)</b>	
<b>Table</b>	Add a table to your dashboard.



<b>Bar Chart</b>	Add a bar chart to your dashboard.
<b>Pie Chart</b>	Add a pie chart to your dashboard.
<b>Matrix</b>	Add a matrix to your dashboard.
<b>Line Chart</b>	Add a line chart to your dashboard.
<b>Area Chart</b>	Add an area chart to your dashboard.



## Import a Dashboard

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information, see [Dashboards](#).

To import a dashboard:

1. Log in to Tenable Security Center via the user interface.
2. Click **Dashboard**.  
The **Dashboards** page appears.
3. In the upper-right corner of the page, click the **Options** drop-down button.
4. Click **Add Dashboard**.  
The **Dashboard Templates** page appears.
5. In the **Other** section, click **Import**.  
The **Import Dashboard** page appears.
6. In the **Name** box, type a name for the dashboard.
7. Click **Choose File** and browse to the dashboard file you want to import.
8. Click **Submit**.

Tenable Security Center imports the dashboard.



# Manage Dashboards

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information, see [Dashboards](#).

To manage dashboards:

1. Log in to Tenable Security Center via the user interface.
2. Click **Dashboard > Dashboard**.

The **Dashboards** page appears.

3. In the upper-right corner of the page, click the **Options** drop-down button.
4. Click **Manage Dashboards**

The **Manage Dashboards** page appears.

5. To add a dashboard, click **Add**. For more information, see [Add a Template-Based Dashboard](#) or [Add a Custom Dashboard](#).
6. To filter the dashboards in the table, see [Apply a Filter](#).
7. To manage a single dashboard, right-click the dashboard.

-or-

To manage multiple dashboards, select the check box for the dashboard.

The actions menu appears.

From this menu, you can:

- Click **View** to view details for the dashboard.
- Click **Share** to share or revoke access to the dashboard.
- Click **Export** to download an XML version of the dashboard.
- Click **Copy** to copy the dashboard.
- Click **Edit** to edit the dashboard.



- Click **Hide from Dashboard** to hide the dashboard from the **Switch Dashboard** drop-down on the **Dashboards** page.
- Click **Show on Dashboard** to show the dashboard on the **Switch Dashboard** drop-down on the **Dashboards** page.
- Click **Delete** to delete the dashboard.

To export the dashboard as an XML file:

- a. Click **Export**.
- b. Then, identify how you want Tenable Security Center to handle object references:
  - **Remove All References** – all object references are removed, altering the definitions of the components. Importing users do not need to make any changes for components to be useable.
  - **Keep All References** – object references are kept intact. Importing users must be in the same organization and have access to all relevant objects for the components to be useable.
  - **Replace With Placeholders** – object references are removed and replaced with their respective names. Importing users see the name of the reference object, but need to replace it with an applicable object within their organization before the component is useable.

**Note:** Due to version-specific changes in dashboard XML file formats, exported dashboards are not always compatible for import between Tenable Security Center versions.



## Edit Settings for a Dashboard

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information, see [Dashboards](#).

To edit the settings for a dashboard:

1. Log in to Tenable Security Center via the user interface.
2. Click **Dashboard > Dashboard**.

The **Dashboards** page appears, displaying your default dashboard.

3. If you want to switch to a different dashboard:
  - a. In the upper-right corner of the page, click the **Switch Dashboard** drop-down box.
  - b. Click the dashboard you want to view.

The dashboard appears.

4. In the upper-right corner of the page, click the **Options** drop-down box.
5. Click **Edit Dashboard**.

The **Edit Dashboard** page appears.

6. Edit the **Name**, **Description**, or **Layout**.
7. Click **Submit**.

Tenable Security Center saves your configuration.



## Share or Revoke Access to a Dashboard

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can share access to a dashboard to give users in a group the ability to view the dashboard. The user's role and custom permissions determine if they can drill down into other pages with more information. For more information, see [Dashboards](#).

To share or revoke access to a dashboard:

1. Log in to Tenable Security Center via the user interface.
2. Click **Dashboard > Dashboard**.

The **Dashboards** page appears, displaying your default dashboard.

3. If you want to switch to a different dashboard:
  - a. In the upper-right corner of the page, click the **Switch Dashboard** drop-down box.
  - b. Click the dashboard you want to view.

The dashboard appears.

4. In the upper-right corner of the page, click the **Options** drop-down box.
5. Click **Share**.

The **Share Dashboard** window appears.

6. In the box, search for and select the groups for which you want to share or revoke access.
7. Click **Submit**.

Tenable Security Center saves your configuration.





## Delete a Dashboard

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information, see [Dashboards](#).

To delete a dashboard:

1. Log in to Tenable Security Center via the user interface.
2. Click **Dashboard > Dashboard**.

The **Dashboards** page appears, displaying your default dashboard.

3. If you want to switch to a different dashboard:
  - a. In the upper-right corner of the page, click the **Switch Dashboard** drop-down box.
  - b. Click the dashboard you want to view.

The dashboard appears.

4. In the upper-right corner of the page, click the **Options** drop-down box.
5. Click **Delete**.

A confirmation window appears.

6. Click **Delete**.

The system deletes the dashboard.



# Manage Dashboard Components

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information, see [Dashboards](#).

To manage dashboard components:

1. Log in to Tenable Security Center via the user interface.
2. Click **Dashboard > Dashboard**.

The **Dashboards** page appears.

To edit a dashboard component:

1. Hover over the dashboard component.
2. Click the **•••** menu.

The actions menu appears.

3. Click **Edit**.
4. Edit the dashboard component options. For more information, see [Custom Dashboard Component Options](#).

To view the data behind a dashboard component:

1. Hover over the dashboard component.
2. In the lower right corner, click **View Data**.

The analysis page appears.

**Note:** Only dashboard components that display vulnerability analysis or event analysis data support viewing the data behind a dashboard component.

To reorder a dashboard component:

1. Click the title of a dashboard component.
2. Drag the dashboard component around the page.



---

To copy a dashboard component to the dashboard in view or a different dashboard:

1. Hover over the dashboard component.

2. Click the **•••** menu.

The actions menu appears.

3. Click **Copy**.

4. In the **Name** box, edit the name for the copied dashboard component.

5. In the **Dashboard** drop-down box, click the name of the dashboard where you want to copy the dashboard component.

6. Click **Copy**.

Tenable Security Center copies the dashboard component.

To refresh the dashboard component data:

1. Hover over the dashboard component.

2. Click the **•••** menu.

The actions menu appears.

3. Click **Refresh**.

Tenable Security Center refreshes the dashboard component data.

To delete the dashboard component:

1. Hover over the dashboard component.

2. Click the **•••** menu.

The actions menu appears.

3. Click **Delete**.

A confirmation window appears.

4. Click **Delete**.

Tenable Security Center deletes the dashboard component.



## Add a Template-Based Dashboard Component

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can add a dashboard component by configuring a Tenable-provided dashboard component template. To add a custom dashboard component instead, see [Add a Custom Dashboard Component](#).

For more information, see [Dashboards](#) and [Dashboard and Component Templates](#).

Before you begin:

- Add a dashboard, as described in [Add a Template-Based Dashboard](#), [Add a Custom Dashboard](#), or [Import a Dashboard](#).

To add a template-based dashboard component to a dashboard:

1. Log in to Tenable Security Center via the user interface.
2. Click **Dashboard**.

The **Dashboards** page appears.

3. In the upper-right corner of the page, click the **Switch Dashboard** drop-down box.
4. Click the name of the dashboard for which you want to add a component.

The dashboard appears.

5. In the upper-right corner of the page, click the **Options** drop-down box.
6. Click **Add Component**.

The **Component Templates** page appears.

7. In the **Common** section, click the template you want to use for the dashboard component.

The **Add Component Template** page updates to reflect the template you selected.

8. Modify the dashboard component template:



- To edit the dashboard component name, click the name box and edit the name.
- To edit the dashboard component description, click the **Description** box and edit the description.
- To restrict the target data displayed in the dashboard component, click the **Targets** drop-down box.
- To edit the dashboard component refresh schedule, click the **Schedule** link.

9. Click **Add**.

Tenable Security Center saves your configuration and the **Dashboards** page appears.



## Add a Custom Dashboard Component

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can configure a custom dashboard component to add a table, bar chart, pie chart, line chart, area chart, or matrix to a dashboard. For more information, see [Dashboards](#) and [Dashboard and Component Templates](#).

For an example matrix component configuration, see [Configure a Simple Matrix Dashboard Component](#).

Before you begin:

- Add a dashboard, as described in [Add a Template-Based Dashboard](#), [Add a Custom Dashboard](#), or [Import a Dashboard](#).

To add a custom dashboard component to a dashboard:

1. Log in to Tenable Security Center via the user interface.
2. Click **Dashboard**.

The **Dashboards** page appears.

3. In the upper-right corner of the page, click the **Switch Dashboard** drop-down box.
4. Click the name of the dashboard for which you want to add a component.

The dashboard page appears.

5. In the upper-right corner of the page, click the **Options** drop-down box.
6. Click **Add Component**.

The **Component Templates** page appears.

7. In the **Other** section, click the type of component you want to configure.

The component configuration page appears.

8. Configure the options for your component type, as described in [Custom Dashboard Component Options](#).



9. Click **Submit**.

Tenable Security Center saves your configuration.



## Custom Dashboard Component Options

Use the following options to configure custom dashboard components. For more information about dashboard component types, see [Dashboard and Component Templates](#).

Tenable Security Center supports the following custom dashboard components:

- [Table Component Options](#)
- [Bar Chart Component Options](#)
- [Pie Chart Component Options](#)
- [Matrix Component Options](#)
- [Line and Area Chart Component Options](#)

### General Options

Configure the following options for all custom dashboard component types.

Option	Description	Default
<b>Name</b>	(Required) A name for the dashboard component.	--
<b>Description</b>	A description for the dashboard component. The description appears on the <b>Dashboards</b> page when you hover over a dashboard component.	--
<b>Schedule</b>	(Required for all except <b>Matrix</b> components) Specifies how often the component polls the data source to obtain updates: <ul style="list-style-type: none"><li>• <b>Never</b> —The component never polls the data source.</li><li>• <b>Minutely</b> —Polls every 15, 20, or 30 minutes.</li><li>• <b>Hourly</b> —Polls every 1, 2, 4, 6, or 12 hours.</li><li>• <b>Daily</b> —Polls daily or every specified number of days at the specified time.</li><li>• <b>Weekly</b> —Polls weekly or every specified number of weeks at the specified time.</li></ul>	Daily





Option	Description	Default
	<ul style="list-style-type: none"><li>• <b>Monthly</b>—Polls monthly or every specified number of months at the specified day and time.</li></ul> <div style="border: 1px solid red; padding: 5px;"><p><b>Caution:</b> Excessively frequent updates may cause the application to become less responsive due to the added processing load imposed on the host OS.</p></div>	

## Table Component Options

Option	Description	Default
<b>Data</b>		
<b>Type</b>	The type of data: <b>Vulnerability</b> , <b>Event</b> , <b>Mobile</b> , <b>User</b> , <b>Ticket</b> , or <b>Alert</b> .	Vulnerability
<b>Query</b>	Predefined query used to further narrow down the data source options. If a query does not exist or is not desired, it may be left unselected. The query may be used as is or as a template on which to base the <b>Filters</b> option.	--
<b>Source</b>	(If <b>Type</b> is <b>Vulnerability</b> or <b>Event</b> ) Specifies the data source.  For vulnerability data, select <b>Cumulative</b> or <b>Mitigated</b> .  For event data, the data source is <b>Active</b> . Tenable Security Center can use only active event data for event-based components.	Cumulative
<b>Tool</b>	The analysis tool to use for creating the chart. For more information, see <a href="#">Vulnerability Analysis Tools</a> and <a href="#">Event Analysis Tools</a> .	Vulnerability Summary
<b>Filters</b>	Additional filters to use on the data source. For more information, see <a href="#">Filters</a> .	--
<b>Display</b>		



Option	Description	Default
<b>Results Displayed</b>	<p>The number of displayed results. You can choose to display up to 999 results.</p> <p>If the <b>Viewport Size</b> setting is smaller than this setting, the results display is limited to the <b>Viewport Size</b> setting with a scrollbar to display the additional results.</p>	10
<b>Viewport Size</b>	<p>The number of records (maximum: 50) to display along with a scrollbar to handle additional records. For example, if <b>Results Displayed</b> is set to <b>100</b> and <b>Viewport Size</b> is <b>15</b>, 15 records are displayed with a scrollbar to view the additional 85 records.</p>	10
<b>Sort Column</b>	<p>(Not available if <b>Type</b> is <b>Event</b>) The column Tenable Security Center uses to sort the results.</p>	Plugin ID
<b>Sort Direction</b>	<p>(Not available if <b>Type</b> is <b>Event</b>) The sort direction: <b>Descending</b> or <b>Ascending</b>.</p>	Descending
<b>Display Columns</b>	<p>The columns to display in the component output.</p>	--

## Bar Chart Component Options

Option	Description	Default
<b>Data</b>		
<b>Type</b>	<p>The type of data: <b>Vulnerability</b>, <b>Event</b>, <b>Mobile</b>, or <b>Ticket</b>.</p>	Vulnerability
<b>Query</b>	<p>Predefined query used to further narrow down the data source options. If a query does not exist or is not desired, it may be left unselected. The query may be used as is or as a template on which to base the <b>Filters</b> option.</p>	--
<b>Source</b>	<p>(If <b>Type</b> is <b>Vulnerability</b> or <b>Event</b>) Specifies the data source.</p>	Cumulative



Option	Description	Default
	<p>For vulnerability data, select <b>Cumulative</b> or <b>Mitigated</b>.</p> <p>For event data, the data source is <b>Active</b>. Tenable Security Center can use only active event data for event-based components.</p>	
<b>Tool</b>	The analysis tool to use for creating the chart. For more information, see <a href="#">Vulnerability Analysis Tools</a> and <a href="#">Event Analysis Tools</a> .	Vulnerability Summary
<b>Filters</b>	Additional filters to use on the data source. For more information, see <a href="#">Filters</a> .	--
<b>Display</b>		
<b>Results Displayed</b>	The number of displayed results. You can choose to display up to 100 results.	10
<b>Sort Column</b>	(If <b>Type</b> is <b>Vulnerability</b> or <b>Ticket</b> ) The column Tenable Security Center uses to sort the results.	Plugin ID
<b>Sort Direction</b>	(If <b>Type</b> is <b>Vulnerability</b> or <b>Ticket</b> ) The sort direction: <b>Descending</b> or <b>Ascending</b> .	Descending
<b>Display Column</b>	The columns to display in the component output.	--

## Pie Chart Component Options

Option	Description	Default
<b>Data</b>		
<b>Type</b>	The type of data: <b>Vulnerability</b> , <b>Event</b> , <b>Mobile</b> , or <b>Ticket</b> .	Vulnerability
<b>Query</b>	Predefined query used to further narrow down the data source options. If a query does not exist or is not desired, it may be left unselected. The query may be used as is or as a template on which to base the <b>Filters</b> option.	--



Option	Description	Default
<b>Source</b>	(If <b>Type</b> is <b>Vulnerability</b> or <b>Event</b> ) Specifies the data source.  For vulnerability data, select <b>Cumulative</b> or <b>Mitigated</b> .  For event data, the data source is <b>Active</b> . Tenable Security Center can use only active event data for event-based components.	Cumulative
<b>Tool</b>	The analysis tool to use for creating the chart. For more information, see <a href="#">Vulnerability Analysis Tools</a> and <a href="#">Event Analysis Tools</a> .	Vulnerability Summary
<b>Filters</b>	Additional filters to use on the data source. For more information, see <a href="#">Filters</a> .	--
<b>Display</b>		
<b>Results Displayed</b>	The number of displayed results.	10
<b>Sort Column</b>	The column Tenable Security Center uses to sort the results.	Plugin ID
<b>Sort Direction</b>	The sort direction: <b>Descending</b> or <b>Ascending</b> .	Descending
<b>Display Column</b>	The columns to display in the component output.	--

## Matrix Component Options

For information about configuring matrix components and to download samples, visit the [Tenable Security Center Dashboards](#) blog. For an example matrix component, see [Configure a Simple Matrix Dashboard Component](#).

When you create a matrix component, you define rules to determine what displays in each cell in a table of customizable columns and rows.



- Use columns to define a group of vulnerability, mobile, event, ticket, user, or alert data. For example, you could create columns for critical, high, medium, low, and informational vulnerabilities.
- Use rows to define the operations performed against each column element for that row. For example, if each column determines the vulnerability type (critical, high, medium, low, and informational), you can create a row to calculate the ratio of the particular vulnerability type count against the total vulnerability count.

By default, each cell definition includes a single customizable rule that defines what appears in the cell if no other conditions have been defined or triggered.

Tenable Security Center reviews each rule in a cell from top to bottom and triggers the display rule on the first rule match. Once a rule triggers, Tenable Security Center stops reviewing rules for the cell. If none of the added rules match, Tenable Security Center performs the default rule.

Option	Action
<b>Cells</b>	
<b>Size</b>	Use the drop-down menus to select the number of columns and rows for the matrix. Tenable Security Center supports matrices from 1x1 to 10x10.  Click <b>Generate Cells</b> create a blank matrix with customizable cells.
••• icon	Click the ••• icon in a row or column header cell to manage the column or row. <ul style="list-style-type: none"><li>• To edit the header name or refresh frequency, click <b>Edit Header</b>.</li></ul> <div style="border: 1px solid green; padding: 5px; margin: 10px 0;"><b>Tip:</b> You can choose to refresh the data more often to see the most current view. However, frequent refreshes can cause slow system performance.</div> <ul style="list-style-type: none"><li>• To delete the row or column, click <b>Delete Cells</b>.  Tenable Security Center deletes the row or column.</li><li>• To copy the row or column, click <b>Copy</b>.  Tenable Security Center copies the row or column.</li></ul>
✎ icon	Click the ✎ icon inside a cell to configure rules for the cell. For more information, see <a href="#">Matrix Component Query Options</a> .



## Matrix Component Query Options

Option	Description	Default
<b>Data</b>		
<b>Data Type</b>	<p>The type of data: <b>Vulnerability, Mobile, Event, User, Alert, or Ticket.</b></p> <p>The <b>Data Type</b> determines which query values are available in the <b>Condition</b> option.</p>	Vulnerability
<b>Type</b>	The matrix component display type: <b>Count</b> or <b>Ratio</b>	Count
<b>Source</b>	<p>(If <b>Data Type</b> is <b>Vulnerability</b> or <b>Event</b>) Specifies the data source.</p> <p>For vulnerability data, select <b>Cumulative</b> or <b>Mitigated</b>.</p> <p>For event data, the data source is <b>Active</b>. Tenable Security Center can use only active event data for event-based components.</p>	Cumulative
<b>Filters</b>	(If <b>Type</b> is <b>Count</b> ) Additional filters to use on the data source. For more information, see <a href="#">Filters</a> .	--
<b>Numerator Filters</b>	(If <b>Type</b> is <b>Ratio</b> ) The filters to apply to the ratio numerator. For more information, see <a href="#">Filters</a> .	--
<b>Denominator Filters</b>	(If <b>Type</b> is <b>Ratio</b> ) The filters to apply to the ratio denominator. For more information, see <a href="#">Filters</a> .	--
<b>Rules</b>		
<b>Condition</b>	<p>Specifies the conditions for the matrix component. Use the drop-down menus to define the quantity and query value to use for the rule.</p> <p>Quantities: <b>Less than or equal to, Greater than or equal to, Exactly, or Not Equal to.</b></p> <p>Query values: <b>Events, Hosts, Vulnerabilities, Ports,</b></p>	--



Option	Description	Default
	<p><b>Devices, Users, Alerts, or Tickets.</b></p> <div style="border: 1px solid blue; padding: 5px; margin: 5px 0;"> <p><b>Note:</b> The available query values depend on the <b>Data Type</b>.</p> </div>	
<b>Display</b>	<p>Specifies the appears of the matrix component when the rule <b>Condition</b> is met.</p> <ul style="list-style-type: none"> <li>• <b>Text</b> —Displays the <b>Query Value</b> or custom <b>User-Defined</b> text.</li> <li>• <b>Icon</b> —Displays the selected indicator icon.</li> <li>• (If <b>Type</b> is <b>Ratio</b>) <b>Indicator</b> —Displays a percentage.</li> </ul>	Text
<b>Text Color</b>	(If <b>Display</b> is <b>Text</b> ) The matrix component text color.	#1a1a40
<b>Background</b>	(If <b>Display</b> is <b>Text</b> ) The matrix component background color.	#333333 or #ffffff

## Line and Area Chart Component Options

Option	Description	Default
<b>Data</b>		
<b>Date Type</b>	<p>The date type:</p> <ul style="list-style-type: none"> <li>• <b>Relative</b> —A date relative to the current time when the chart is loaded.</li> <li>• <b>Absolute</b> —An absolute time frame that is the same on each page visit.</li> </ul>	Relative
<b>Date Range</b>	<p>The date range for the line or area chart.</p> <p>If <b>Date Type</b> is <b>Relative</b>, select from the following options:</p> <ul style="list-style-type: none"> <li>• <b>Within x Minutes</b> —Display data within the last 15, 20, or 30</li> </ul>	Within 24 Hours



Option	Description	Default
	<p>minutes.</p> <ul style="list-style-type: none"> <li>• <b>Within x Hours</b> —Display data within the last 1, 2, 4, 6, 12, 24, 48, or 72 hours.</li> <li>• <b>Within x Days</b> —Display data within the last 5, 7, 25, or 50 days.</li> <li>• <b>Within x Months</b> —Display data within the last 3 or 6 months.</li> <li>• <b>Within 1 Year</b> —Display data within the last year.</li> </ul> <p>If <b>Date Type</b> is <b>Absolute</b>, select a date and time for the beginning and end of the range.</p>	
<b>Series</b>	Click to add a series to the line or area chart. For more information, see <a href="#">Line and Area Chart Series Options</a> .	--

## Line and Area Chart Series Options

Option	Description	Default
<b>Name</b>	The name of the series.	--
<b>Data</b>		
<b>Data Type</b>	<p>The type of data: <b>Vulnerability</b> or <b>Event</b>.</p> <div style="border: 1px solid blue; padding: 5px; margin-top: 10px;"> <p><b>Note:</b> For line/area charts, vulnerability data analysis often requires that the underlying repository be a trending repository. If the selected repository is not a trending repository, no historical analysis is available.</p> </div>	Vulnerability
<b>Query</b>	Predefined query used to further narrow down the data source options. If a query does not exist or is not desired, it may be left unselected. The query may be used as is or as a template on which to base the <b>Filters</b> option.	--
<b>Filters</b>	Additional filters to use on the data source. For more information, see <a href="#">Filters</a> .	--





Display		
Series Data	Data to display in the chart: <b>Total, Info, Low, Medium, High</b> , or <b>Critical</b> .	All



---

## Configure a Simple Matrix Dashboard Component

---

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information, see [Dashboards](#) and [Matrix Component Options](#).

Before you begin:

- Begin adding a custom matrix dashboard component, as described in [Add a Custom Dashboard Component](#).

To construct a simple matrix dashboard component:

1. On the **Add Matrix Component** page, in the **Name** box, type a name for the dashboard component.
2. Type a **Description** for the dashboard component.
3. In the **Cells** section, select the number of **Columns** and **Rows** for the matrix.

## Add Matrix Component

Name\*

Description

### Cells

Size\*  Columns x  Rows [Generate Cells](#)

[Submit](#)

[Cancel](#)

For example, 5 columns and 3 rows.

4. Click **Generate Cells**.

The matrix editor appears.

5. Next to the header label, click the **⋮** menu.

The actions menu appears.

6. Click **Edit Header**.

7. Type a **Label** for the column or row header.

8. Click **Submit**.

The matrix editor appears, with the new header label displayed.



### Cells

	Exploit %	Metasploit	Core Impact	Canvas	Malware
Critical					
High					
Medium					

- Repeat the header label steps for the other header cells.
- Hover over the body cells and click the edit icon.

The **Add Matrix Component** page appears.

- Customize the matrix component options.

For example, this matrix component displays Vulnerability data by a ratio from the Cumulative database. The numerator filters are looking for vulnerabilities that have an exploit available with a Critical severity discovered within the last 7 days. The Denominator filters are for vulnerabilities that have a Critical severity discovered within the last 7 days. The rules are looking for percentages of the vulnerabilities that match and designate the ratio value with the corresponding color based on the percentages found.

### Add Matrix Component

← Back

**Data**

Data Type: Vulnerability

Type: Ratio

Source: Cumulative

**Numerator Filters**

Exploit Available: Yes

Severity: Critical

Vulnerability Discovered: Within the last 7 days

+ Add Filter

**Denominator Filters**

Severity: Critical

Vulnerability Discovered: Within the last 7 days

+ Add Filter

**Rules**

Greater than or equal to 50 % of Vulnerabilities match: Display Ratio Value: Vulnerabilities

Greater than or equal to 10 % of Vulnerabilities match: Display Ratio Value: Vulnerabilities

Greater than or equal to 1 % of Vulnerabilities match: Display Ratio Value: Vulnerabilities

Default: Display Ratio Value: Vulnerabilities

+ Add Rule

Submit Cancel

12. Repeat the body cell steps for the other body cells.

In the example above, the other cells are similar with many of the same rules. The differences are adding a Numerator filter to include the Exploit Framework we are looking for and a Denominator filter for the Exploit Available option.

### Cells

	Exploit %	Metasploit	Core Impact	Canvas	Malware
Critical					
High					
Medium					

Submit Cancel



13. Click **Submit**.

The matrix element appears.



## Interact with a Customizable Table

To interact with a customizable table:

1. Log in to Tenable Security Center via the user interface.
2. View a customizable table.
3. Do any of the following:

Navigate the table:

- To adjust the sort order, click a column title.

Tenable Security Center sorts all pages of the table by the data in the column that you selected.

- To view all action buttons available in a single row, right-click the row:

A drop-down menu appears with all the available actions.

- To navigate to another page of the table, click the arrows:

Button	Action
«	Navigate to the first page of the table.
»	Navigate to the last page of the table.
>	Navigate to the next page of the table.
<	Navigate to the previous page of the table.

- Click any row to navigate to another page to view more details.
- On the **Dashboard** page, click any plugin ID to view the **Plugin ID** pane.
- To change the column order, drag and drop a column header to another position in the table.
- Remove or add columns:



1. Roll over any column.

The ☰ appears in the header.

2. Click the ☰ button.

A column selection box appears.

3. Select or clear the check box for any column you want to show or hide in the table.

Tenable Security Center updates the table based on your selection.

- Adjust column width:

- a. Roll over the header between two columns until the resize cursor appears.

Click and drag the column width to the desired width.

- To sort data in the table, click a column header.

Tenable Security Center sorts all pages of the table by the data in the column you selected.





## Scan Results

The **Scan Results** page displays scan results and statuses from active scans, agent scans, and agent synchronization jobs .

**Note:** Tenable Security Center does not include all agent scans in the scan results table. If an agent scan imports scan results identical to the previous agent scan, Tenable Security Center omits the most recent agent scan from the scan results table.

**Note:** If you added the parent node of a Tenable Nessus Manager cluster as a scanner in Tenable Security Center, Tenable Security Center displays scan results for all child nodes. For more information, see [Clustering](#) in the *Tenable Nessus User Guide*.

**Note:** For each agent synchronization job result for a child node, Tenable Security Center imports a metadata record containing no vulnerability data. This metadata record appears as a second result on the **Scan Results** page. To prevent Tenable Security Center from importing the metadata file, configure and launch agent scans from Tenable Security Center, as described in [Agent Scans](#).

For more information, see [Manage Scan Results](#) and [Scan Result Statuses](#).



## Scan Result Statuses

You can view the scan status and the import status for all scan results, as described in [View Scan Result Details](#).

- [Scan Status](#)
- [Import Status](#)

### Scan Status

The scan status specifies the status of the scan.

Status	Description
Active Scans	
<b>Queued</b>	The scan is queued.
<b>Preparing</b>	Tenable Security Center is preparing to run the scan.
<b>Resolving Host-names</b>	Tenable Security Center is resolving hostnames before running the scan.
<b>Verifying Targets</b>	Tenable Security Center is verifying targets before running the scan.
<b>Initializing Scanners</b>	Tenable Security Center is initializing scanners before running the scan.
<b>Running</b>	The scan is running.
<b>Pausing</b>	You paused the scan and Tenable Security Center is pausing the scan.
<b>Paused</b>	The scan is paused.
<b>Resuming</b>	You resumed the scan and Tenable Security Center is resuming the scan.
<b>Stopping</b>	Tenable Security Center is stopping the scan.
<b>Completed</b>	The scan finished successfully.
<b>Partial</b>	The scan finished and some results are available.



Status	Description
Error	The scan did not finish.
Agent Scans	
Queued	The scan is queued.
Running	The scan is running.
Completed	The scan finished successfully.
Error	The scan did not finish.

## Import Status

The scan status specifies the status of the scan result import to Tenable Security Center.

Status	Description
Active and Agent Scans	
No Results	The scan finished successfully but yielded no results.
Import Pending	Tenable Security Center is preparing to start the import.
Importing	Tenable Security Center is importing the scan result data.
Finished	The import finished successfully.
Blocked	Tenable Security Center did not import the scan result for one of the following reasons: <ul style="list-style-type: none"><li>You have exceeded your license limit.</li><li>The scan result import would cause you to exceed your license.</li></ul> For more information about license limits, see <a href="#">License Requirements</a> .
Error	The import did not finish.



## Manage Scan Results

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

Depending on the state of a scan result, you can perform different management actions (for example, you cannot download results for a scan with errors).

For more information, see [Scan Results](#).

To manage scan results:

1. Log in to Tenable Security Center via the user interface.
2. Click **Scans > Scan Results**.

The **Scan Results** page appears.

3. Manage the results:

To filter the scan results:

- Click the filter icon.

Filters allow you to view only desired scan results. Filter parameters include:

- **Access** - filters by whether the scan is manageable or usable.
- **Group** - filters by the groups that can access the scans.
- **Name** - filters by the scan name.
- **Owner** - filters by the scan owner.
- **Scan Policy** - filters by the scan policy.
- **Status** - filters by the scan status.
- **Time (Created)** - filters by when the scan result was created.
- **Time (Finished)** - filters by when the scan finished running.
- **Type** - filters by the type of scan.

To remove all filters:



- Under the filter options, click **Clear Filters**.

**Note:** To return to the default filter for your user account, refresh your browser window. The number in grey next to the filter displays how many filters are currently in use.

### To view a set of scan results:

- a. Right-click the row for the scan.

The actions menu appears.

-or-

Select the check box for the scan.

The available actions appear at the top of the table.

- b. Select **Browse**.

The Vulnerability Summary analysis tool appears, populated with data from the scan.

### To view scan result details for a set of scan results:

- a. Right-click the row for the scan.

The actions menu appears.

-or-

Select the check box for the scan.

The available actions appear at the top of the table.

- b. Click **View**.

The **View Scan Result** page appears. For more information, see [Scan Result Details](#).

### To download the results of a scan:

- a. Right-click the row for the scan.

The actions menu appears.

-or-



Select the check box for the scan.

The available actions appear at the top of the table.

- b. Select **Download**.

**Tip:** On a standard scan, you can download a Tenable Nessus results file. If the scan contains SCAP results, you can use an additional option to download the SCAP results.

To manually import scans listed on the scan results page:

- a. Right-click the row for the scan.

The actions menu appears.

-or-

Select the check box for the scan.

The available actions appear at the top of the table.

- b. Select **Import**.

**Tip:** This option is useful for cases where a scan may have not fully imported after completion. For example, if Tenable Security Center blocked a scan because importing it would have exceeded the licensed IP address count, you can increase the IP address count, then import the scan results previously not imported.

To share scan results with other users:

- a. Right-click the row for the scan.

The actions menu appears.

-or-

Select the check box for the scan.

The available actions appear at the top of the table.

- b. Select **Copy**.

Selecting a **Group** from the drop-down box displays a list of users from that group. You can select one or more users from the list.



---

To send a copy of the scan results to users without access to Tenable Security Center:

- a. Right-click the row for the scan.

The actions menu appears.

-or-

Select the check box for the scan.

The available actions appear at the top of the table.

- b. Select **Email**.

To generate a report for the scan results based off a preconfigured report:

- a. Right-click the row for the scan.

The actions menu appears.

-or-

Select the check box for the scan.

The available actions appear at the top of the table.

- b. Select **Send to Report**.

Tenable Security Center sends the scan results to a report.

To upload Tenable Nessus scan results performed by other systems:

- See [Upload Scan Results](#).

To pause or resume a running scan:

- In the row for the scan, click the pause or play button, as described in [Start or Pause a Scan](#).

To delete a set of scan results from Tenable Security Center:

- a. Right-click the row for the scan.

The actions menu appears.



-or-

Select the check box for the scan.

The available actions appear at the top of the table.

b. Select **Delete**.

Tenable Security Center deletes the scan results.





## View Scan Results

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information, see [Scan Results](#).

**Note:** Tenable Security Center does not include all agent scans in the scan results table. If an agent scan imports scan results identical to the previous agent scan, Tenable Security Center omits the most recent agent scan from the scan results table.

**Note:** If you added the parent node of a Tenable Nessus Manager cluster as a scanner in Tenable Security Center, Tenable Security Center displays scan results for all child nodes. For more information, see [Clustering](#) in the *Tenable Nessus User Guide*.

**Note:** For each agent synchronization job result for a child node, Tenable Security Center imports a metadata record containing no vulnerability data. This metadata record appears as a second result on the **Scan Results** page. To prevent Tenable Security Center from importing the metadata file, configure and launch agent scans from Tenable Security Center, as described in [Agent Scans](#).

To view a list of scan results:

1. Log in to Tenable Security Center via the user interface.
2. Click **Scans > Scan Results**.

The **Scan Results** page appears.

3. View details about each scan result.
  - **Name** —The name for the scan associated with the result.
  - **Type** —The type of scan that generated the scan result.
  - **Scan Policy** —The name of the scan policy that generated the scan result.
  - **Scanned IPs** —The number of IP addresses scanned.
  - **Group** —The group associated with the scan.
  - **Owner** —The username for the user who added the scan.



- **Duration** —The total time elapsed while running the scan.
- **Import Time** —The date and time Tenable Security Center completed the scan result import.
- **Status** —The status of the scan that generated the scan result. For more information, see [Scan Status](#).

4. To view additional details for a scan result, see [View Scan Result Details](#).



## View Scan Result Details

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can view details for any scan result. For more information, see [Scan Results](#).

To view scan result details:

1. Log in to Tenable Security Center via the user interface.
2. Click **Scans > Scan Results**.

The **Scan Results** page appears.

3. Right-click the row for the scan result.

The actions menu appears.

-or-

Select the check box for the scan result.

The available actions appear at the top of the table.

4. Click **View**.

The **View Scan Result** page appears.

Section	Action
<b>General</b>	<p>View general information for the scan result.</p> <ul style="list-style-type: none"><li>• <b>Name</b> —The scan result name.</li><li>• <b>Type</b> —The type of scan that generated the scan result.</li><li>• <b>Scan Policy</b> —The name of the scan policy that generated the scan result.</li><li>• <b>Repository</b> —The name of the repository associated with the scan policy that generated the scan result.</li><li>• <b>Scanned IPs / Total IPs</b> —The number of IP addresses</li></ul>



Section	Action
	<p>scanned compared to the total number of IP addresses targeted in the scan.</p> <ul style="list-style-type: none"><li>• <b>Status</b> —The scan status. For more information, see <a href="#">Scan Status</a>.</li><li>• <b>Start Time</b> —The date and time Tenable Security Center started the scan.</li><li>• <b>Finish Time</b> —The date and time Tenable Security Center completed the scan.</li><li>• <b>Status</b> —The scan status. For more information, see <a href="#">Scan Status</a>.</li><li>• <b>Duration</b> —The total time elapsed while running the scan.</li><li>• <b>Import Start</b> —The date and time Tenable Security Center started the scan result import.</li><li>• <b>Import Finish</b> —The date and time Tenable Security Center completed the scan result import.</li><li>• <b>Import Status</b> —The scan result import status. For more information, see <a href="#">Import Status</a>.</li><li>• <b>Import Duration</b> —The total time elapsed during scan result import.</li><li>• <b>Owner</b> —The username for the user who added the scan.</li><li>• <b>Group</b> —The group associated with the scan.</li><li>• <b>ID</b> —The scan result ID.</li></ul>
<b>Tenable.io Synchronization Data</b>	<p>View synchronization summary data:</p> <ul style="list-style-type: none"><li>• <b>Status</b> —The status of the Tenable Lumin synchronization containing this scan result data:</li></ul>



Section	Action
	<ul style="list-style-type: none"><li>• <b>Not Synced</b> —The repository containing this scan result data is not configured for Tenable Lumin synchronization.</li><li>• <b>Syncing</b> —The Tenable Lumin synchronization containing this scan result data is in progress.</li><li>• <b>Finished</b> —The most recent synchronization that included this scan result data succeeded.</li><li>• <b>Error</b> —An error occurred. For more information, see <a href="#">View Tenable Lumin Data Synchronization Logs</a>.</li><li>• <b>Start Time</b> —The date and time Tenable Security Center started the most recent transfer of data to Tenable Vulnerability Management.</li><li>• <b>Finish Time</b> —The date and time Tenable Security Center finished the most recent transfer of data to Tenable Vulnerability Management.</li><li>• <b>Duration</b> —The total time elapsed during the most recent transfer of data to Tenable Vulnerability Management.</li><li>• <b>Details</b> —If the <b>Status</b> is <b>Error</b>, details about the error.</li></ul> <p>For more information about Tenable Lumin synchronization, see <a href="#">Tenable Lumin Synchronization</a>.</p>



## Upload Scan Results

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can upload active or agent scan results from scans performed by other systems. Tenable Security Center supports either raw (.nessus) or compressed (.zip) files, with one .nessus file per archive before uploading. This allows you to import scan results from scans run in remote locations without network connectivity to Tenable Security Center.

**Note:** To upload files greater than 300 MB to Tenable Security Center, you must modify `upload_max_filesize` in `/opt/sc/support/etc/php.ini` to accommodate the larger uploads.

### Scan Result-Repository Incompatibility

**Caution:** Tenable does not recommend importing scan results to incompatible repositories since data may be omitted.

If you upload agent scan results to a non-agent repository, Tenable Security Center omits all vulnerabilities without **IP Address** data for the host. Non-agent repositories cannot uniquely identify hosts without **IP Address** data for the host.

If you upload non-agent scan results to an agent repository, Tenable Security Center omits all vulnerabilities without **Agent ID** data for the host. Agent repositories cannot uniquely identify hosts without **Agent ID** data for the host.

To upload scan results:

1. Log in to Tenable Security Center via the user interface.
2. Click **Scans > Scan Results**.

The **Scan Results** page appears.

3. At the top of the table, click **Upload Scan Results**.
4. In the **Scan File** option, click **Choose File**.

The file uploads to Tenable Security Center.

5. In the **Import Repository** drop-down box, select a repository.



6. If you selected an IPv4, IPv6, or Universal repository, enable or disable the **Advanced** options: **Track hosts which have been issued new IP address**, **Scan Virtual Hosts**, and **Immediately remove vulnerabilities from scanned hosts that do not reply**.

For more information about the advanced options, see [Active Scan Settings](#).

7. Click **Submit**.

Tenable Security Center saves your configuration.



---

## Solutions Analysis

---

Tenable provides recommended solutions for all vulnerabilities on your network. You can perform the recommended action in a solution to lower the risk on your network.

For more information, see:

- [View Solutions](#)
- [View Solution Details](#)





## View Solutions

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can use the **Solutions** page to view solutions for specific assets on your network or drill into solution details.

To view solutions for assets on your network:

1. Log in to Tenable Security Center via the user interface.
2. Click **Solutions**.

The **Solutions** page appears.

3. To filter the solutions in the table by an asset list, in the **Targeted Assets** drop-down box, click an asset list name.

The system refreshes the page and filters the table by the asset list you selected. For more information about asset lists, see [Assets](#).

4. To customize the table, see [Interact with a Customizable Table](#).
5. View information about each solution.

- **Solution** —A description for the solution.
- **Risk Reduction** —The percent you would reduce your risk by addressing the vulnerability in the solution. Tenable Security Center calculates the risk reduction percentage by dividing the score of the vulnerabilities in the solution by the score of all of the vulnerabilities on your network.
- **Hosts Affected** —The number of devices affected by the solution.
- **Vulnerabilities** —The number of vulnerability instances included in the solution.

**Tip:** A vulnerability instance is a single instance of a vulnerability appearing on an asset, identified uniquely by plugin ID, port, and protocol.

- **VPR** —The highest VPR for a vulnerability included in the solution.



- **CVSSv3 Base Score** —The highest CVSSv3 score for a vulnerability included in the solution. If only CVSSv2 is available, the column is blank.

6. To view details for a solution, click a row.

The **Solution Details** page appears. For more information, see [Solution Details](#).



## View Solution Details

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can use the **Solution Details** page to view details for a specific solution. To export the details for a solution, see [Export Hosts Affected by a Solution](#).

To view details for a specific solution:

1. Log in to Tenable Security Center via the user interface.
2. Click **Solutions**.

The **Solutions** page appears.

3. Click a solution row.

The **Solution Details** page appears.

Section	Action
Metrics summary	<p>View summary statistics for the recommended solution.</p> <ul style="list-style-type: none"><li>• <b>Hosts Affected</b> —The number of devices affected by the solution.</li><li>• <b>Vulnerabilities</b> —The total number of vulnerability instances included in the solution.</li></ul> <div style="border: 1px solid green; padding: 5px;"><p><b>Tip:</b> A vulnerability instance is a single instance of a vulnerability appearing on an asset, identified uniquely by plugin ID, port, and protocol.</p></div> <ul style="list-style-type: none"><li>• <b>VPR</b> —The highest VPR for a vulnerability included in the solution.</li><li>• <b>CVSSv3 Base Score</b> —The highest CVSSv3 score for a vulnerability included in the solution. If only CVSSv2 is available, the column is blank.</li></ul>



Section	Action
<b>Vulnerabilities Included</b> table	<p>View all vulnerabilities related to the recommended solution, sorted by decreasing VPR.</p> <ul style="list-style-type: none"><li>• <b>Plugin</b> —The plugin ID.</li><li>• <b>Hosts Affected</b> —The number of devices affected by the solution.</li><li>• <b>VPR</b> —The VPR for the vulnerability.</li><li>• <b>CVSSv3 Base Score</b> —The CVSSv3 score for the vulnerability included in the solution. If only CVSSv2 is available, the column is blank.</li></ul>
<b>Hosts Affected</b> table	<p>View device information.</p> <ul style="list-style-type: none"><li>• <b>IP Address</b> —The IP address for the device.</li><li>• <b>NetBIOS</b> —The NetBIOS name, if known.</li><li>• <b>DNS</b> —The DNS name, if known.</li><li>• <b>OS CPE</b> —The operating system common platform enumeration (CPE) name.</li><li>• <b>Repository</b> —The repository name where device's scan data is stored.</li></ul> <p>A device appears in multiple rows if the device's scan data is stored in multiple repositories.</p>

#### What to do next:

- (Optional) Export the hosts affected by the solution to share with others in your organization, as described in [Export Hosts Affected by a Solution](#).



## Export Hosts Affected by a Solution

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can export a list of hosts affected by a solution as a .csv file to share the data with others in your organization. For more information, see [Solutions Analysis](#).

To export hosts affected by a solution:

1. Log in to Tenable Security Center via the user interface.

2. Click **Solutions**.

The **Solutions** page appears.

3. Click the row for the solution for which you want to export a list of affected hosts.

The **Solution Details** page appears.

4. In the upper-right corner, click **Export as CSV**.

A confirmation window appears.

**Note:** If the number of affected hosts is greater than 1,000, Tenable Security Center prompts you to type a name for the CSV report result you want to generate. After generation, you can download the report result, as described in [Download a Report Result](#).

5. Select or clear the check boxes to indicate which columns you want to appear in the exported file.

Column Name	Description
Solution ID	The plugin ID associated with the recommended solution.
Solution	A description for the solution.
Tenable UUID	The Tenable UUID, if applicable. A Tenable UUID uniquely identifies: <ul style="list-style-type: none"><li>• Agent-detected assets that may share a common IP address.</li><li>• Tenable OT Security assets that may not have an IP address.</li></ul>



	For more information, see <a href="#">Tenable OT Security Instances</a> .
DNS	The DNS name of the device, if known.
IP Address	The IP address for the device.
OS	The operating system running on the device.
CVEs	The number of unique CVEs associated with vulnerabilities on the affected host that are addressed by the solution.
CVE Instances	<p>The total number of CVE instances associated with vulnerabilities on the affected host that are addressed by the solution.</p> <p><b>Tip:</b> A vulnerability instance is a single instance of a vulnerability appearing on an asset, identified uniquely by plugin ID, port, and protocol.</p>
OS CPE	The operating system common platform enumeration (CPE) name of the device.
Repository	The name of the repository that stores the device's scan data.
MAC	The MAC address of the device, if known.
NetBIOS	The NetBIOS name of the device, if known.
Vulnerabilities	<p>The total number of vulnerability instances on the affected host addressed by the solution.</p> <p><b>Tip:</b> A vulnerability instance is a single instance of a vulnerability appearing on an asset, identified uniquely by plugin ID, port, and protocol.</p>
Vulnerability Percentage	<p>The number of vulnerability instances on the affected host addressed by the solution as a percentage of total vulnerability instances.</p> <p><b>Tip:</b> A vulnerability instance is a single instance of a vulnerability appearing on an asset, identified uniquely by plugin ID, port, and protocol.</p>



Score	<p>The sum of the weighted <a href="#">CVSS</a> score across vulnerability instances on the affected host addressed by the solution.</p> <p><b>Note:</b> Tenable Security Center uses either CVSSv2 or CVSSv3 to assess the severity of vulnerabilities, depending on your configuration. For more information, see <a href="#">Organizations</a>.</p> <p><b>Tip:</b> A vulnerability instance is a single instance of a vulnerability appearing on an asset, identified uniquely by plugin ID, port, and protocol.</p>
Risk Reduction	<p>The percent you would reduce your risk across all solutions and affected hosts by addressing the vulnerabilities on this affected host associated with the solution. Tenable Security Center calculates the risk reduction percentage by dividing the total <a href="#">CVSS</a> score of the vulnerabilities on the affected host addressed by the solution by the total CVSS score of all of the vulnerabilities on your network.</p> <p><b>Note:</b> Tenable Security Center uses either CVSSv2 or CVSSv3 to assess the severity of vulnerabilities, depending on your configuration. For more information, see <a href="#">Organizations</a>.</p>
MS Bulletins	<p>The number of unique MS Bulletins associated with vulnerabilities on the affected host that are addressed by the solution.</p>
MS Bulletin Instances	<p>The total number of vulnerabilities with associated MS Bulletins on the affected host that are addressed by the solution.</p>
VPR	<p>The highest <a href="#">VPR</a> of all vulnerabilities on the affected host that are addressed by the solution. If no VPR is available, the column is blank.</p>
CVSS v3	<p>The highest <a href="#">CVSSv3</a> score of all vulnerabilities on the affected host that are addressed by the solution. If only a CVSSv2 score is available, the column is blank.</p>

6. Click **Download**.

Tenable Security Center exports the list of hosts affected by the solution.



---

## Vulnerability Analysis

---

The **Vulnerabilities** page displays vulnerabilities from either the cumulative or mitigated vulnerability database. For more information, see [Cumulative vs. Mitigated Vulnerabilities](#).

**Note:** If multiple vulnerabilities share the same **IP Address** or **Agent ID** data, Tenable Security Center assumes they are from the same host.

To perform a common type of vulnerability analysis, see [View Vulnerabilities by Plugin](#) or [View Vulnerabilities by Host](#).

To view a specific vulnerability analysis tool, see [Vulnerability Analysis Tools](#).





---

## Cumulative vs. Mitigated Vulnerabilities

---

Tenable Security Center stores vulnerabilities in two databases: the cumulative database and the mitigated database. You can choose to view cumulative vulnerabilities or mitigated vulnerabilities in any vulnerability analysis tool. For more information, see [View Cumulative or Mitigated Vulnerabilities](#).

### Cumulative Vulnerabilities

The cumulative database contains currently vulnerable vulnerabilities, including recast, accepted, or previously mitigated vulnerabilities.

### Mitigated Vulnerabilities

The mitigated database contains vulnerabilities that Tenable Security Center determines are not vulnerable, based on the scan definition, the results of the scan, the current state of the cumulative view, and authentication information.

A vulnerability is mitigated if:

- The IP address of the vulnerability was in the target list of the scan.
- The plugin ID of the vulnerability was in the list of scanned plugins.
- The port of the vulnerability was in the list of scanned ports.
- The vulnerability with that IP address/port/plugin ID combination was not in the scan result.

To start, the vulnerability must appear in the cumulative view to be considered for mitigation. The import process then looks at each vulnerability in the import repository. The import process also verifies that authentication was successful before mitigating any local check vulnerabilities that meet the above criteria.

**Note:** Mitigation logic works with scans using policies defined by templates, advanced policies, and remediation scans. These policies are set up to take advantage of this new mitigation logic.

For more information about mitigation, see the [knowledge base](#) article.



---

## View Cumulative or Mitigated Vulnerabilities

---

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

For general information about cumulative vulnerabilities and mitigated vulnerabilities, see [Cumulative vs. Mitigated Vulnerabilities](#).

To switch between viewing mitigated or cumulative vulnerabilities:

1. Log in to Tenable Security Center via the user interface.
2. Click **Analysis > Vulnerabilities**.

The **Vulnerabilities** page appears.

3. In the upper-right corner, click **Cumulative** or **Mitigated**.

The page updates to display data from the mitigated or cumulative vulnerability database.



---

## CVSS vs. VPR

---

Tenable uses CVSS scores and a dynamic Tenable-calculated Vulnerability Priority Rating (VPR) to quantify the risk and urgency of a vulnerability.

**Note:** When you view these metrics on an analysis page organized by plugin (for example, the **Vulnerabilities** page), the metrics represent the highest value assigned or calculated for a vulnerability associated with the plugin.



## CVSS

Tenable uses and displays third-party Common Vulnerability Scoring System (CVSS) values retrieved from the National Vulnerability Database (NVD) to describe risk associated with vulnerabilities.

Tenable assigns all vulnerabilities a severity (**Info**, **Low**, **Medium**, **High**, or **Critical**) based on the vulnerability's static CVSSv2 or CVSSv3 score, depending on your configuration. For more information, see [Organizations](#).

Tenable Security Center analysis pages provide summary information about vulnerabilities using the following CVSS categories.

Severity	CVSSv2 Range	CVSSv3 Range
Critical	The plugin's highest vulnerability CVSSv2 score is 10.0.	The plugin's highest vulnerability CVSSv3 score is between 9.0 and 10.0.
High	The plugin's highest vulnerability CVSSv2 score is between 7.0 and 9.9.	The plugin's highest vulnerability CVSSv3 score is between 7.0 and 8.9.
Medium	The plugin's highest vulnerability CVSSv2 score is between 4.0 and 6.9.	The plugin's highest vulnerability CVSSv3 score is between 4.0 and 6.9.
Low	The plugin's highest vulnerability CVSSv2 score is between 0.1 and 3.9.	The plugin's highest vulnerability CVSSv3 score is between 0.1 and 3.9.
Info	The plugin's highest vulnerability CVSSv2 score is 0.  - or -  The plugin does not search for vulnerabilities.	The plugin's highest vulnerability CVSSv3 score is 0.  - or -  The plugin does not search for vulnerabilities.



## Vulnerability Priority Rating

Tenable calculates a dynamic VPR for most vulnerabilities. The VPR is a dynamic companion to the data provided by the vulnerability's CVSS score, since Tenable updates the VPR to reflect the current threat landscape. VPR values range from 0.1-10.0, with a higher value representing a higher likelihood of exploit.

VPR Category	VPR Range
Critical	9.0 to 10.0
High	7.0 to 8.9
Medium	4.0 to 6.9
Low	0.1 to 3.9

**Note:** Vulnerabilities without CVEs in the National Vulnerability Database (NVD) (for example, many vulnerabilities with the **Info** severity) do not receive a VPR. Tenable recommends remediating these vulnerabilities according to their CVSS-based severity.

**Note:** You cannot edit VPR values.

Tenable Security Center provides new and updated VPR values through the Tenable Security Center feed. For more information, see [Edit Plugin and Feed Schedules](#).

Tenable recommends resolving vulnerabilities with the highest VPRs first. You can view VPR scores and summary data in:

- The Tenable-provided **Vulnerability Priority Rating (VPR) Summary** dashboard, described in [Dashboards](#).
- The **Vulnerability Summary**, **Vulnerability List**, and **Vulnerability Detail List** tools, described in [View Vulnerabilities by Plugin](#).



## VPR Key Drivers

You can view the following key drivers to explain a vulnerability's VPR.

**Note:** Tenable does not customize these values for your organization; VPR key drivers reflect a vulnerability's global threat landscape.

Key Driver	Description
<b>Vulnerability Age</b>	The number of days since the National Vulnerability Database (NVD) published the vulnerability.
<b>CVSSv3 Impact Score</b>	The NVD-provided CVSSv3 impact score for the vulnerability. If the NVD did not provide a score, Tenable Security Center displays a Tenable-predicted score.
<b>Exploit Code Maturity</b>	The relative maturity of a possible exploit for the vulnerability based on the existence, sophistication, and prevalence of exploit intelligence from internal and external sources (e.g., Reversinglabs, Exploit-db, Metasploit, etc.). The possible values ( <b>High</b> , <b>Functional</b> , <b>PoC</b> , or <b>Unproven</b> ) parallel the CVSS Exploit Code Maturity categories.
<b>Product Coverage</b>	The relative number of unique products affected by the vulnerability: <b>Low</b> , <b>Medium</b> , <b>High</b> , or <b>Very High</b> .
<b>Threat Sources</b>	A list of all sources (e.g., social media channels, the dark web, etc.) where <a href="#">threat events</a> related to this vulnerability occurred. If the system did not observe a related threat event in the past 28 days, the system displays <b>No recorded events</b> .
<b>Threat Intensity</b>	The relative intensity based on the number and frequency of recently observed <a href="#">threat events</a> related to this vulnerability: <b>Very Low</b> , <b>Low</b> , <b>Medium</b> , <b>High</b> , or <b>Very High</b> .
<b>Threat Recency</b>	The number of days (0-180) since a <a href="#">threat event</a> occurred for the vulnerability.

### Threat Event Examples

Common threat events include:



- An exploit of the vulnerability
- A posting of the vulnerability exploit code in a public repository
- A discussion of the vulnerability in mainstream media
- Security research about the vulnerability
- A discussion of the vulnerability on social media channels
- A discussion of the vulnerability on the dark web and underground
- A discussion of the vulnerability on hacker forums



## Vulnerability Analysis Tools

On the **Vulnerabilities** page, you can use the drop-down box to select the vulnerability analysis tool you want to view.

To perform a common type of vulnerability analysis, see [View Vulnerabilities by Plugin](#) or [View Vulnerabilities by Host](#).

Analysis Tool	Description
<b>IP Summary</b>	<p>Summarizes host information, organized by IP address/agent ID. You can click the <b>IP Address</b> to view host details, as described in <a href="#">View Host Details</a>.</p> <p>For more information, see <a href="#">View Vulnerabilities by Host</a>.</p>
<b>Class A Summary</b> <b>Class B Summary</b> <b>Class C Summary</b>	<p>Summarizes host information.</p> <p>The vulnerability score for an address is computed by adding up the number of vulnerabilities at each severity level and multiplying it with the organization's severity score.</p> <p>Starting out with a Class A or Class B summary can identify more active network ranges for networks with a large number of active IP addresses.</p> <p>You can click a <b>Class A</b> or <b>Class B</b> row to view the <b>Class B</b> or <b>Class C</b> tool, filtered by the asset list you selected. You can click a <b>Class C</b> row to view the <b>IP Summary</b> tool, filtered by the asset list you selected.</p>
<b>Asset Summary</b>	<p>This tool summarizes the scores and counts of vulnerabilities for all dynamic or static asset lists.</p> <p>A breakdown of each asset's specific vulnerabilities and counts for each severity level is also included.</p> <p>You can click a count to view the <b>IP Summary</b> tool, filtered by the asset list you selected.</p>
<b>CCE Summary</b>	<p>This displays a summary of hosts which have Common Configuration Enumeration (CCE) vulnerabilities.</p> <p>You can click a count to view the <b>Vulnerability Summary</b> tool, filtered by</p>





Analysis Tool	Description
	the CCE vulnerability you selected.
<b>CVE Summary</b>	This view groups vulnerabilities based on their CVE ID, Hosts Total, and vulnerability count.
<b>DNS Name Summary</b>	<p>Tenable Security Center includes the ability to summarize information by vulnerable DNS name. The DNS Name Summary lists the matching hostnames, the repository, vulnerability count, and a breakdown of the individual severity counts.</p> <p>You can click a DNS name to view the <b>Vulnerability List</b> tool, filtered by the DNS name you selected.</p>
<b>List Mail Clients</b>	<p>Tenable Security Center uses Tenable Nessus Network Monitor to determine a unique list of email clients. The list contains the email client name, count of detections, and the detection method.</p> <p>You can click a count to view the <b>IP Summary</b> tool, filtered by the email client you selected.</p>
<b>List OS</b>	<p>Tenable Security Center understands both actively and passively fingerprinted operating systems. This tool lists what has been discovered.</p> <p>The method (active, passive, or event) of discovery is also indicated.</p> <p>You can click a count to view the <b>IP Summary</b> tool, filtered by operating system.</p>
<b>List Services</b>	<p>Tenable Security Center processes information from scans and creates a summary of unique services discovered. The service discovered, count of hosts, and detection method are listed.</p> <p>You can click a service to view the <b>IP Summary</b> tool, filtered by the service you selected.</p>
<b>List SSH Servers</b>	This tool utilizes active and passive scan results to create a unique list of known SSH servers. The list contains the ssh server name, count of detections, and the detection method.



Analysis Tool	Description
	<p><b>Tip:</b> Not all SSH servers run on port 22. Do not be surprised if you encounter SSH servers running on unexpected ports.</p> <p>You can click a count to view the <b>IP Summary</b> tool, filtered by the SSH server you selected.</p>
<b>List Software</b>	<p>Tenable Security Center processes information from scans and creates a summary of unique software packages discovered. The software name, count of hosts, and detection method are listed.</p> <p>You can click a software name to view the <b>IP Summary</b> tool, filtered by the software you selected.</p>
<b>List Web Clients</b>	<p>Tenable Security Center understands Tenable Nessus Network Monitor plugin ID 1735, which passively detects the web client in use. This tool lists the unique web clients detected. The list contains the user-agents, count of detections, and the detection method.</p> <p>You can click a count to view the <b>IP Summary</b> tool, filtered by the web client you selected.</p>
<b>List Web Servers</b>	<p>This tool takes the passive output from passive and active scans to create a unique list of known web servers. The list contains the web server name, count of detections, and the detection method.</p> <p><b>Tip:</b> Not all web servers run on port 80 or 443. Do not be surprised if you encounter web servers running on unexpected ports.</p> <p>You can click a count to view the <b>IP Summary</b> tool, filtered by the web server you selected.</p>
<b>MS Bulletin Summary</b>	<p>This tool filters vulnerabilities based on Microsoft Bulletin ID. Displayed are the IDs, Vulnerability Totals, Host Total, and Severity. This view is particularly useful in cases where Microsoft releases a new bulletin and a quick snapshot of vulnerable hosts is required.</p>
<b>Plugin Family</b>	<p>This tool charts the Nessus, Tenable Nessus Network Monitor, or Event</p>



Analysis Tool	Description
<b>Summary</b>	<p>plugin family as well as their relative counts based on severity level for all matching vulnerabilities.</p> <p>You can click a count to view the <b>Vulnerability List</b> tool, filtered by the plugin family you selected.</p>
<b>Port Summary</b>	<p>A summary of the ports in use is displayed for all matched vulnerabilities. Each port has its count of vulnerabilities as well as a breakdown for each severity level.</p> <p>You can click a port to view the <b>IP Summary</b> tool, filtered by the port you selected.</p>
<b>Protocol Summary</b>	<p>This tool summarizes the detected IP protocols such as TCP, UDP, and ICMP. The tool also breaks out the counts for each protocol's severity levels.</p> <p>You can click a count to view the <b>IP Summary</b> tool, filtered by the count you selected.</p>
<b>Remediation Summary</b>	<p>The Remediation Summary tool provides a list of remediation actions that may be taken to prioritize tasks that have the greatest effect to reduce vulnerabilities in systems. This list provides a solution to resolve a particular CPE on a given OS platform. The data provided includes:</p> <ul style="list-style-type: none"><li>• <b>Risk Reduction</b> —The percent you would reduce your risk by addressing the vulnerability in the solution. Tenable Security Center calculates the risk reduction percentage by dividing the score of the vulnerabilities in the solution by the score of all of the vulnerabilities on your network.</li><li>• <b>Hosts Affected</b> —The number of unique hosts that would be affected by performing the remediation action.</li><li>• <b>Vulnerabilities</b> —The count of vulnerabilities (Tenable Nessus plugins) that would be remediated by performing the remediation action.</li></ul>



Analysis Tool	Description
	<ul style="list-style-type: none"><li>• <b>Score</b> —This is calculated by adding up the score for each vulnerability that would be remediated by performing the remediation action.</li><li>• <b>CVE</b> —The number of distinct CVEs that would be remediated by performing the remediation action.</li><li>• <b>MS Bulletin</b> —The number of unique MS Bulletins that would be remediated by performing the remediation action.</li><li>• <b>Vulnerability %</b> —The count of vulnerabilities (Tenable Nessus plugins) that would be remediated by performing the remediation action over the total vulnerability count returned by the query as a percentage.</li></ul>
<b>Severity Summary</b>	<p>This tool considers all of the matching vulnerabilities and then charts the total number of info, low, medium, high, and critical vulnerabilities.</p> <p>You can click a count to view the <b>Vulnerability Summary</b> tool, filtered by the severity you selected.</p>
<b>User Responsibility Summary</b>	<p>This displays a list of the users who are assigned responsibility for the vulnerability based on the user's assigned asset list. Multiple users with the same responsibility are displayed on the same line. Users without any assigned responsibilities are not displayed in the list. Tenable Security Center populates this list after you assign an asset to a user account.</p>
<b>Vulnerability Detail List</b>	<p>Displays the details for a specific vulnerability instance on your network.</p> <div data-bbox="444 1465 1479 1581" style="border: 1px solid green; padding: 5px;"><p><b>Tip:</b> A vulnerability instance is a single instance of a vulnerability appearing on an asset, identified uniquely by plugin ID, port, and protocol.</p></div> <p>Important options include CVSS v2/ CVSS v3 score, CVSS v2/ CVSSv3 temporal score, VPR, VPR key drivers, availability of public exploit, CVE, BID, synopsis, description, and solution.</p> <p>For more information, see <a href="#">View Vulnerability Instance Details</a>.</p>



Analysis Tool	Description
<b>Vulnerability List</b>	<p>Displays a table of all vulnerability instances found on your network, organized by plugin ID.</p> <div data-bbox="444 363 1479 478" style="border: 1px solid green; padding: 5px;"><p><b>Tip:</b> A vulnerability instance is a single instance of a vulnerability appearing on an asset, identified uniquely by plugin ID, port, and protocol.</p></div> <p>For more information, see <a href="#">View Vulnerabilities by Plugin</a>.</p>
<b>Vulnerability Summary</b>	<p>Displays a table of all plugins associated with vulnerabilities on your network, organized by plugin ID.</p> <p>For more information, see <a href="#">View Vulnerabilities by Plugin</a>.</p>



## Vulnerability Analysis Filter Components

For general information about using filters, see [Filters](#).

Filter Component	Availability	Description
<b>Accept Risk</b>	Cumulative View	Displays vulnerabilities based on their Accepted Risk workflow status. Available choices include <b>Accepted Risk</b> or <b>Non-Accepted Risk</b> . Choosing both options displays all vulnerabilities regardless of acceptance status.
<b>Address</b>	All	This filter specifies an IPv4 or IPv6 address, range, or CIDR block to limit the viewed vulnerabilities. For example, entering <i>198.51.100.28/24</i> and/or <i>2001:DB8::/32</i> limits any of the web tools to show vulnerability data from the specified networks. You can enter addresses in a comma-separated list or on separate lines.
<b>Agent ID</b>	All	Displays results matching the specified agent UUID (Tenable UUID). An agent UUID uniquely identifies: <ul style="list-style-type: none"><li>• Agent-detected assets that may share a common IP address.</li><li>• Tenable OT Security assets that may not have an IP address. For more information, see <a href="#">Tenable OT Security Instances</a>.</li></ul>
<b>Application CPE</b>	All	Allows a text string search to match against available CPEs. The filter may be set to search based on a <b>contains</b> , <b>Exact Match</b> , or <b>Regex Filter</b> filter. The <b>Regex Filter</b> is based on Perl-compatible regular expressions (PCRE).
<b>Asset</b>	All	This filter displays systems from the assets you select. If more than one asset contains the systems from the primary asset (i.e., there is an intersect between the asset lists), those assets are displayed as well.



Filter Component	Availability	Description
		<p><b>Tip:</b> Use NOT, OR, and AND operators to exclude unwanted assets from the view.</p>
<b>Asset Criticality Rating (ACR)</b>	All	<p>(Requires Tenable Security Center+ license) Filters for vulnerabilities on hosts within the specified ACR range, between 0 and 10.</p> <p>For more information, see <a href="#">Asset Criticality Rating</a> in the <i>Tenable Vulnerability Management User Guide</i>.</p> <p><b>Tip:</b> To edit the ACR for an asset, see <a href="#">Edit an ACR Manually</a>.</p>
<b>Asset Exposure Score (AES)</b>	All	<p>(Requires Tenable Security Center+ license) Filters for hosts within the specified AES range, between 0 and 1000.</p> <p>For more information, see <a href="#">Asset Exposure Score</a> in the <i>Tenable Vulnerability Management User Guide</i>.</p>
<b>AES Severity</b>	All	<p>(Requires Tenable Security Center+ license) Filters for hosts with the specified AES severity.</p> <p>For more information, see <a href="#">Asset Exposure Score</a> in the <i>Tenable Vulnerability Management User Guide</i>.</p>
<b>Audit File</b>	All	Filters vulnerabilities by plugin IDs associated with the audit file used to perform a scan.
<b>CCE ID</b>	All	Displays results matching the entered CCE ID.
<b>CVE ID</b>	All	Displays vulnerabilities based on one or more CVE IDs. Type multiple IDs as a comma-separated list (e.g., <b>CVE-2011-3348,CVE-2011-3268,CVE-2011-3267</b> ).
<b>CVSS v2 Score</b>	All	Displays vulnerabilities within the chosen Common Vulnerability Scoring System version 2 (CVSS v2) score



Filter Component	Availability	Description
		range.
<b>CVSS v2 Vector</b>	All	Filters results based on a search against the CVSS v2 vector information.
<b>CVSS v3 Score</b>	All	Displays vulnerabilities within the chosen Common Vulnerability Scoring System version 3 (CVSS v3) score range.
<b>CVSS v3 Vector</b>	All	Filters results based on a search against the CVSS v3 vector information.
<b>Cross References</b>	All	Filters results based on a search against the cross reference information in a vulnerability.
<b>Data Format</b>	All	Displays results matching the specified data type: <b>IPv4</b> , <b>IPv6</b> , or <b>Agent</b> .
<b>DNS Name</b>	All	This filter specifies a DNS name to limit the viewed vulnerabilities. For example, entering host.example.com limits any of the web tools to only show vulnerability data from that DNS name.
<b>Exploit Available</b>	All	If set to yes, displays only vulnerabilities for which a known public exploit exists.
<b>Exploit Frameworks</b>	All	When set, the text option can be equal to or contain the text entered in the option.
<b>IAVM ID</b>	All	Displays vulnerabilities based on one or more IAVM IDs. Type multiple IDs as a comma-separated list (e.g., 2011-A-0005,2011-A-0007,2012-A-0004).
<b>MS Bulletin ID</b>	All	Displays vulnerabilities based on one or more Microsoft Bulletin IDs. Type multiple IDs as a comma-separated list (e.g., MS10-012,MS10-054,MS11-020).





Filter Component	Availability	Description
<b>Mitigated</b>	All	<p>Displays vulnerabilities for a specific mitigation status:</p> <ul style="list-style-type: none"><li>• <b>Previously Mitigated</b> —the vulnerability was previously mitigated but it reappeared in a scan and is currently vulnerable</li><li>• <b>Never Mitigated</b> —the vulnerability is currently vulnerable and has never been mitigated</li></ul> <p>For more information about mitigation, see <a href="#">Mitigated Vulnerabilities</a>.</p>
<b>NetBIOS Name</b>	All	<p>Displays vulnerabilities that match the specified NetBIOS name.</p> <div style="border: 1px solid blue; padding: 5px;"><p><b>Note:</b> This filter searches for exact matches only. Type the NetBIOS name as <i>workgroup \ NetBIOS name</i>.</p></div>
<b>Output Assets</b>	Asset Summary Analysis Tool	<p>This filter displays only the desired asset list systems.</p>
<b>Patch Published</b>	All	<p>Some plugins contain information about when a patch was published for a vulnerability. This filter allows the user to search based on when a vulnerability's patch became available:</p> <ul style="list-style-type: none"><li>• <b>None</b> (displays vulnerabilities that do not have a patch available)</li><li>• <b>Within the last day</b></li><li>• <b>Within the last 7 days</b></li><li>• <b>Within the last 30 days</b></li><li>• <b>More than 7 days ago</b></li></ul>



Filter Component	Availability	Description
		<ul style="list-style-type: none"><li>• <b>More than 30 days ago</b></li><li>• <b>Current Month</b></li><li>• <b>Last Month</b></li><li>• <b>Current Quarter</b> (during the current calendar year quarter)</li><li>• <b>Last Quarter</b> (during the previous calendar year quarter)</li><li>• <b>Current Year</b></li><li>• <b>Last Year</b></li><li>• <b>Custom Range</b> (during a specific range you specify)</li><li>• <b>Explicit</b> (at a specific time you specify)</li></ul>
<b>Plugin Family</b>	All	This filter chooses a Nessus or Tenable Nessus Network Monitor plugin family. Only vulnerabilities from that family display.
<b>Plugin ID</b>	All	Type the plugin ID desired or range based on a plugin ID. Available operators are equal to (=), not equal to (!=), greater than or equal (>=) and less than or equal to (<=).
<b>Plugin Modified</b>	All	Tenable plugins contain information about when a plugin was last modified. This filter allows users to search based on when a particular plugin was modified: <ul style="list-style-type: none"><li>• <b>Within the last day</b></li><li>• <b>Within the last 7 days</b></li><li>• <b>Within the last 30 days</b></li><li>• <b>More than 7 days ago</b></li></ul>



Filter Component	Availability	Description
		<ul style="list-style-type: none"><li>• <b>More than 30 days ago</b></li><li>• <b>Current Month</b></li><li>• <b>Last Month</b></li><li>• <b>Current Quarter</b> (during the current calendar year quarter)</li><li>• <b>Last Quarter</b> (during the previous calendar year quarter)</li><li>• <b>Current Year</b></li><li>• <b>Last Year</b></li><li>• <b>Custom Range</b> (during a specific range you specify)</li><li>• <b>Explicit</b> (at a specific time you specify)</li></ul>
<b>Plugin Name</b>	All	<p>Using the <b>Contains</b> option, type all or a portion of the actual plugin name. For example, entering <b>MS08-067</b> in the plugin name filter displays vulnerabilities using the plugin named <b>MS08-067: Microsoft Windows Server Service Crafted RPC Request Handling Remote Code Execution (958644) (unauthenticated check)</b>. Similarly, entering the string <b>unauthenticated</b> displays a list of vulnerabilities with that string in the plugin name.</p> <p>Use the <b>Regex Match</b> option to filter plugin names based on Perl-compatible regular expressions (PCRE).</p>
<b>Plugin Published</b>	All	<p>Tenable plugins contain information about when a plugin was first published. This filter allows users to search based on when a particular plugin was created:</p> <ul style="list-style-type: none"><li>• <b>Within the last day</b></li><li>• <b>Within the last 7 days</b></li></ul>



Filter Component	Availability	Description
		<ul style="list-style-type: none"><li>• <b>Within the last 30 days</b></li><li>• <b>More than 7 days ago</b></li><li>• <b>More than 30 days ago</b></li><li>• <b>Current Month</b></li><li>• <b>Last Month</b></li><li>• <b>Current Quarter</b> (during the current calendar year quarter)</li><li>• <b>Last Quarter</b> (during the previous calendar year quarter)</li><li>• <b>Current Year</b></li><li>• <b>Last Year</b></li><li>• <b>Custom Range</b> (during a specific range you specify)</li><li>• <b>Explicit</b> (at a specific time you specify)</li></ul>
<b>Plugin Type</b>	All	Select whether to view all plugin types or passive, active, event, or compliance vulnerabilities.
<b>Port</b>	All	<p>This filter is in two parts. First the equality operator is specified to allow matching vulnerabilities with the same ports, different ports, all ports less than or all ports greater than the port filter. The port filter allows a comma separated list of ports. For the <b>larger than</b> or <b>less than</b> filters, only one port may be used.</p> <div style="border: 1px solid blue; padding: 5px;"><p><b>Note:</b> All host-based vulnerability checks are reported with a port of 0 (zero).</p></div>
<b>Protocol</b>	All	This filter provides boxes to select TCP, UDP, or ICMP-based vulnerabilities.



Filter Component	Availability	Description
<b>Recast Risk</b>	Cumulative View	Display vulnerabilities based on their Recast Risk workflow status. Available choices include <b>Recast Risk</b> or <b>Non-Recast Risk</b> . Choosing both options displays all vulnerabilities regardless of recast risk status.
<b>Repositories</b>	All	Display vulnerabilities from the chosen repositories.
<b>STIG Severity</b>	All	Display vulnerabilities with the chosen STIG severity in the plugins database.
<b>Scan Policy Plugins</b>	All	Display vulnerabilities found by the currently enabled plugins in the scan policy. For more information, see <a href="#">Plugins Options</a> .
<b>Severity</b>	All	Displays vulnerabilities with the selected severity. For more information, see <a href="#">CVSS vs. VPR</a> .
<b>Users</b>	All	Allows selection of one or more users who are responsible for the vulnerabilities.
<b>Vulnerability Discovered</b>	All	Tenable Security Center tracks when each vulnerability was first discovered. This filter allows you to see when vulnerabilities were discovered: <ul style="list-style-type: none"><li>• <b>Within the last day</b></li><li>• <b>Within the last 7 days</b></li><li>• <b>Within the last 30 days</b></li><li>• <b>More than 7 days ago</b></li><li>• <b>More than 30 days ago</b></li><li>• <b>Current Month</b></li><li>• <b>Last Month</b></li><li>• <b>Current Quarter</b> (during the current calendar year)</li></ul>



Filter Component	Availability	Description
		<p>quarter)</p> <ul style="list-style-type: none"><li>• <b>Last Quarter</b> (during the previous calendar year quarter)</li><li>• <b>Current Year</b></li><li>• <b>Last Year</b></li><li>• <b>Custom Range</b> (during a specific range you specify)</li><li>• <b>Explicit</b> (at a specific time you specify)</li></ul> <div data-bbox="683 768 1479 1045" style="border: 1px solid blue; padding: 5px;"><p><b>Note:</b> The discovery date is based on when the vulnerability was first imported into Tenable Security Center. For Tenable Nessus Network Monitor, this date does not match the exact vulnerability discovery time as there is normally a lag between the time that Tenable Nessus Network Monitor discovers a vulnerability and the import occurs.</p></div> <div data-bbox="683 1066 1479 1304" style="border: 1px solid blue; padding: 5px;"><p><b>Note:</b> Days are calculated based on 24-hour periods prior to the current time, not calendar days. For example, if the report run time was 1/8/2019 at 1:00 PM, using a 3-day count would include vulnerabilities starting 1/5/2019 at 1:00 PM and not from 12:00 AM.</p></div>
<b>Vulnerability Last Observed</b>	Cumulative View	<p>This filter allows the user to see when the vulnerability was last observed by Tenable Nessus, Tenable Log Correlation Engine, or Tenable Nessus Network Monitor:</p> <ul style="list-style-type: none"><li>• <b>Within the last day</b></li><li>• <b>Within the last 7 days</b></li><li>• <b>Within the last 30 days</b></li><li>• <b>More than 7 days ago</b></li><li>• <b>More than 30 days ago</b></li></ul>



Filter Component	Availability	Description
		<ul style="list-style-type: none"><li>• <b>Current Month</b></li><li>• <b>Last Month</b></li><li>• <b>Current Quarter</b> (during the current calendar year quarter)</li><li>• <b>Last Quarter</b> (during the previous calendar year quarter)</li><li>• <b>Current Year</b></li><li>• <b>Last Year</b></li><li>• <b>Custom Range</b> (during a specific range you specify)</li><li>• <b>Explicit</b> (at a specific time you specify)</li></ul> <div data-bbox="683 961 1479 1276" style="border: 1px solid #0070C0; padding: 5px;"><p><b>Note:</b> The observation date is based on when the vulnerability was most recently imported into Tenable Security Center. For Tenable Nessus Network Monitor, this date does not match the exact vulnerability discovery as there is normally a lag between the time that Tenable Nessus Network Monitor discovers a vulnerability and the import occurs.</p></div>
<b>Vulnerability Mitigated</b>	Mitigated View	<p>This filter allows the user to filter results based on when the vulnerability was mitigated:</p> <ul style="list-style-type: none"><li>• <b>Within the last day</b></li><li>• <b>Within the last 7 days</b></li><li>• <b>Within the last 30 days</b></li><li>• <b>More than 7 days ago</b></li><li>• <b>More than 30 days ago</b></li><li>• <b>Current Month</b></li></ul>



Filter Component	Availability	Description
		<ul style="list-style-type: none"><li>• <b>Last Month</b></li><li>• <b>Current Quarter</b> (during the current calendar year quarter)</li><li>• <b>Last Quarter</b> (during the previous calendar year quarter)</li><li>• <b>Current Year</b></li><li>• <b>Last Year</b></li><li>• <b>Custom Range</b> (during a specific range you specify)</li><li>• <b>Explicit</b> (at a specific time you specify)</li></ul>
<b>Vulnerability Priority Rating (VPR)</b>	All	<p>Displays vulnerabilities within the chosen VPR range. For more information, see <a href="#">CVSS vs. VPR</a>.</p> <div data-bbox="683 1010 1479 1167" style="border: 1px solid green; padding: 5px;"><p><b>Tip:</b> The <b>Vulnerabilities</b> page displays vulnerabilities by plugin. The VPR that appears is the highest VPR of all the vulnerabilities associated with that plugin.</p></div>
<b>Vulnerability Published</b>	All	<p>When available, Tenable plugins contain information about when a vulnerability was published. This filter allows users to search based on when a particular vulnerability was published:</p> <ul style="list-style-type: none"><li>• <b>All</b></li><li>• <b>Within the last day</b></li><li>• <b>Within the last 7 days</b></li><li>• <b>Within the last 30 days</b></li><li>• <b>More than 7 days ago</b></li><li>• <b>More than 30 days ago</b></li></ul>





Filter Component	Availability	Description
		<ul style="list-style-type: none"><li>• <b>Current Month</b></li><li>• <b>Last Month</b></li><li>• <b>Current Quarter</b> (during the current calendar year quarter)</li><li>• <b>Last Quarter</b> (during the previous calendar year quarter)</li><li>• <b>Current Year</b></li><li>• <b>Last Year</b></li><li>• <b>Custom Range</b> (during a specific range you specify, up to 999 days ago)</li><li>• <b>Explicit</b> (at a specific time you specify)</li></ul>
<b>Vulnerability Text</b>	All	Displays vulnerabilities containing the entered text (e.g., php 5.3) or regex search term.



## View Vulnerabilities by Host

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can drill into analysis views, filtering by host, to view vulnerabilities and vulnerability instances on a host.

To view vulnerabilities and vulnerability instances associated with a host:

1. Log in to Tenable Security Center via the user interface.
2. Click **Analysis > Vulnerabilities**.

The **Vulnerabilities** page appears.

3. In the drop-down box, click **IP Summary**.

The **IP Summary** tool appears.

4. Filter the tool to locate the host where you want to view vulnerability instance details, as described in [Filters](#) and [Vulnerability Analysis Filter Components](#).

5. To customize the table, see [Interact with a Customizable Table](#).

6. To view details of a vulnerability instance:

- a. Click the row for the vulnerability instance for which you want to view the details.

The **Vulnerability List** tool appears, filtered by the vulnerability instance you selected.

In this tool, you can:

Options	Actions
<b>Jump to Vulnerability Detail</b>	View the <b>Vulnerability Detail List</b> page. This page displays the synopsis, description, solution, and the plugin output of the vulnerability.
<b>Export</b>	Export data as a .csv or a .pdf file, as described in <a href="#">Export Vulnerability Data</a> .



<b>Save</b>	<ul style="list-style-type: none"><li>• <b>Save Query</b> —Save a query, as described in <a href="#">Add or Save a Query</a>.</li><li>• <b>Save Asset</b> —Save an asset, as described in <a href="#">Assets</a>.</li></ul>
<b>More</b>	<ul style="list-style-type: none"><li>• <b>Open Ticket</b> —Open a ticket, as described in <a href="#">Open a Ticket</a>.</li><li>• <b>Set as Default View</b> —Set this view as your default view.</li></ul>
<b>Cumulative</b>	Switch between viewing cumulative vulnerabilities or mitigated vulnerabilities, as described in <a href="#">View Cumulative or Mitigated Vulnerabilities</a> .
<b>Mitigated</b>	Switch between viewing cumulative vulnerabilities or mitigated vulnerabilities, as described in <a href="#">View Cumulative or Mitigated Vulnerabilities</a> .
Filters side bar	Apply a filter, as described in <a href="#">Apply a Filter</a> and <a href="#">Vulnerability Analysis Filter Components</a> .
Vulnerability row	<ul style="list-style-type: none"><li>• Click the <b>Plugin ID</b> to view the plugin details associated with the vulnerability, as described in <a href="#">View Plugin Details</a>.</li><li>• Click the <b>IP Address</b> to view the host details for the vulnerability, as described in <a href="#">View Host Details</a>.</li><li>• Click the row to view the vulnerability instance details in the <b>Vulnerability Detail List</b> tool, as described in <a href="#">View Vulnerability Instance Details</a>.</li></ul> <div style="border: 1px solid green; padding: 5px;"><p><b>Tip:</b> A vulnerability instance is a single instance of a vulnerability appearing on an asset, identified uniquely by plugin ID, port, and protocol.</p></div>

7. To view the host details of an instance:

- a. Click the **IP Address** link.

The **System Information** pane appears. For more information, see [View Host Details](#).



## View Vulnerabilities by Plugin

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can drill into analysis views, filtering by plugin, to view vulnerabilities and vulnerability instances related to that plugin.

To view vulnerabilities and vulnerability instances associated with a plugin:

1. Log in to Tenable Security Center via the user interface.
2. Click **Analysis > Vulnerabilities**.

The **Vulnerabilities** page appears.

3. In the drop-down box, click **Vulnerability Summary**.

The **Vulnerability Summary** tool appears.

In this tool, you can:

Options	Actions
<b>Jump to Vulnerability Detail</b>	View the <b>Vulnerability Detail List</b> page. This page displays the synopsis, description, solution, and the plugin output of the vulnerability.
<b>Export</b>	Export data as a .csv or a .pdf file, as described in <a href="#">Export Vulnerability Data</a> .
<b>Save</b>	<ul style="list-style-type: none"><li>• <b>Save Query:</b> Save a query, as described in <a href="#">Add or Save a Query</a>.</li><li>• <b>Save Asset:</b> Save an asset, as described in <a href="#">Assets</a>.</li></ul>
<b>More</b>	<ul style="list-style-type: none"><li>• <b>Open Ticket:</b> Open a ticket, as described in <a href="#">Open a Ticket</a>.</li><li>• <b>Set as Default View:</b> Set this view as your default view.</li></ul>
<b>Cumulative</b>	Switch between viewing cumulative vulnerabilities or mitigated vulnerabilities, as described in <a href="#">View Cumulative or Mitigated Vulnerabilities</a> .



Mitigated	Switch between viewing cumulative vulnerabilities or mitigated vulnerabilities, as described in <a href="#">View Cumulative or Mitigated Vulnerabilities</a> .
Table	Customize the table, as described in <a href="#">Interact with a Customizable Table</a> .
Filters side bar	Apply a filter, as described in <a href="#">Apply a Filter</a> and <a href="#">Vulnerability Analysis Filter Components</a> .
Plugin row	<ul style="list-style-type: none"><li>• Click the <b>Plugin ID</b> to view the plugin details for the plugin, as described in <a href="#">View Plugin Details</a>.</li><li>• Click the row to view the vulnerability details in the <b>Vulnerability List</b> tool.</li></ul>
Plugin row	You can right-click any row to do the following: <ul style="list-style-type: none"><li>• View <b>Asset Summary</b> tool, <b>DNS Summary</b> tool, or <b>IP Summary</b> tool.</li><li>• Create an accept risk rule, as described in <a href="#">Add an Accept Risk Rule</a>.</li><li>• Create a recast risk rule, as described in <a href="#">Add a Recast Risk Rule</a>.</li><li>• Launch a remediation scan, as described in <a href="#">Launch a Remediation Scan</a>.</li></ul>

4. Click the row for the plugin where you want to view vulnerability instance details.

The **Vulnerability List** tool appears, filtered by the plugin you selected.

In this tool, you can:

Options	Actions
<b>Jump to Vulnerability Detail</b>	View the <b>Vulnerability Detail List</b> page. This page displays the synopsis, description, solution, and the plugin output of the vulnerability.
<b>Export</b>	Export data as a .csv or a .pdf file, as described in <a href="#">Export Vulnerability</a>



	<a href="#">Data.</a>
<b>Save</b>	<ul style="list-style-type: none"><li>• <b>Save Query</b> —Save a query, as described in <a href="#">Add or Save a Query</a>.</li><li>• <b>Save Asset</b> —Save an asset, as described in <a href="#">Assets</a>.</li></ul>
<b>More</b>	<ul style="list-style-type: none"><li>• <b>Open Ticket</b> —Open a ticket, as described in <a href="#">Open a Ticket</a>.</li><li>• <b>Set as Default View</b> —Set this view as your default view.</li></ul>
<b>Cumulative</b>	Switch between viewing cumulative vulnerabilities or mitigated vulnerabilities, as described in <a href="#">View Cumulative or Mitigated Vulnerabilities</a> .
<b>Mitigated</b>	Switch between viewing cumulative vulnerabilities or mitigated vulnerabilities, as described in <a href="#">View Cumulative or Mitigated Vulnerabilities</a> .
Filters side bar	Apply a filter, as described in <a href="#">Apply a Filter</a> and <a href="#">Vulnerability Analysis Filter Components</a> .
Vulnerability row	<ul style="list-style-type: none"><li>• Click the <b>Plugin ID</b> to view the plugin details associated with the vulnerability, as described in <a href="#">View Plugin Details</a>.</li><li>• Click the <b>IP Address</b> to view the host details for the vulnerability, as described in <a href="#">View Host Details</a>.</li><li>• Click the row to view the vulnerability instance details in the <b>Vulnerability Detail List</b> tool, as described in <a href="#">View Vulnerability Instance Details</a>.</li></ul> <div style="border: 1px solid green; padding: 5px; margin-top: 10px;"><p><b>Tip:</b> A vulnerability instance is a single instance of a vulnerability appearing on an asset, identified uniquely by plugin ID, port, and protocol.</p></div>



## View Vulnerability Instance Details

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can drill into analysis views to view details for a specific instance of a vulnerability found on your network.

**Tip:** A vulnerability instance is a single instance of a vulnerability appearing on an asset, identified uniquely by plugin ID, port, and protocol.

To view vulnerability instance details:

1. Log in to Tenable Security Center via the user interface.
2. Click **Analysis > Vulnerabilities**.

The **Vulnerabilities** page appears.

3. In the drop-down box, click **Vulnerability Detail List**.

The **Vulnerability Detail List** tool appears.

In this tool, you can:

Section	Actions
<b>Options</b> menu	<ul style="list-style-type: none"><li>• Export data as a .csv or a .pdf file, as described in <a href="#">Export Vulnerability Data</a>.</li><li>• Save a query, as described in <a href="#">Add or Save a Query</a>.</li><li>• Save an asset.</li><li>• Open a ticket, as described in <a href="#">Open a Ticket</a>.</li><li>• Set this view as your default view.</li><li>• Switch between viewing cumulative vulnerabilities or mitigated vulnerabilities, as described in <a href="#">View Cumulative or Mitigated Vulnerabilities</a>.</li></ul>



arrows	Click the arrows to view other vulnerability instances related to the plugin.
toolbar	<ul style="list-style-type: none"><li>• Launch a remediation scan, as described in <a href="#">Launch a Remediation Scan</a>.</li><li>• Create an accept risk rule, as described in <a href="#">Add an Accept Risk Rule</a>.</li><li>• Create a recast risk rule, as described in <a href="#">Add a Recast Risk Rule</a>.</li></ul>
<b>Synopsis and Description</b>	View information about the plugin, vulnerability instance, and affected assets.
<b>Solution</b>	View the Tenable-recommended action to remediate the vulnerability.
<b>See Also</b>	View related links about the plugin or vulnerability.
<b>Discovery</b>	View details about when the vulnerability was discovered and last seen on your network.
<b>Host Information</b>	View details about the asset.
<b>Risk Information</b>	View metrics (e.g., CVSS score, VPR, etc.) about the risk associated with the vulnerability.
<b>Exploit Information</b>	View details about the exploit.
<b>Plugin Details</b>	View details about the plugin.
<b>VPR Key Drivers</b>	View the key drivers Tenable used to calculate the VPR score. For more information, see <a href="#">CVSS vs. VPR</a> .
<b>Vulnerability Information</b>	View Common Platform Enumeration (CPE) details.
<b>Reference Information</b>	View related links to the CVE, BID, MSFT, CERT, and other industry materials about the vulnerability.





## View Host Details

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can drill into analysis views to view details for a specific host on your network.

To view host details from the **Vulnerabilities** page:

1. Log in to Tenable Security Center via the user interface.
2. Click **Analysis > Vulnerabilities**.

The **Vulnerabilities** page appears.

3. In the drop-down box, click **Vulnerability List**.

The **Vulnerability List** tool appears.

4. In the **IP Address** column, click the IP address link to view host details for a specific vulnerability instance.

**Tip:** A vulnerability instance is a single instance of a vulnerability appearing on an asset, identified uniquely by plugin ID, port, and protocol.

The host details panel appears.

Section	Actions
<b>System Information</b>	<p>View information about the host system.</p> <ul style="list-style-type: none"><li>• <b>IP Address</b> —The host's IP address, if available.</li><li>• <b>UUID</b> —The host's UUID, if available.</li><li>• <b>NetBIOS Name</b> —The host's NetBIOS name, if available.</li><li>• <b>DNS Name</b> —The host's DNS name, if available.</li><li>• <b>MAC Address</b> —The host's MAC address, if available.</li><li>• <b>OS</b> —The operating system running on the host, if available.</li><li>• <b>CPE</b> —The host's application common platform enumeration</li></ul>



	<p>(CPE).</p> <ul style="list-style-type: none"><li>• <b>Score</b> —The cumulative score for all vulnerability instances on the host. For more information about vulnerability scoring, see <a href="#">CVSS vs. VPR</a>.</li></ul> <div style="border: 1px solid green; padding: 5px;"><p><b>Tip:</b> A vulnerability instance is a single instance of a vulnerability appearing on an asset, identified uniquely by plugin ID, port, and protocol.</p></div> <ul style="list-style-type: none"><li>• <b>Repository</b> —The repository that contains vulnerability data associated with the host.</li><li>• <b>Last Scan</b> —The date and time Tenable Security Center last scanned the host.</li><li>• <b>Passive Data</b> —Indicates whether a passive scan detected the vulnerability.</li><li>• <b>Compliance Data</b> —Indicates whether the scan that detected the vulnerability included compliance plugins.</li></ul>
<b>Vulnerabilities</b>	View the number of vulnerabilities on the host, organized by severity category. For more information, see <a href="#">CVSS vs. VPR</a> .
<b>Links</b>	<ul style="list-style-type: none"><li>• View SANS and ARIN links for the host. If configured, this section also displays custom resource links.</li><li>• Click a resource link to view details for the current IP address/agent IDs. For example, if the current IP address was a publicly registered address, click the ARIN link to view the registration information for that address.</li></ul>
<b>Assets</b>	View the asset lists containing the asset. For more information, see <a href="#">Assets</a> .

To view host details from the **Host Assets** page:



1. Log in to Tenable Security Center via the user interface.
2. Click **Assets > Host Assets**.

The **Host Assets** page appears.

3. Click the row for the host.

The **Host Asset Details** page appears.

Section	Action
<b>Host Information</b>	<p>View general information about the host.</p> <ul style="list-style-type: none"><li>• <b>Name</b> —The name of the host.</li><li>• <b>System Type</b> —The host's device type, as determined by plugin 54615.</li><li>• <b>Operating System</b> —The operating system running on the host, if available.</li><li>• <b>IP Addresses</b> —The host's IP address, if available.</li><li>• <b>MAC Addresses</b> —The host's MAC address, if available.</li><li>• <b>Asset ID</b> —The ID of the host.</li><li>• <b>Repository</b> —The repository that contains vulnerability data associated with the host.</li></ul>
<b>Asset Exposure Score</b>	<p>(Requires Tenable Security Center+ license) View the host's AES. For more information, see <a href="#">Asset Exposure Score</a> in the <i>Tenable Vulnerability Management User Guide</i>.</p>
<b>Asset Criticality Rating</b>	<p>(Requires Tenable Security Center+ license) View the host's ACR and details about modifications to the ACR.</p> <ul style="list-style-type: none"><li>• <b>Overwrite Reasoning</b> —The justification for overwriting the host's ACR.</li><li>• <b>Notes</b> —Notes associated with overwriting the host's ACR.</li></ul>



Section	Action
	<ul style="list-style-type: none"><li>• <b>Overwritten By</b> —The user that overwrote the host's ACR.</li><li>• <b>ACR By Key Drivers</b> —The key drivers used to calculate the host's ACR.</li></ul> <p>For more information, see <a href="#">Asset Criticality Rating</a> and <a href="#">ACR Key Drivers</a> in the <i>Tenable Vulnerability Management User Guide</i>.</p> <p>To edit the host's ACR, see <a href="#">Edit an ACR Manually</a>.</p>
<b>Scan Information</b>	<p>View scan information related to the host.</p> <ul style="list-style-type: none"><li>• <b>First Seen</b> —The date and time Tenable Security Center first detected the host on your network.</li><li>• <b>Last Seen</b> —The date and time last Tenable Security Center detected the host on your network.</li><li>• <b>Source</b> —The type of scan that discovered the host on your network: <b>Tenable Nessus Scan</b>, <b>Tenable Nessus Network Monitor</b>, <b>Log Correlation Engine</b>, or <b>Agent Scan</b>.</li></ul>
<b>Findings</b> tab	<ul style="list-style-type: none"><li>• View the vulnerabilities detected on the host. For more information, see <a href="#">CVSS vs. VPR</a>.</li><li>• Customize the table, as described in <a href="#">Interact with a Customizable Table</a>.</li></ul>
<b>Installed Software</b> tab	<p>View the software packages installed on the host, if available.</p> <p>Customize the table, as described in <a href="#">Interact with a Customizable Table</a>.</p>



## View Plugin Details

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can drill into analysis views to view details for a specific instance of a vulnerability found on your network.

**Tip:** A vulnerability instance is a single instance of a vulnerability appearing on an asset, identified uniquely by plugin ID, port, and protocol.

To view plugin details:

1. Log in to Tenable Security Center via the user interface.
2. Click **Analysis > Vulnerabilities**.

The **Vulnerabilities** page appears.

3. In the drop-down box, click **Vulnerability Summary**.

The **Vulnerability Summary** tool appears.

4. To customize the table, see [Interact with a Customizable Table](#).

5. In the **Plugin ID** column, click the plugin ID to view plugin details for a specific plugin.

The **Plugin Details** panel appears.

In this panel, you can:

Section	Actions
<b>Description</b>	View information about the plugin, vulnerability instance, and affected assets.
<b>Solution</b>	View the Tenable-recommended action to remediate the vulnerability.
<b>Vulnerability Priority Rating (VPR) Key Drivers</b>	View the key drivers Tenable used to calculate the vulnerability VPR. For more information, see <a href="#">CVSS vs. VPR</a> .



<b>CVE and BID</b>	View related links to the CVE and BID materials about the vulnerability.
<b>Cross-References</b>	View related documentation for the vulnerability.
<b>See Also</b>	View related links about the plugin or vulnerability.



## Export Vulnerability Data

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can export data from the **Vulnerabilities** page as a .csv or a .pdf file.

To export data from the **Vulnerabilities** page:

1. Log in to Tenable Security Center via the user interface.
2. Click **Analysis > Vulnerabilities**.

The **Vulnerabilities** page appears.

3. In the **Export** drop-down box, click **Export > Export as CSV** or **Export as PDF**.

**Note:** If the record count (rows displayed) of any CSV export is greater than 1,000, Tenable Security Center prompts you for the name of the CSV report you want to generate. After generation, you can download the report from the **Report Results** page.

4. Select or clear the check boxes to indicate which columns you want to appear in the exported file.
5. Click **Submit**.

Tenable Security Center exports the vulnerability data.



## Event Analysis

The **Events** display page contains an aggregation of security events from Tenable Log Correlation Engine. Events can be viewed in a list format with options similar to the Vulnerability interface.

### Raw Syslog Events

Tenable Security Center's event filters includes a **Syslog Text** option to narrow down the scope of a set of events, and supports the use of keyword searches for active filters.

### Active vs. Archived

In the upper-right corner, click **Active** or **Archived** to switch between the active and archived data. This selection determines whether the displayed events are pulled from the active or an archived event database. The Active view is the default that displays all currently active events. The Archived view prompts for the selection of the Log Correlation Engine and an Archive Silo from which the event data is displayed. In the example below, the Log Correlation Engine and Silo date range are displayed to help the user choose the correct archive data for analysis.

The screenshot shows a dialog box titled "Select Archive Silo" with a close button (X) in the top right corner. Inside the dialog, there is a section labeled "LCE" with a dropdown menu. Below that is a section labeled "Silo" with a list of radio buttons and date ranges. The selected option is "Oct 09, 2012 - Feb 02, 2013". At the bottom of the dialog is a teal "Submit" button.

Silo
<input type="radio"/> Aug 16, 2013 - Sep 21, 2013
<input type="radio"/> Aug 06, 2013 - Aug 16, 2013
<input checked="" type="radio"/> Oct 09, 2012 - Feb 02, 2013
<input type="radio"/> Aug 31, 2012 - Oct 09, 2012
<input type="radio"/> Jul 09, 2012 - Aug 31, 2012
<input type="radio"/> Jun 19, 2012 - Jul 09, 2012
<input type="radio"/> Jun 19, 2012 - Jun 19, 2012





## Analysis Tools

A wide variety of analysis tools are available for comprehensive event analysis.

When viewing the analysis tool results, clicking on result will generally take you to the next level of detail for the analysis. For instance, from the Type summary page clicking on a type will display the Normalized Event Summary. Clicking on an even in that list will display the List of Events page featuring that event. Along each progression a new drop-down menu will appear allowing for easy access to either pivot to another analysis tool based on the current view or to return to the previous view.

Additionally most results will have a gear icon next to them. This icon will provide summaries, normally based on time restrictions or a view of the vulnerability summary for the affected host, around that item's result.

For more information, see [Event Analysis Tools](#).

## Load Query

The **Load Query** option enables users to load a predefined query and display the current dataset against that query. Click on **Load Query** in the filters list to display a box with all available queries. The query names are displayed in alphabetical order. After clicking on an individual query, the vulnerability view is changed to match the query view for the current dataset.

## Event Analysis Filters

For more information, see [Event Analysis Filter Components](#).

## Event Analysis Actions

You can use the **Options** drop-down menu to perform the following event analysis actions.

### Save Query

You can save the current view as a query for reuse. For more information about queries, see [Queries](#).

### Save Asset

Event results can be saved to an asset list for later use. For more information, see [Assets](#).



## Save Watchlist

Event results can be saved to a watchlist asset list for later use. For more information, see [Assets](#).

## Open Ticket

Tickets are used within Tenable Security Center to assist with the assessment and remediation of vulnerabilities and security events. For more information, see [Open a Ticket](#).

## View Settings

When available, this setting controls the columns displayed in your view.

## Switch to Archived / Switch Archive / Switch to Active

The **Switch to Archived** item is displayed when viewing active event data and when selected will present a dialog to choose the archived event data to display by Tenable Log Correlation Engine and date range.

The **Switch Archive** menu item is displayed when viewing archived event data. Selecting this option displays the same menu and selections as above to select a different archive silo for viewing.

The **Switch to Active** menu item is displayed when viewing archived data and when selected, changes the view to active event data for analysis.

## Export as CSV

Event results can be exported to a comma-separated file for detailed analysis outside of Tenable Security Center by clicking on the Options drop-down menu and then the **Export as CSV** option. When selected, a window opens with an option to choose the columns to be included in the CSV file.

If the record count (rows displayed) of any CSV export is greater than 1,000 records, a note is displayed that prompts for the name of the CSV report to be generated. When complete, the report can be downloaded from the **Report Results** page. For CSV exports of under 1,000 records, the browser's standard **Save As** dialog window is displayed.

Once the appropriate selections are made, click the **Submit** button to create the CSV file or **Cancel** to abort the process.



## Event Analysis Tools

A wide variety of analysis tools are available for comprehensive event analysis. Clicking on the drop-down menu indicating the current view (Type Summary by default) displays a list of analysis tools to choose from.

When viewing the analysis tool results, clicking on result will generally take you to the next level of detail for the analysis. For instance, from the Type summary page clicking on a type will display the Normalized Event Summary. Clicking on an even in that list will display the List of Events page featuring that event. Along each progression a new drop-down menu will appear allowing for easy access to either pivot to another analysis tool based on the current view or to return to the previous view.

Additionally most results will have a gear icon next to them. This icon will provide summaries, normally based on time restrictions or a view of the vulnerability summary for the affected host, around that item's result.

Tool	Description
Asset Summary	<p>This tool can be used to see how certain types of activity, remote attackers, or non-compliant events have occurred across different asset groups.</p> <p>Clicking on the <b>Total</b> count for the listed asset displays a Type Summary analysis tool.</p>
Connection Summary	<p>This tool lists connections made between two different hosts by source and destination IP address and the counts of connections between them.</p> <p>Clicking on a host will display the Type Summary analysis tool.</p>
Date Summary	<p>When analyzing large amounts of data, it is often useful to get a quick summary of how the data set manifests itself across several dates.</p> <p>For example, when analyzing a suspected attacker's IP address, creating a filter for that IP address and looking at the type of events is simple enough. However, displaying that same data over the last few days or weeks can paint a much more interesting picture of a potential attacker's activity.</p> <p>Selecting a date will display the Type Summary analysis tool.</p>



Tool	Description
Destination IP Summary	<p>This tool displays events listed by the destination IP address recorded. The table lists the Tenable Log Correlation Engine it was discovered on, the IP address, and the count. Clicking on the information icon next to the IP address displays the system information pertaining to the host IP address.</p> <p>Clicking on one of the hosts displays the Type Summary analysis tool.</p>
Detailed Event Summary	<p>This tool displays a summary of the various events based on their full event name and count. Clicking on an event displays the List of Events analysis tool.</p>
Event Trend	<p>This analysis tool displays an event trend area graph with total events over the last 24 hours. Modify the filters for this graph to display the desired event trend view.</p>
IP Summary Class A Summary Class B Summary Class C Summary	<p>Tenable Security Center provides the ability to quickly summarize matching IP addresses by single IP address, Class A, Class B, and Class C addresses.</p> <p>The IP Summary tool displays the associated Tenable Log Correlation Engine server along with the IP address of the reporting system and about the event count for that system.</p> <p>Clicking on an IP address displays a Host Detail window for that IP address. Clicking the information icon next to the IP address displays information about the NetBIOS Name (if known), DNS Name (if known), MAC address (if known), OS (if known), Score, Repository, Last Scan, Passive Data, Compliance Data, and Vulnerability severity counts. The Assets box displays which asset lists the IP address belongs to. The Useful Links box contains a list of resources that can be queried by IP address. Clicking on one of the Resource links causes the resource to be queried with the current IP address. For example, if the current IP address was a publicly registered address, clicking on the ARIN link causes the ARIN database to be queried for the registration information for that address. If custom resources have been added by an administrative user (via the <b>Manage IP Address Information Links</b> selection under the <b>Customization</b> tab), they will be displayed here.</p>



Tool	Description
	<p>The Sum by Class A, B, and C tools work by displaying matching addresses. Clicking on the number displayed in the Total column will display the Type Summary for that IP address range.</p>
List of Events	<p>This tool displays a line of data for each matching event. The line includes many pieces of information such as time, event name, number of correlated vulnerabilities involved IP addresses, and sensor.</p>
Normalized Event Summary	<p>This tool summarizes a listing of all normalized events and their count for the chosen time period. Normalized events are lower-level events that have been assigned a Tenable name based on Tenable Log Correlation Engine scripts parsing of the log records (e.g., Snort-HTTP_Inspect).</p> <p>Clicking on the event name displays the List of Events analysis tool.</p>
Port Summary	<p>A port summary can be invoked. This tool produces a table of the top used ports and combines counts for source and destination ports into one overall count.</p> <p>Clicking on the port will display a Type Summary of events filtered for that port.</p> <div data-bbox="407 1171 1479 1287" style="border: 1px solid blue; padding: 5px;"><p><b>Note:</b> Port 0 events are host-based events that are not specific to any particular TCP/UDP port.</p></div>
Protocol Summary	<p>This tool summarizes counts of events based on IP protocols.</p> <p>Clicking on the event total displays a Type Summary view of events filtered by the selected protocol.</p>
Raw Syslog Events	<p>Users can choose to view the original log message or IDS event for full forensic analysis.</p> <p>It is recommended that users attempt some sort of filtering match first before attempting to find their desired event. Users will typically sort their results and drill into the list until they find what they are looking for before attempting to view the raw data.</p>



Tool	Description
Sensor Summary	<p>This tool displays the unique event counts for any query from unique sensor types.</p> <p>When a sensor is clicked on, the Type Summary analysis tool is displayed for events from the selected sensor.</p>
Source IP Summary	<p>This tool displays events listed by the source IP address recorded. The table lists the Tenable Log Correlation Engine it was discovered on, the IP address, and the count. Clicking on the information icon next to the IP address displays the system information pertaining to the host IP address.</p> <p>Clicking on one of the hosts displays the Type Summary analysis tool.</p>
Type Summary	<p>This tool displays the matching unique event types and the number of corresponding events for each.</p> <p>The unique event types are based on normalized logs or events such as firewall, system, correlated, network and IDS. These types are high-level types used to describe event types (e.g., login or lce).</p> <p>Clicking on any of the event counts displays the Normalized Event Summary for the type.</p>
User Summary	<p>This tool displays the matching unique event types and the number of corresponding events for each user when user tracking is enabled in Tenable Log Correlation Engine.</p> <p>The unique event types are based on normalized logs such as firewall, system, correlated, network, and IDS.</p> <p>Clicking on any of the event counts under the <b>Total</b> column will display the Type Summary analysis tool.</p>



## Event Analysis Filter Components

Filters limit the results of the event data displayed and can be added, modified, or reset as desired. For more information, see [Filters](#).

The **Events** page also supports using a filter bar for filtering. To display the filter bar, in the toolbar, click **More > Show Filter Bar**.

**Note:** The filter bar does not display or adjust the time frame filter.

Filter Component	Description
<b>Address</b>	Specifies an IP address, range, or CIDR block to limit the displayed events. For example, entering 198.51.100.64/24 limits any of the web tools to show only the event data from that network. You can enter addresses on separate lines or comma separated.
<b>Asset</b>	Filter the event by the specified asset list. <b>Tip:</b> Use NOT, OR, and AND operators to exclude unwanted assets from the view.
<b>Destination Address</b>	Specifies an IP address or CIDR block to limit the displayed events based on destination. For example, entering 198.51.100.64/24 limits any of the analysis tools to show only the event data with destination IPs in that block. Addresses can be comma-separated.
<b>Destination Asset</b>	Filter the destination address of the event data by the specified asset list. <b>Tip:</b> Use NOT, OR, and AND operators to exclude unwanted assets from the view.
<b>Destination Port</b>	This filter is in two parts. Specify the type of filter to allow matching events with the same ports (=) or different ports (≠). The port filter may specify a single, comma separated list of ports or range of ports (e.g., 8000-8080).
<b>Detailed Event</b>	This is the detailed event name given by the IDS vendor. For example, an event received from a Snort sensor can have a detailed event name of



Filter Component	Description
	DOUBLE DECODING ATTACK, which means that HTTP_INSPECT 119:2:1 fired and was sent to the Log Correlation Engine.
<b>Direction</b>	Filter by event direction of All by default or select Inbound, Outbound, or Internal.
<b>Log Correlation Engines</b>	Specify the Log Correlation Engine(s) to obtain events from by checking the box next to the choices.
<b>Normalized Event</b>	The name given to the event by the Log Correlation Engine after the Log Correlation Engine runs its PRM and TASL scripts against it.
<b>Port</b>	<p>This filter is in two parts. Specify the type of filter to allow matching vulnerabilities with the specified ports (<math>=</math>), excluding ports (<math>\neq</math>), ports greater than or equal to (<math>\geq</math>), or ports less than or equal to (<math>\leq</math>). The specified and excluding port filter may specify a single port, comma-separated list of ports, or range of ports (for example, 8000-8080).</p> <div style="border: 1px solid blue; padding: 5px;"><p><b>Note:</b> Tenable Security Center reports all host-based vulnerability checks with a port of 0 (zero).</p></div>
<b>Protocol</b>	Specify the protocol of the event TCP, UDP, or ICMP.
<b>Repositories</b>	Specify the Repositories to obtain events from. You can search the repositories using the search filter at the top. You can select multiple repositories from the list.
<b>Sensor</b>	Filter the events by sensor using the equal ( $=$ ) or not equal ( $\neq$ ) operators.
<b>Source Address</b>	Specifies an IP address or CIDR block to limit the displayed events based on source. For example, entering 198.51.100.64/24 limits any of the analysis tools to show only the event data with source IPs in that block. Addresses can be comma separated.
<b>Source Asset</b>	Filter the source address of the event data by asset list and select an asset list from those available or the NOT operator to exclude asset lists. After





Filter Component	Description
	you add each list, the AND or OR operator are available to customize the combining of asset lists.
<b>Source Port</b>	This filter is in two parts. Specify the type of filter to allow matching events with the same ports (=) or different ports (≠). The port filter may specify a single port, comma-separated list of ports, or range of ports (for example, 8000-8080).
<b>Syslog Text</b>	(Raw Syslog Events Analysis Tool) String to search for within the filtered event.
<b>Targeted IDS Events</b>	This filter box selects IDS events that have targeted systems and ports with vulnerabilities likely to be exploited by the detected attack. This is determined by comparing the host's vulnerabilities (CVE, etc.) against those tied to the actual IDS event.
<b>Timeframe</b>	<div style="border: 1px solid green; padding: 5px;"><b>Tip:</b> Tenable Security Center always uses this filter. By default, it is set for the last 24 hours, based on the time of the page load.</div> <p>By default, Tenable Security Center displays an explicit timeframe using the last 24 hours. Specify either an explicit or relative timeframe for the event filter. Choosing explicit allows for selecting dates and times from a calendar and time sliders for the start and end time. Relative timeframes, available from the drop-down box, range using various time periods from the last 15 minutes to the last 12 months and All.</p>
<b>Type</b>	Use this to filter by the event type. For example: error, lce, login, intrusion, etc..
<b>User</b>	Specify only events tied to a particular username.

**Note:** Clicking on **Clear Filters** causes the filters to return to the default settings.



## Mobile Analysis

The **Mobile** page displays lists of vulnerabilities discovered by scanning an ActiveSync, Apple Profile Manager, AirWatch, Good, and/or MobileIron MDM servers.

For information about mobile analysis filtering, see [Mobile Analysis Filter Components](#).

### Mobile Analysis Actions

You can use the options in the toolbar to perform the following mobile analysis actions:

- Save Query
- Export as CSV or PDF

#### Save Query

You can save the current view as a query for reuse. For more information about queries, see [Queries](#).

#### Export as CSV or PDF

You can export mobile results in the current view to a comma-separated file or a PDF for detailed analysis outside of Tenable Security Center.

**Note:** If the record count (rows displayed) of any CSV export is greater than 1,000 records, a note is displayed that prompts for the name of the CSV report to be generated. When complete, the report can be downloaded from the **Report Results** page. For CSV exports of under 1,000 records, the browser's standard **Save As** dialog window is displayed.

Select the columns of data you want exported, then click **Submit**.



## Mobile Analysis Filter Components

For general information about using filters, see [Filters](#).

Option	Description
Analysis Tool Filter	
<b>Analysis Tool</b>	This drop-down box is used to choose the analysis tool used by the filter. This is the same as selecting the desired analysis tool from the <b>Analysis &gt; Mobile</b> dialog.
<b>Active Filters</b>	Displays the existing filters and allows the user to selectively remove filters as needed.
Filters	
<b>Identifier</b>	A text based search filter that looks at the <b>Identifier</b> option in the repository.
<b>MDM Type</b>	A drop-down box to select the MDM server type of ActiveSync, Apple Profile Manager, Good, AirWatch, and MobileIron MDM server.
<b>Model</b>	A text based search filter that looks at the <b>Model</b> option in the repository.
<b>Operating System CPE</b>	A text based search filter that looks at the <b>Operating System CPE</b> option in the repository.
<b>Plugin ID</b>	Type the Plugin ID to filter results on.
<b>Plugin Output</b>	Filter results based on a text search of plugin output.
<b>Repositories</b>	Display vulnerabilities from the chosen repositories.
<b>Serial Number</b>	This is a text based search filter that looks at the <b>Serial Number</b> option in the repository.
<b>Severity</b>	Displays vulnerabilities with the selected severity ( <b>Info, Low, Medium, High, Critical</b> ).
<b>Username</b>	This is a text based search filter that looks at the <b>User</b> option in the repository.



Option	Description
<b>Version</b>	This is a text based search filter that looks at the <b>OS Version</b> option in the repository.
<b>Vulnerability Last Observed (Cumulative only)</b>	This filter allows the user to see when the vulnerability was last observed.



# Reports

You can create reports in Tenable Security Center to share data with users in other organizations. For more information about which users can access what data, see [Tenable Security Center Architecture](#).

Tenable provides reporting through an assortment of report templates and customizable report formats, including PDF and CSV.

Custom CyberScope, DISA ASR, and DISA ARF reports are also available for specialized needs. An administrator user must enable [report generation options](#) before organizational users can generate reports with CyberScope, DISA ASR, or DISA ARF data.

Custom CyberScope, DISA ASR, DISA ARF, and DISA Consolidated ARF reports are also available for specialized needs. An administrator user must enable [report generation options](#) before organizational users can generate reports with CyberScope, DISA ASR, DISA ARF, or DISA Consolidated ARF data.

In Tenable Security Center, organizational users can create custom reports or template-based reports, as described in [Create a Custom Report](#) or [Create a Template Report](#).

**Note:** To create custom PDF reports and template-based reports, you must install either the Oracle Java JRE or OpenJDK (along with their accompanying dependencies) on the system hosting the Tenable Security Center.

**Tip:** Tenable provides report templates through the Tenable Security Center feed. For a complete index of Tenable-provided report templates, see the [Tenable Security Center Report Templates](#) blog.

For more information, see:

- [Manage Reports](#)
- [Manage Report Results](#)
- [CyberScope and DISA Report Attributes](#)
- [Report Images](#)



# Manage Reports

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

On the **Reports** page of Tenable Security Center, you can manage report definitions and launch reports. For more information, see [Reports](#).

To manage reports:

1. In the left navigation, click **Reporting > Reports**.

The **Reports** page appears.

2. Do any of the following:
  - [Filter existing report definitions in the reports table](#).
  - [Create a custom report](#).
  - [Create a template report](#).
  - [Edit a report definition](#).
  - [Edit a report outline](#).
  - [Manage filters for a chapter report](#).
  - [Manage filters for a non-chapter report](#).
  - [View a report definition](#).
  - [Copy a report definition](#).
  - [Export a report definition](#).
  - [Import a report definition](#).
  - [Delete a report definition](#).
  - [Launch a report on demand](#).
  - [Add a report to a scan](#).



# Create a Custom Report

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information, see [Reports](#).

Before you begin:

- If you want to create a CyberScope, DISA ASR, DISA ARF, or DISA Consolidated ARF report, confirm an administrator user enabled the corresponding report generation options, as described in [Configuration Settings](#).
- If you want to create a CyberScope, DISA ARF, or DISA Consolidated ARF report, create report attributes as described in [CyberScope and DISA Report Attributes](#).

To create a custom report definition:

1. Log in to Tenable Security Center via the user interface.
2. In the left navigation, click **Reporting > Reports**.

The **Reports** page appears.

3. At the top of the table, click **Add**.

The **Report Template** page appears.

4. In the **Other** section, click a report tile. For more information, see [Report Templates](#).
5. [Configure the options](#) for the report.

Tenable Security Center displays options relevant to the report format you selected.

6. (Optional) [Edit the report outline](#).

7. Click **Submit** to save your report.

Tenable Security Center saves your configuration.



# Create a Template Report

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

Template reports are formatted reports that can be customized using chapter and target selections. For more information, see [Reports](#).

To create a template report:

1. Log in to Tenable Security Center via the user interface.
2. In the left navigation, click **Reporting > Reports**.

The **Reports** page appears.

3. At the top of the table, click **Add**.

The **Report Template** page appears.

4. Do one of the following to locate a specific template:

- In the **Search Templates** box in the top right corner of the page, search for a specific template by keyword.

**Tip:** After the initial search, you can limit search results by template category.

- In the **Common** section, click a template category to view the related templates. For more information, see [Report Templates](#).

5. Click a template report.

**Note:** Each template description specifies which Tenable Security Center data must be available to obtain a complete report. For more information, see [Data Required for Template-Based Reports](#).

6. (Optional) In the **Chapters** section, select which chapters from the template you want to include in your report. By default, the report includes all chapters from the template.
7. In the **Focus** section, do one of the following:

Target all systems in the report.





**Note:** This is the default setting.

To return to this setting, click **All Systems** in the **Targets** drop-down box.

Target specific assets in the report.

- a. In the **Targets** drop-down box, click **Assets**.
- b. Select **Assets** and **Repositories**.

Target specific IP addresses in the report.

- a. In the **Targets** drop-down box, click **IP Addresses**.
- b. In the **IP Addresses** box, type the IP address or addresses where you want the report to focus. Use commas to separate multiple addresses.
- c. In the **Repositories** box, select a target repository or repositories.

Target specific repositories in the report.

- a. In the **Targets** drop-down box, click **Repositories**.
  - b. In the **Repositories** box, select a target repository or repositories.
8. (Optional) Edit the default text in the **Description** box.

**Note:** You cannot modify any information in the **Details** section of the page.

9. Click **Add**.

Tenable Security Center creates a report based on the template and displays the **Reports** page. The new report appears as the last entry in reports table.

10. (Optional) Modify report options that are common to both custom and template reports. For more information, see [Report Options](#).

For example, the default value for the **Schedule** option for all template-based reports is **On Demand**. If you want to run the report automatically, modify the **Schedule** option for the report.

11. (Optional) Customize the report outline, as described in [Edit a Report Outline](#).










For example, you might want to use text elements to add your business context to template-based chapters.



## Data Required for Template-Based Reports

Each report template description contains icons that represent which types of data must be available on Tenable Security Center to obtain a complete report.

Hover the cursor over the icon to display the label.

Icon	Label	Action Required
	Asset Required	Configure an IPv4/IPv6 repository and store scan results in the repository; see <a href="#">Local Repositories</a> and <a href="#">IPv4/IPv6 Repositories</a> .
	Audit File Required	Upload audit files and add them to your scan policy; see <a href="#">Audit Files</a> and <a href="#">Scan Policies</a> .
	Compliance Data Required	
	Local Checks Required	Configure and run credentialed scans; see <a href="#">Active Scans</a> .
	Mobile Data Required	Configure a mobile repository and store scan results in the repository; see <a href="#">Mobile Repositories</a> .
	Active Data Required	Configure a Tenable Nessus scanner and run active scans. For more information, see <a href="#">Tenable Nessus Scanners</a> and <a href="#">Active Scans</a> .
	Passive Data Required	Configure a Tenable Nessus Network Monitor (NNM) scanner; see <a href="#">Tenable Nessus Network Monitor Instances</a> .
	Event Data Required	Configure a Tenable Log Correlation Engine server; see <a href="#">Tenable Log Correlation Engines</a> .



## Report Templates

Tenable Security Center provides a selection of report templates and customizable report formats. You can configure a Tenable-provided report template or you can create a fully customized report from one of the available formats. For more information, see [Reports](#).

For a complete index of Tenable-provided report templates, see the [Tenable Security Center Report Templates](#) blog.

Template	Description
<b>Common</b>	
<b>Compliance &amp; Configuration Assessment</b>	Reports that aid with configuration, change, and compliance management.
<b>Discovery &amp; Detection</b>	Reports that aid in trust identification, rogue detection, and new device discovery.
<b>Executive</b>	Reports that provide operational insight and metrics geared towards executives.
<b>Monitoring</b>	Reports that provide intrusion monitoring, alerting, and analysis.
<b>Security Industry Trends</b>	Reports related to trends, reports, and analysis from industry leaders.
<b>Threat Detection &amp; Vulnerability Assessments</b>	Reports that aid with identifying vulnerabilities and potential threats.
<b>Other</b>	
<b>PDF</b>	Create a Portable Document Format (PDF) report that can be viewed universally.
<b>CSV</b>	Create a Comma Separated Values (CSV) report that can be imported into spreadsheets or databases.
<b>DISA ARF</b>	(Requires <a href="#">Report Generation</a> configuration) Create a report that meets



	the standards of the Defense Information Systems Agency Assessment Results Format (DISA ARF).
<b>DISA Consolidated ARF</b>	(Requires <a href="#">Report Generation</a> configuration) Create a report that meets the standards of the Defense Information Systems Agency Consolidated Assessment Results Format (DISA Consolidated ARF).
<b>DISA ASR</b>	(Requires <a href="#">Report Generation</a> configuration) Create a report that meets the standards of the Defense Information Systems Agency Assessment Summary Results (DISA ASR).
<b>CyberScope</b>	(Requires <a href="#">Report Generation</a> configuration) Create a report that meets CyberScope reporting standards to support FISMA compliance.



## Edit a Report Definition

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

In Tenable Security Center, you can edit both custom reports and reports based on templates.

To edit a report definition:

1. In the left navigation, click **Reporting > Reports**.

The **Reports** page appears.

2. In the reports table, click the name of the report you want to edit.

-or-

Right-click the row for the report you want to edit, and click **Edit**.

The **Edit Report** page appears.

3. In the reports table, click the name of the report you want to edit.

-or-

Right-click the row for the report you want to edit, and click **Edit**.

The **Edit Report** page appears.

4. [Modify the report options](#).

**Note:** Tenable Security Center displays options relevant to the report type.

5. (PDF and template reports only) [Edit the report outline](#).

6. Click **Submit** to save your changes to the report.



## Report Options

In Tenable Security Center, you can configure the options described below for both custom and template reports.

Option descriptions below are grouped by the section where they appear in the **Add Report** and **Edit Report** pages. In the option description tables, the **Relevant Reports** column specifies which report types use each option.

**Note:** Tenable Security Center classifies a template-based report as a PDF report. You can configure the same options for that report as you can for a PDF report.

During template report creation, Tenable Security Center set these options to default values. You can change these options for a template report only after creation is complete.

- [General Options](#)
- [Report Options](#)
- [Definition Options](#)
- [Display Options](#)
- [Distribution Options](#)

### General Options

Option	Description	Relevant Reports
<b>Name</b>	Name assigned to the report.	Any
<b>Description</b>	Descriptive text for the report.	Any
<b>Schedule</b>	Determines how often the report runs. Options are <b>On Demand</b> , <b>Now</b> , <b>Once</b> , <b>Daily</b> , <b>Weekly</b> , or <b>Monthly</b> . When you select a frequency from the drop-down box, Tenable Security Center displays additional options for the selected time frame.	Any
<b>Attribute Sets</b>	Predefined operational attributes that add required	DISA ARF, DISA



Option	Description	Relevant Reports
	information to DISA ARF, DISA Consolidated ARF, or CyberScope report types. The drop-down box displays only the attribute set defined for the report you are currently creating.	Consolidated ARF, Cyber-Scope
<b>ASR Content</b>	When creating a report, this drop-down box offers a selection of Benchmark, IAVM, CVE, or Plugin ID to be included.	DISA ASR, DISA Consolidated ARF
<b>ASR Record Format</b>	This drop-down box determines the format (Summary or Detail) of the DISA ASR report.	DISA ASR
<b>Include ARF</b>	When enabled, allows for the inclusion of a DISA attribute set for the report.	DISA ASR
<b>Benchmarks</b>	Benchmarks are generated after a scan using certain audit files that have been successfully run against at least one target system.	DISA ASR, DISA Consolidated ARF, Cyber-Scope

## Report Options

Option	Description	Relevant Reports
<b>Style</b>	<p>A compound value that specifies the report style, paper size, and orientation. For example, <b>Plain, Letter</b></p> <p>Report styles include:</p> <ul style="list-style-type: none"><li>• <b>Plain</b> —a report with basic graphs</li><li>• <b>Tenable</b> —a report with basic graphs and a <a href="#">footer logo</a> on the cover page</li><li>• <b>Tenable 3D</b> —a report with enhanced 3D graphs and a <a href="#">footer logo</a> on the cover page</li></ul>	PDF





Option	Description	Relevant Reports
	<p data-bbox="402 289 1253 405"><b>Note:</b> If an administrator configured a Classification Type banner, plain report styles are the only options listed.</p> <p data-bbox="402 436 678 468">Paper sizes include:</p> <ul data-bbox="451 510 1235 541" style="list-style-type: none"><li data-bbox="451 510 1235 541">• <b>Letter</b> —the standard 8.5 inches x 11 inches letter size</li></ul> <p data-bbox="483 573 1253 772"><b>Note:</b> Letter size is the default paper size, used by options that do not explicitly state a paper size. For example, the paper size for <b>Plain, Landscape</b> is letter size.</p> <ul data-bbox="451 804 1203 835" style="list-style-type: none"><li data-bbox="451 804 1203 835">• <b>A4</b> —the standard 8.27 inches x 11.69 inches A4 size</li></ul> <p data-bbox="402 877 789 909">Orientation options include:</p> <ul data-bbox="451 951 732 982" style="list-style-type: none"><li data-bbox="451 951 732 982">• <b>Portrait</b> —vertical</li></ul> <p data-bbox="483 1014 1253 1171"><b>Note:</b> Portrait is the default orientation, used by options that do not explicitly state an orientation. For example, the orientation for <b>Plain, Letter</b> is vertical.</p> <ul data-bbox="451 1203 813 1234" style="list-style-type: none"><li data-bbox="451 1203 813 1234">• <b>Landscape</b> —horizontal</li></ul>	
<b>Include Cover Page</b>	<p data-bbox="402 1276 1179 1308">Include a cover page in the report. Cover pages include:</p> <ul data-bbox="451 1350 1247 1812" style="list-style-type: none"><li data-bbox="451 1350 654 1381">• a <a href="#">cover logo</a></li><li data-bbox="451 1423 691 1455">• the scan <b>Name</b></li><li data-bbox="451 1497 1084 1528">• the date and time you generated the report</li><li data-bbox="451 1570 1247 1696">• the date and time Tenable Security Center imported the scan results, if you generated the report from scan results</li><li data-bbox="451 1738 1195 1812">• the scan result <b>ID</b>, if you generated the report from scan results</li></ul>	PDF



Option	Description	Relevant Reports
<b>Include Header</b>	Include a predefined header in the report.	PDF
<b>Include Footer</b>	Include a predefined footer in the report.	PDF
<b>Include Table of Contents</b>	Include a table of contents with the report.	PDF
<b>Include Index</b>	Include an Index with the report.	PDF
<b>Cover Logo</b>	<p>Specifies which image to use for the lower-left footer logo on the cover page of the report. The default logo is the Tenable logo. To add a custom logo, see <a href="#">Report Images</a>.</p> <div style="border: 1px solid blue; padding: 5px;"><p><b>Note:</b> The Plain report style suppresses this footer logo on the cover page.</p></div>	PDF
<b>Footer Logo</b>	Specifies which image to use for the lower-left footer logo on all pages <i>except</i> the cover page. The default logo is the Tenable logo. To add a custom logo, see <a href="#">Report Images</a> .	PDF
<b>Watermark</b>	Specifies a watermark for each page of the report. The default is no watermark. To add a custom watermark, see <a href="#">Report Images</a> .	PDF
<b>Encrypt PDF</b>	Protect the PDF with a password and 256-bit Advanced Encryption Standard (AES) encryption. When enabled, the <b>Password</b> text box appears. Enter a password to use to open the report and view its contents.	PDF

## Definition Options

Tenable Security Center displays definition options relevant to the report or report element type.

Option	Description	Relevant Reports
<b>Add Chapter</b>	The primary component in the report organization.	PDF



Option	Description	Relevant Reports
	Chapters are listed in the table of contents for the report and consist of sections and elements. For more information, see <a href="#">Add a Custom Chapter to a Report</a> and <a href="#">Edit a Report Outline</a> .	
<b>Add Template Chapter</b>	A predefined chapter from a Tenable-provided report template. For more information, see <a href="#">Add a Template Chapter to a Report</a> .	PDF
<b>Query</b>	A list of predefined queries you can use to retrieve data for the report. For more information, see <a href="#">Queries</a> .	CSV, DISA ARF, DISA Consolidated ARF, DISA ASR, Cyber-Scope; Iterator, Table, and Chart elements in PDF
<b>Type</b>	The type of data to include in the report.	CSV; Iterator, Table, and Chart elements in PDF
<b>Source</b>	<p>The source of the data to include in the report.</p> <p>For CSV reports, valid values for this field differ based on the setting of the <b>Type</b> option:</p> <ul style="list-style-type: none"><li>• If <b>Type</b> is set to <b>Vulnerability</b>, valid <b>Source</b> values are:<ul style="list-style-type: none"><li>◦ <b>Cumulative</b>—All vulnerabilities, regardless of whether the vulnerabilities have been remediated or not</li><li>◦ <b>Mitigated</b>—Remediated vulnerabilities</li><li>◦ <b>Individual Scan</b>—Vulnerabilities identified in a specific scan</li></ul></li></ul>	CSV, DISA ARF, DISA Consolidated ARF, DISA ASR, Cyber-Scope; Iterator, Table, and Chart elements in PDF



Option	Description	Relevant Reports
	<p data-bbox="609 262 1096 462"><b>Note:</b> If you select <b>Individual Scan</b>, Tenable Security Center displays the <b>Selected Scan</b> option, which allows you to select a scan to use as the basis of the report:</p> <ol data-bbox="641 493 1104 871" style="list-style-type: none"><li>Click one of the predefined date ranges, or click <b>Custom Range</b> and enter starting and ending days for the range.</li><li>Click <b>Fetch Scans</b> to view a list of possible scans within the date range.</li><li>Click the scan you want to use in the drop-down box.</li></ol> <ul data-bbox="462 934 1096 1155" style="list-style-type: none"><li>If <b>Type</b> is set to <b>Event</b>, valid <b>Source</b> values are:<ul data-bbox="544 1050 1015 1155" style="list-style-type: none"><li>◦ <b>Active</b>—Currently active events</li><li>◦ <b>Archive</b>—Archived events</li></ul></li></ul> <p data-bbox="609 1207 1096 1407"><b>Note:</b> If you select <b>Archive</b>, Tenable Security Center displays additional options, allowing you to select the <b>LCE</b> that collected the events and the <b>Silo</b> that stores the archived events.</p> <ul data-bbox="462 1459 1112 1543" style="list-style-type: none"><li>If <b>Type</b> is set to <b>Mobile</b>, <b>Ticket</b>, or <b>Alert</b>, this option is absent.</li></ul> <p data-bbox="414 1575 1120 1816">For DISA ARF, DISA Consolidated ARF, and DISA ASR reports, you do not set the <b>Type</b> option. Valid <b>Source</b> values are limited to <b>Cumulative</b> and <b>Individual Scan</b>, which operate in the same way as they do for CSV reports.</p>	



Option	Description	Relevant Reports
<b>Tool</b>	Select the tool Tenable Security Center uses to analyze the data in the report.	CSV; Iterator, Table, and Chart elements in PDF
<b>Filters</b>	Specifies additional criteria to refine report data. For more information, see <a href="#">Manage Filter Components for a Non-Chapter Report</a> .	CSV, DISA ARF, DISA Consolidated ARF, DISA ASR, Cyber-Scope; Iterator, Table, and Chart elements in PDF
<b>Find/Update Filters</b>	This option appears after you add at least one chapter to the report.  For more information, see <a href="#">Manage Filter Components for Multiple Elements</a> .	PDF

## Display Options

These options allow you to specify column format information format. A selection to define the columns and number of results to appear in the report is then available for configuration.

Option	Description	Relevant Reports
<b>Results Displayed</b>	The number of results included in the CSV file.	CSV; Iterator, Table, Bar Chart, and Pie Chart elements in PDF
<b>Sort Column</b>	The column that Tenable Security Center uses to sort results in the CSV file.  Available columns depend on: <ul style="list-style-type: none"><li>• the <b>Type</b> you selected in the <b>Definition</b> options</li><li>• the <b>Display Columns</b> value you select in the <b>Display</b> options</li></ul>	CSV; Iterator, Table, Bar Chart, and Pie Chart elements in PDF



Option	Description	Relevant Reports
<b>Sort Direction</b>	The sort direction for results in the CSV file.	CSV; Iterator, Table, Bar Chart, and Pie Chart elements in PDF
<b>Display Columns</b>	The columns included in the results file. Available columns depend on <b>Definition</b> options you select.  <b>Tip:</b> The <b>Display Columns</b> appear in the results file in the order in which you select them.	CSV; Iterator, Table, Bar Chart, and Pie Chart elements in PDF

## Distribution Options

Distribution options specify the actions Tenable Security Center takes when a report run completes.

Option	Description	Relevant Reports
<b>Email Users</b>	Select Tenable Security Center users to whom Tenable Security Center emails the completed report. The drop-down list includes only users with defined email addresses.	Any
<b>Email Addresses (cc)</b>	Add CC email addresses where Tenable Security Center emails the completed report. You can specify multiple email addresses, separated by commas.	Any
<b>Email Addresses (bcc)</b>	Add Bcc email addresses where Tenable Security Center emails the completed report. You can specify multiple email addresses, separated by commas.	Any
<b>Share</b>	Allows you to select which Tenable Security Center users within your organization can view the completed report in Tenable Security Center. Use this option if organizational policies prohibit emailing potentially sensitive data.	Any
<b>Publishing</b>	Allows you to select predefined publishing sites where Ten-	Any



Option	Description	Relevant Reports
<b>Sites</b>	able Security Center uploads the completed report. For more information, see <a href="#">Publishing Sites Settings</a> .	



## Edit a Report Outline

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

In Tenable Security Center, the report outline allows you to modify the structure of a PDF or template-based report.

The outline consists of the following components:

Component	Outline Level	Description
chapter	primary	Highest-level component. Can contain any type of element (grouping, text, chart).
element	subordinate	A grouping, text, or chart element. Can be nested in a chapter or grouping component.

To edit a report outline:

1. In the left navigation, click **Reporting > Reports**.

The **Reports** page appears.

2. In the reports table, click the name of the report you want to edit.

-or-

Right-click the row for the report you want to edit, and click **Edit**.

The **Edit Report** page appears.

3. On the left side of the page, click **Definition**.

The report outline appears. The outline is, by default, expanded.

4. In the report outline, you can:

- Expand or collapse elements nested in the outline by clicking **Collapse All** or **Expand All** at the top of the outline.





- Expand or collapse elements nested in an individual chapter or element by clicking the arrow next to the element.
- [Add a custom chapter.](#)
- [Add a template chapter.](#)
- [Add or edit a report element.](#)
- [Reorder chapters and elements in a report.](#)
- Delete a report element by clicking the delete icon next to the element.

**Note:** Tenable Security Center does not ask you to confirm this deletion. However, the deletion is not final until you save all changes to the report.

5. Click **Submit** to save your changes to the report.



## Add a Custom Chapter to a Report

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

In Tenable Security Center, you can add custom chapters to PDF or template-based reports.

To add a custom chapter to a report definition:

1. In the left navigation, click **Reporting > Reports**.

The **Reports** page appears.

2. In the reports table, click the name of the report you want to edit.

-or-

Right-click the row for the report you want to edit, and click **Edit**.

The **Edit Report** page appears.

3. On the left side of the page, click **Definition**.

The report outline appears. This outline is, by default, expanded. For more information, see [Edit a Report Outline](#).

4. At the bottom of the report outline, click **Add Chapter**

**Tip:** If the report contains multiple chapters or sections, scroll down to locate the bottom navigation bar. It can also be helpful to click **Collapse All** on the top navigation bar to collapse the outline to its highest-level components.

The **Add Chapter** page appears.

5. In the **Name** box, enter a title for the chapter.
6. In the **Location** box, select a relative location for the chapter within the report.
7. In the **Style** box, select a style for the report.
8. Click **Submit**.

Tenable Security Center adds the chapter to the report and displays the **Edit Report** page.

9. Click **Submit** to save your changes to the report.



## Add a Template Chapter to a Report

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

In Tenable Security Center, you can add template chapters to template reports and custom PDF reports.

To add a template-based chapter to a report definition:

1. In the left navigation, click **Reporting > Reports**.

The **Reports** page appears.

2. In the reports table, click the name of the report you want to edit.

-or-

Right-click the row for the report you want to edit, and click **Edit**.

The **Edit Report** page appears.

3. On the left side of the page, click **Definition**.

The report outline appears. This outline is, by default, expanded. For more information, see [Edit a Report Outline](#).

4. At the bottom of the outline, click **Add Template Chapter**.

5. Do one of the following:

- In the **Search Templates** box in the top right corner of the page, search for a specific template by keyword.

**Tip:** After the initial search, you can limit search results by template category.

- Click a template category icon to view the related templates.

6. Click the report template that contains chapters you want to include in your custom report.

7. (Optional) Modify the default options for the report template:



- a. In the **Chapters** section, select which chapters from the template you want to include in your report. By default, the report includes all chapters from the template.
- b. Do one of the following:
  - In the **Focus** section, target all systems in the report.

This is the default setting. To return to this setting, click **All Systems** in the **Targets** drop-down box.
  - Target specific assets in the report.
    - i. In the **Targets** drop-down box, click **Assets**.
    - ii. Select **Assets** and **Repositories**.
  - Target specific IP addresses in the report.
    - i. In the **Targets** drop-down box, click **IP Addresses**.
    - ii. In the **IP Addresses** box, type the IP address or addresses where you want the report to focus. Use commas to separate multiple addresses.
    - iii. In the **Repositories** box, select a target repository or repositories.
  - Target specific repositories in the report.
    - i. In the **Targets** drop-down box, click **Repositories**.
    - ii. In the **Repositories** box, select a target repository or repositories.
- c. (Optional) Edit text in the **Description** box.

**Note:** You cannot modify any information in the **Details** section.

8. Click **Add**.

Tenable Security Center adds the template chapter or chapters to your custom report and displays the **Add Report** page again.

9. (Optional) Change the template chapter options.



- a. Click the edit icon next to the chapter you added.
  - b. In the **Name** box, edit the chapter title.
  - c. In the **Location** box, change the relative location for the chapter within the report.
  - d. In the **Style** box, select a style for the chapter.
  - e. Click **Submit** to save your changes to the chapter.
10. Click **Submit** to save your changes to the report.



## Add or Edit a Report Element

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can add or edit elements within chapters or grouping elements in Tenable Security Center reports.

To add or edit a report element:

1. In the left navigation, click **Reporting > Reports**.

The **Reports** page appears.

2. In the reports table, click the name of the report you want to edit.

-or-

Right-click the row for the report you want to edit, and click **Edit**.

The **Edit Report** page appears.

3. On the left side of the page, click **Definition**.

The report outline appears. This outline is, by default, expanded. For more information, see [Edit a Report Outline](#).

4. Do one of the following:

- Click **Add Element** next to the element where you want to add the element.
- Click the edit icon next to the element you want to change.

**Tip:** To display **Add Element** or the edit icon, hover the cursor over the element.

5. Configure any of the following types of elements:

- [Grouping](#)
- [Text](#)
- [Charts](#)

6. Click **Submit** to save your changes to the report.



## Configure a Grouping Element in a Report

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

Grouping elements in Tenable Security Center reports include:

Type	Description	Relevant Reports
Group	Groups associated elements on the same page.	PDF
Section	Allows you to organize content within chapters.	PDF
Iterator	Allows you to specify how the report groups its data. For example, if an <b>Iterator Type</b> of <b>Port Summary</b> is chosen for a vulnerability report, vulnerability data in the report is grouped by detected ports. If you do not configure an iterator, hosts and vulnerabilities are listed in the report individually.	PDF

To configure a grouping element:

1. In the left navigation, click **Reporting > Reports**.

The **Reports** page appears.

2. In the reports table, click the name of the report you want to edit.

-or-

Right-click the row for the report you want to edit, and click **Edit**.

The **Edit Report** page appears.

3. On the left side of the page, click **Definition**.

The report outline appears. This outline is, by default, expanded. For more information, see [Edit a Report Outline](#).

4. Click **Add Element**.

**Tip:** To display **Add Element**, hover the cursor over the element.



5. Do one of the following:

- Add a group to the report.
  - a. In the **Grouping** section, click the **Group** icon.
  - b. Configure the following options:

Option	Action
<b>Name</b>	Type a name for the element.
<b>Location</b>	Select a location for the element in the report.
<b>Style</b>	Select a style for the element.

- Add a section to the report.
  - a. In the **Grouping** section, click the **Section** icon.
  - b. Configure the following options:

Option	Action
<b>Name</b>	Type a name for the element.
<b>Location</b>	Select a location for the element in the report.
<b>Style</b>	Select a style for the element.

- Add an iterator to the report.
  - a. In the **Grouping** section, click the **Iterator** icon.
  - b. Configure the following options:

Option	Action
<b>General</b>	
<b>Name</b>	Type a name for the element.





<b>Location</b>	Select a location for the element in the report.
<b>Style</b>	Select a style for the element.
<b>Definition</b>	
<b>Query</b>	Select a predefined query to define the data included in the element. For more information, see <a href="#">Queries</a> .
<b>Type</b>	Select the type of data to include in the element. Iterator elements support vulnerability or event data only.
<b>Source</b>	<p>Select the source of the data included in the element.</p> <p>Valid values for this field differ based on the setting of the <b>Type</b> option:</p> <ul style="list-style-type: none"><li>• If <b>Type</b> is set to <b>Vulnerability</b>, valid <b>Source</b> values are:<ul style="list-style-type: none"><li>◦ <b>Cumulative</b>—All vulnerabilities, regardless of whether the vulnerabilities have been remediated or not</li><li>◦ <b>Mitigated</b>—Remediated vulnerabilities</li><li>◦ <b>Individual Scan</b>—Vulnerabilities identified in a specific scan</li></ul></li></ul> <div style="border: 1px solid blue; padding: 10px; margin-top: 10px;"><p><b>Note:</b> If you select <b>Individual Scan</b>, Tenable Security Center displays the <b>Selected Scan</b> option, which allows you to select a scan to use as the basis of the report:</p><ol style="list-style-type: none"><li>a. Click one of the predefined date ranges, or click <b>Custom Range</b> and enter starting and ending days for the range.</li><li>b. Click <b>Fetch Scans</b> to view a list of possible scans within the date range.</li></ol></div>



	<p>c. Click the scan you want to use in the drop-down box.</p> <ul style="list-style-type: none"><li>• If <b>Type</b> is set to <b>Event</b>, valid <b>Source</b> values are:<ul style="list-style-type: none"><li>◦ <b>Active</b>—Currently active events</li><li>◦ <b>Archive</b>—Archived events</li></ul></li></ul> <p><b>Note:</b> If you select <b>Archive</b>, Tenable Security Center displays additional options, allowing you to select the <b>LCE</b> that collected the events and the <b>Silo</b> that stores the archived events.</p>
<b>Filters</b>	Specify additional criteria to refine element data. See <a href="#">Manage Filters for a Chapter Report</a>
<b>Iterator Type</b>	Select a grouping method for iteration data: <ul style="list-style-type: none"><li>• <b>IP Summary</b>—Group vulnerability or event data by the IP addresses of detected hosts.</li><li>• <b>Port Summary</b>—Group vulnerability or event data by the detected ports.</li><li>• <b>Type Summary</b>—Group event data by event type.</li><li>• <b>User Summary</b>—Group event data by user.</li><li>• <b>Vulnerability Summary</b>—Group vulnerability data by individual vulnerability.</li></ul>
<b>Results Displayed</b>	Select the number of results you want to include in the iteration.
<b>Sort Column</b>	Select the column that Tenable Security Center uses to sort the iteration data.



<b>Sort Direction</b>	Select the sort direction for the iteration data.
<b>Header Information</b>	Select the columns you want to include in the iteration data. Available columns depend on the settings of the <b>Type</b> and <b>Source</b> options.

6. Click **Submit** to save the element.
7. Click **Submit** to save your changes to the report.



## Configure a Text Element in a Report

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

Text elements in Tenable Security Center reports include:

Type	Description	Relevant Reports
<b>Matrix</b>	Data in a chart layout.	PDF
<b>Table</b>	Data in a table layout (max results displayed: 999).  The underlying data set determines the report display. The default view for most reports is host-centric and Tenable Security Center presents the user with the ability to choose a vulnerability-centric report (a listing of vulnerabilities with all associated hosts).	PDF
<b>Paragraph</b>	Descriptive text that can be inserted anywhere in the report. Use this option to describe table elements or report output for the viewer.	PDF
<b>Assurance Report Card</b>	An element based on the results of a selected Assurance Report Card.	PDF

To configure a text element in a report:

1. In the left navigation, click **Reporting > Reports**.

The **Reports** page appears.

2. In the reports table, click the name of the report you want to edit.

-or-

Right-click the row for the report you want to edit, and click **Edit**.

The **Edit Report** page appears.

3. On the left side of the page, click **Definition**.



The report outline appears. This outline is, by default, expanded. For more information, see [Edit a Report Outline](#).

4. Do one of the following:

- Click **Add Element** to add an element.
- Click the edit icon next to the element to edit an existing element.

**Tip:** To display **Add Element** and the edit icon, hover the cursor over the element.

5. Do one of the following:

- [Add a matrix to the report](#).
- [Add a table to the report](#).
- Add a paragraph to the report.
  - a. In the **Text** section, click the **Paragraph** icon.
  - b. Configure the following options:

Option	Action
<b>Name</b>	Type a name for the element.
<b>Location</b>	Select a location for the element in the report.
<b>Style</b>	Select a style for the element.
<b>Text</b>	Type the text of the paragraph.

- c. Click **Submit** to save your changes to the element.
- Add an Assurance Report Card to the report.
    - a. In the **Text** section, click the **Assurance Report Card** icon.



b. Configure the following options:

Option	Action
<b>Name</b>	Type a name for the element.
<b>Location</b>	Select a location for the element in the report.
<b>Style</b>	Select a style for the element.
<b>Assurance Report Card</b>	Select the Assurance Report Card (ARC) you want to add to the report. For more information on ARCs, see <a href="#">Assurance Report Cards</a> .

c. Click **Submit** to save your changes to the element.

6. Click **Submit** to save your changes to the report.



## Configure a Matrix Element in a Report

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

A matrix element is a type of text element you can insert into a Tenable Security Center report definition. For more information on text elements, see [Configure a Text Element in a Report](#).

To configure a matrix element in a report:

1. In the left navigation, click **Reporting > Reports**.

The **Reports** page appears.

2. In the reports table, click the name of the report you want to edit.

-or-

Right-click the row for the report you want to edit, and click **Edit**.

The **Edit Report** page appears.

3. On the left side of the page, click **Definition**.

The report outline appears. This outline is, by default, expanded. For more information, see [Edit a Report Outline](#).

4. Do one of the following:

- Add a new element.
  - a. Click **Add Element**.
  - b. In the **Text** section, click the **Matrix** icon.
    - Click the edit icon next to the element you want to change.

**Tip:** To display **Add Element** and the edit icon next to an element, hover the cursor over the element.

5. Configure the **General** options:



Option	Action
<b>Name</b>	Type a name for the element.
<b>Location</b>	Select a location for the element in the report.
<b>Style</b>	Select a style for the element.


6. In the **Cells** section, select the number of columns and rows you want the matrix to include. By default, the matrix is 4 cells by 4 cells.

7. Click **Generate Cells**.

Tenable Security Center displays the empty matrix for configuration.

8. Do one of the following:

- Edit a row or column header.

- a. Click the header for the row or column you want to edit.
- b. Next to the header label, click the  menu.

The actions menu appears.

- c. Click **Edit Header**.
- d. In the **Label** box, type a new header.
- e. Click **Submit**.

- Add a matrix component.

- a. Click the matrix cell where you want to add the component.
- b. In the **Data Type** drop-down box, select the type of data for the component.
- c. In the **Type** drop-down box, select the type of calculation you want the component to perform.
- d. In the **Source** drop-down box, select a data source.
- e. (Optional) In the **Filter** box, add or edit a filter using the same steps you would to add a filter to a report element; see [Manage Filter Components for a Single](#)





### Element.

f. In the **Rules** section, click **Add Rule** to add a rule.

-or-

Click the edit icon next to a rule to edit an existing rule.

g. Click **Submit** to save your changes to the component.

- **Copy a row or column.**

a. Click the header for the row or column you want to copy.

b. Next to the header label, click the  menu.

The actions menu appears.

c. Click **Copy**.

For columns, Tenable Security Center inserts the copied column to the right of the original column

For rows, Tenable Security Center inserts the copied row under the original row.

- **Delete a row or column.**

a. Click the header for the row or column you want to delete.

b. Next to the header label, click the  menu.

The actions menu appears.

c. Click **Delete Cells**.

9. Click **Submit** to save your changes to the element.

10. Click **Submit** to save your changes to the report.

### Example



### Current Vulnerabilities

	New IP's	Info	Low	Medium	High	Critical
< 7 Days	895	895	62	67	24	21
8 - 14 Days	43	43	7	20	11	9
15 - 21 Days	5	5	12	21	13	4
22 - 30 Days	1	1	2	2	2	2



## Configure a Table Element in a Report

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

A table element is a type of text element you can insert into a Tenable Security Center report definition. For more information on text elements, see [Configure a Text Element in a Report](#).

To configure a table element in a report:

1. In the left navigation, click **Reporting > Reports**.

The **Reports** page appears.

2. In the reports table, click the name of the report you want to edit.

-or-

Right-click the row for the report you want to edit, and click **Edit**.

The **Edit Report** page appears.

3. On the left side of the page, click **Definition**.

The report outline appears. This outline is, by default, expanded. For more information, see [Edit a Report Outline](#).

4. Do one of the following:

- Add a new element.
  - a. Click **Add Element**.
  - b. In the **Text** section, click the **Table** icon.
- Click the edit icon next to the element you want to change.

**Tip:** To display **Add Element** and the edit icon next to an element, hover the cursor over the element.

5. Configure the **General** options:



Option	Action
Name	Type a name for the element.
Location	Select a location for the element in the report.
Style	Select a style for the element.

6. Configure the **Data** options:

Option	Description
Type	Equivalent to the <b>Definition</b> option of the same name in <a href="#">Report Options</a> .
Query	
Source	
Tool	
Filters	

7. Configure the **Display** options:

Option	Description
Results Displayed	Equivalent to the <b>Display</b> option of the same name in <a href="#">Report Options</a> .
Sort Column	
Sort Direction	
Display Columns	

8. Click **Submit** to save your changes to the element.

9. Click **Submit** to save your changes to the report.

Example



### Highest Ranked Asset Vulnerability Index [Scan Result #23]


Asset	Score	Total	Med.	High	Crit.
All Defined Assets	13593	1423	541	777	105
Linux Hosts	4189	476	193	257	26
Linux Kernel 2.6	4092	453	174	253	26
CentOS	3625	386	115	252	19
Linux Kernel 64-Bit	1294	141	68	61	12
Ubuntu Linux	380	48	40	2	6
Debian Linux	74	10	8	1	1
Linux Kernel 3.1	9	3	3	0	0
Linux Kernel 3.2	6	2	2	0	0
Linux Kernel 3.3	6	2	2	0	0



# Configure a Charts Element in a Report

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

Charts elements in Tenable Security Center reports include:

Option	Description	Relevant Reports
Bar Chart	Click to add a bar chart element to the report. 	PDF
Pie Chart	Click to add a pie chart element to the report. 	PDF
Line Chart	Click to add a line chart element to the report.	PDF



Option	Description	Relevant Reports
	<div data-bbox="337 310 930 611"></div> <p data-bbox="337 680 1227 863">Line charts are defined by time (x-axis) and series data (y-axis). When selecting the time, available options include Relative time and Absolute time. One or more series data elements can be chosen and displayed as discrete lines for easy comparison.</p>	
<b>Area Chart</b>	<p data-bbox="337 905 1008 936">Click to add an area chart element to the report.</p> <div data-bbox="337 993 930 1283"></div> <p data-bbox="337 1356 1227 1539">Area charts are defined by time (x-axis) and series data (y-axis). When selecting the time, available options include Relative time and Absolute time. One or more series data elements can be chosen and displayed as a stackable view for easy comparison.</p>	PDF

To configure a chart element in a report:

1. In the left navigation, click **Reporting > Reports**.

The **Reports** page appears.

2. In the reports table, click the name of the report you want to edit.



-or-

Right-click the row for the report you want to edit, and click **Edit**.

The **Edit Report** page appears.

3. On the left side of the page, click **Definition**.

The report outline appears. This outline is, by default, expanded. For more information, see [Edit a Report Outline](#).

4. Do one of the following:

- Add a chart element
  - a. Click **Add Element** to add an element.
  - b. In the **Charts** section, click the icon for the type of chart you want to add.
- Click the edit icon next to an existing chart element.

**Tip:** To display **Add Element** and the edit icon, hover the cursor over the element.

5. For all charts, configure the **General** options:

Option	Action
<b>Name</b>	Type a name for the element.
<b>Location</b>	Select a location for the element in the report.
<b>Style</b>	Select a style for the element.

6. For bar charts and pie charts, configure the following **Data** options:

Option	Action
--------	--------





Type	Equivalent to the option the <b>Definition</b> option of the same name in <a href="#">Report Options</a> .
Query	
Source	
Tool	
Filters	

7. For line charts and area charts, configure the following **Data** options:

Option	Action
<b>Data Type</b>	Valid values are <b>Relative</b> and <b>Absolute</b> . Use to configure the x-axis of the chart.
<b>Data Range</b>	Use to configure the x-axis of the chart: <ul style="list-style-type: none"><li>• If you select <b>Relative</b> for <b>Data Type</b>, select a relative date range.</li><li>• If you select <b>Absolute</b> for <b>Data Type</b>, select a specific start and end date for the data.</li></ul>
<b>Series</b>	Use to configure the y-axis of the chart. Line charts and area charts require that you configure at least one series.

8. For bar charts and pie charts, configure the following **Display** options:

Option	Action
<b>Results Displayed</b>	Equivalent to the <b>Display</b> option of the same name in <a href="#">Report Options</a> .
<b>Sort Column</b>	
<b>Sort Direction</b>	
<b>Display Columns</b>	

9. Click **Submit** to save your changes to the element.

10. Click **Submit** to save your changes to the report.



## Reorder Report Chapters and Elements

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

In Tenable Security Center, you can reorder chapters and elements in a PDF, CSV, or template-based report.

To reorder report chapters and elements:

1. In the left navigation, click **Reporting > Reports**.

The **Reports** page appears.

2. In the reports table, click the name of the report you want to edit.

-or-

Right-click the row for the report you want to edit, and click **Edit**.

The **Edit Report** page appears.

3. On the left side of the page, click **Definition**.

The report outline appears. This outline is, by default, expanded. For more information, see [Edit a Report Outline](#).

4. Do one of the following:

- In the report outline, click the report element, then drag and drop it to its new location.
- Click the edit icon for the component, and select a new location in the **Location** drop-down box.

5. Click **Submit** to save your changes to the report.



---

## Manage Filters for a Chapter Report

---

In Tenable Security Center, PDF and template-based reports use a chapter structure, so you can specify different filters for individual chapter elements of those reports.

You can manage filters for a single element or for multiple elements at the same time. For more information, see:

- [Manage Filter Components for a Single Element](#)
- [Manage Filter Components for Multiple Elements](#)



## Manage Filter Components for a Single Element

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

**Tip:** You can build filters using one or more *filter components* with defined *filter component criteria*. Filter components are types of data (e.g., **CVE ID** or **Severity**). After you select a filter component, you specify the filter component criteria (e.g., a specific CVE ID or a specific severity level).

To manage filter components for a single element in a chapter report in Tenable Security Center:

1. In the left navigation, click **Reporting > Reports**.

The **Reports** page appears.

2. In the reports table, click the name of the report you want to edit.

-or-

Right-click the row for the report you want to edit, and click **Edit**.

The **Edit Report** page appears.

3. On the left side of the page, click **Definition**.

The report outline appears. This outline is, by default, expanded. For more information, see [Edit a Report Outline](#).

4. Click the edit icon next to the element you want to edit.

**Tip:** To display icons next to a element, hover the cursor over the element.

5. Do one of the following:

- Add a filter component.

Use these steps to add one or more filter components to a single element. For information about the filter components available for vulnerability analysis data or event analysis data, see [Vulnerability Analysis Filter Components](#) or [Event Analysis Filter Components](#).



- a. In the **Data** section, click **Add Filter**.
- b. Select a filter component from the drop-down box.
- c. Set the filter component criteria, as prompted.

Depending on the filter component you selected, Tenable Security Center prompts you to type the value you want to filter for or to select from valid values and operators.

**Note:** If Tenable Security Center does not prompt you to specify an operator, the unstated operator is equivalent to **is equal to** or **is set to**.

- d. Click the check mark next to the filter component to stop editing it.

**Note:** The new filter component is not saved until you click **Submit**.

- Edit a filter component.
  - a. In the **Data** section, click the pencil icon next to the filter component.
  - b. Edit the filter component criteria.
  - c. Click the check mark next to the filter component to stop editing it.

**Note:** Your changes to the filter are not saved until you click **Submit**.

- Delete a filter component.

In the **Data** section, click the delete icon next to the filter component.

**Note:** Tenable Security Center does not prompt you to confirm the deletion. However, the deletion is not final until you click **Submit** to save your changes.

6. Click **Submit**.



## Manage Filter Components for Multiple Elements

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

When managing filter components for a chapter report in Tenable Security Center, you can search the report for elements that use certain filter components, then update the filter component criteria for all matching elements in that report at the same time.

**Tip:** You can build filters using one or more *filter components* with defined *filter component criteria*. Filter components are types of data (e.g., **CVE ID** or **Severity**). After you select a filter component, you specify the filter component criteria (e.g., a specific CVE ID or a specific severity level).

You can use the following filter components to search and update: **Address**, **Audit File**, **Asset**, **CVE ID**, **DNS Name**, **IAVM ID**, **Repositories**, **Scan Policy**, and **Severity**.

For example, if you search a report definition for all elements where the **Severity** filter component is set to **Info**, you can update the **Severity** filter component to **Medium** for all elements, and add an **Audit File** filter component to the elements at the same time.

To manage filter components for multiple elements in a chapter report:

1. In the left navigation, click **Reporting > Reports**.

The **Reports** page appears.

2. In the reports table, click the name of the report you want to edit.

-or-

Right-click the row for the report you want to edit, and click **Edit**.

The **Edit Report** page appears.

3. On the left side of the page, click **Definition**.

The report outline appears. This outline is, by default, expanded. For more information, see [Edit a Report Outline](#).

4. At the top of the outline, click **Find/Update Filters**.

To search for specific elements in the report:



1. In the **Search Filters** section, click **Add Search Filter**.
2. Select a filter component from the drop-down box.
3. Select an operator from the drop-down box.
  - a. If you selected **is equal to** or **contains** as operator, type filter component criteria or select a value from the list of valid filter component criteria, as appropriate to the filter component you selected.
4. Click the check mark at the end of the filter box.

Tenable Security Center searches the report outline for elements that match your search criteria and displays the results in the **Matching Filters** box.

To specify the filter updates you want to make:

1. In the **Update Actions** section, click **Add Search Filter**.
2. Select a filter component from the drop-down box.
3. Select an operator from the drop-down box.
4. Type filter component criteria or select a value from the list of valid filter values, as appropriate to the filter component and operator you selected.
5. Click the check mark at the end of the filter box.

To review and update the filter updates:

1. In the **Matching Filters** box, review the list to verify that you want to apply the update to all the listed elements.

**Tip:** If you do not want to apply the current update to all the listed elements, it may be more appropriate to manage filter components by individual element. For more information, see [Manage Filter Components for a Single Element](#).

2. Click **Update Filters**.

Tenable Security Center applies the updates to the matching elements and returns you to the report outline.

3. Click **Submit** to save your changes to the report.



## Manage Filter Components for a Non-Chapter Report

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

In Tenable Security Center, CSV, DISA ARF, DISA ASR, and Cyberscope reports do not use a chapter structure, so you can create a set of filter components that apply to every element of the report.

**Tip:** You can build filters using one or more *filter components* with defined *filter component criteria*. Filter components are types of data (e.g., **CVE ID** or **Severity**). After you select a filter component, you specify the filter component criteria (e.g., a specific CVE ID or a specific severity level).

To manage filter components for a non-chapter report:

1. In the left navigation, click **Reporting > Reports**.

The **Reports** page appears.

2. In the reports table, click the name of the report you want to edit.

-or-

Right-click the row for the report you want to edit, and click **Edit**.

The **Edit Report** page appears.

3. Do one of the following:

- Add a filter component.

Use these steps to add one or more filter components to a single element. For information about the filter components available for vulnerability analysis data or event analysis data, see [Vulnerability Analysis Filter Components](#) or [Event Analysis Filter Components](#).

- a. In the **Definition** section, click **Add Filter**.
- b. Select a filter component from the drop-down box.
- c. Set the filter component criteria, as prompted.





Depending on the filter component you selected, Tenable Security Center prompts you to type the value you want to filter for or to select from valid values and operators.

- d. Click the check mark next to the filter component to stop editing it.

**Note:** The new filter component is not saved until you click **Submit**.

- Edit a filter component.
  - a. In the **Definition** section, click the edit icon next to the filter component.
  - b. Edit the filter criteria.
  - c. Click the check mark next to the filter component to stop editing it.

**Note:** Your changes to the filter component are not saved until you click **Submit**.

- Delete a filter component.

In the **Definition** section, click the delete icon next to the filter component.

**Note:** Tenable Security Center does not prompt you to confirm the deletion. However, the deletion is not final until you click **Submit** to save your changes.

4. Click **Submit** to save your changes.




## View a Report Definition

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

To view a report definition:

1. In the left navigation, click **Reporting > Reports**.

The **Reports** page appears.

2. In the row for the report definition you want to view, click the  menu.

The actions menu appears.

3. In the table, right-click the row for the report definition you want to view.

The actions menu appears.

4. Click **View**.

Tenable Security Center displays a read-only version of the report definition.

**Note:** If you want to edit or delete the report definition from this page, see [Edit a Report Definition](#) or [Delete a Report Definition](#).



## Copy a Report Definition

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can share a copy of a report definition with other users in your organization in Tenable Security Center. This feature is useful for maintaining consistency throughout your organization.

After you share the copy, the other users own their local copy and can edit or delete as with any report they create themselves. Later changes you make to the original do not synchronize automatically to the copy.

To copy a report definition:

1. In the left navigation, click **Reporting > Reports**.

The **Reports** page appears.

2. In the table, right-click the row for the report definition you want to copy.

The actions menu appears.

3. Click **Copy**.

The **Copy Report** page appears.

4. In the **Group** box, select the group you want to grant access to a copy of the report.

5. Specify the user(s) that you want to grant access to a copy of the report.

6. Click **Copy**.

Tenable Security Center copies the report definition to the other accounts you specified. The copy appears, named **Copy of *DefinitionName***.



## Export a Report Definition

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

In Tenable Security Center, you can export a report definition as an .xml file. This feature is useful for organizations running multiple Tenable Security Center deployments to provide consistent reports without duplicating the work needed to create definition templates.

To export a report definition:

1. In the left navigation, click **Reporting > Reports**.

The **Reports** page appears.

2. In the table, right-click the row for the report definition you want to export.

The actions menu appears.

3. Click **Export**.



4. Click the export option you want to use:

Option	Description
<b>Keep All References</b>	<p>Export the report definition with object references intact.</p> <p>Users who meet the following requirements can use an imported report definition with intact object references:</p> <ul style="list-style-type: none"><li>• The user must be in the same organization as the user who exported the report definition.</li><li>• The user must have access to all relevant objects in the report definition.</li></ul>
<b>Remove All References</b>	<p>Export the report definition with object references removed, altering the definitions of the components.</p> <p>Any user can use an imported report definition with object references removed.</p>
<b>Replace With Placeholders</b>	<p>Export the report definition with object references replaced with their respective names.</p> <p>Users must replace the placeholder names with applicable objects available to their organization in order to use an imported report definition with placeholder names.</p>

Tenable Security Center downloads the report definition to your computer.



## Import a Report Definition

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

In Tenable Security Center, you can only import XML files in the same format used to [export report definitions](#). This feature is useful for organizations running multiple Tenable Security Center deployments to provide consistent reports without duplicating the work needed to create definition templates.

To import a report definition:

1. Copy the report definition file to your local computer.
2. In the left navigation, click **Reporting > Reports**.  
The **Reports** page appears.
3. At the top of the table, click **Import Report**.
4. In the **Name** box, type a name for the report.
5. Click **Choose File** next to the **Report Definition** box.
6. Browse to the local copy of the report definition XML file.
7. Click **Import**.

Tenable Security Center imports the report definition.

8. (Optional) [Edit the report definition](#) as desired.



## Delete a Report Definition

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

To delete a report definition:

1. In the left navigation, click **Reporting > Reports**.

The **Reports** page appears.

2. To delete a single report definition:

- a. In the table, right-click the row for the report definition you want to delete.

The actions menu appears.

To delete multiple report definitions:

- a. In the table, select the check box for each report definition you want to delete.

The available actions appear at the top of the table.

3. Click **Delete**.
4. Click **Delete** to confirm the deletion.

Tenable Security Center deletes the report definition.

**Note:** Tenable Security Center retains any report results associated with the deleted definition. You must manually [delete results associated with the report](#).



## Launch a Report on Demand

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

To launch a report on demand:

1. In the left navigation, click **Reporting > Reports**.

The **Reports** page appears.

2. In the table, right-click the row for the report you want to launch.

-or-

Select the check box for the report you want to launch.

The actions menu appears.

3. Click **Launch**.
4. (Optional) Monitor the status of the report in the **Report Results** page.

To view this page, do one of the following:

- In the launch notification message, click **View Report Results**.
- In the left navigation, click **Reporting > Report Results**.

**Note:** In the **Report Results** page, you can also [stop the currently running report](#).





## Add a Report to a Scan

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

After you create one or more on demand reports, you can add them to active scan, agent scan, or agent synchronization job configurations.

To add a preconfigured report to an active scan, agent scan, or agent synchronization job:

1. Do one of the following:
  - Begin configuring an active scan, as described in [Add an Active Scan](#).
  - Begin configuring an agent scan, as described in [Add an Agent Scan](#).
  - Begin configuring an agent synchronization job, as described in [Add an Agent Synchronization Job](#).
2. In the **Post Scan** section, click **Add Report**.

The page displays available on demand reports.
3. Select the report you want to add.
4. (Optional) If you want the report to include cumulative data in Tenable Security Center, enable the **Create report using cumulative data** option.

If you disable this option, the report includes data only from the configured scan.
5. Click the checkmark icon to save the report.
6. (Optional) If you want to add multiple reports, repeat steps 2-5 for each additional report.
7. Click **Submit**.

Tenable Security Center saves your configuration.



## Manage Report Results

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

On the **Report Results** page of Tenable Security Center, you can manage both currently running reports and completed report results. Completed report results include successful and failed report runs, so you can access and distribute a successful report result or troubleshoot a report failure. For more information, see [Reports](#).

To manage report results:

1. Click **Reporting > Report Results**.

The **Report Results** page appears.

2. Do any of the following:
  - [Filter existing report results in the report results table](#).
  - [Stop a currently running report](#).
  - [Download a successful report result to your computer](#).
  - [View a successful report result](#).
  - [Publish a successful result](#).
  - [Email a copy of a successful result to specified users](#).
  - [Share a copy of a successful result with other Tenable Security Center user accounts](#).
  - [View error conditions for a failed report](#).
  - [Delete a report result](#).



## Stop a Running Report

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

If you want to stop a report that is currently running:

1. Click **Reporting > Report Results**.

The **Report Results** page appears.

2. Right-click the row for the report you want to stop, and click **Stop**.

Tenable Security Center stops the report run.

**Note:** You cannot restart a stopped report run. You can only [launch the report](#) again.



---

## Download a Report Result

---

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

To download a successful report result to your computer:

1. Click **Reporting > Report Results**.

The **Report Results** page appears.

2. Do one of the following:

- In the Results table, click the name of the report.
- Right-click the row for the report result.

The actions menu appears.

- a. Click **Export**.
- Select the check box for the report result.

At the top of the table, click **Download**.



## View a Report Result

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

To view a successful report result:

1. Click **Reporting > Report Results**.

The **Report Results** page appears.

2. Right-click the row for the report result you want to view.

The actions menu appears.

3. Click **View**.

The report appears.

4. (Optional) To download the report result to your computer, click **Download**.

The report result downloads.

5. (Optional) To delete the report result, click **Delete**.

Tenable Security Center deletes the report result.



## Publish a Report Result

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

To publish a successful report result:

1. Click **Reporting > Report Results**.

The **Report Results** page appears.

2. Right-click the row for the report result you want to publish.

The actions menu appears.

3. Click **Publish**.

The **Publish Report Results** window appears.

4. Search for and select a publishing site.

5. Click **Publish**.

Tenable Security Center publishes the report result.



## Email a Report Result

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

To email a copy of a successful report result to specific users:

1. Click **Reporting** > **Report Results**.

The **Report Results** page appears.

2. Right-click the row for the report result you want to email.

The actions menu appears.

3. Click **Email**.

4. Do one of the following:

- Use the **Group** and **User** boxes to select the Tenable Security Center user or users you want to receive the report result.
- Type the email address of recipients who are not Tenable Security Center users.

5. Click **Submit**.

Tenable Security Center sends the report result.



## Copy a Report Result

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

To share a copy of a successful report result with other Tenable Security Center user accounts:

1. Click **Reporting > Report Results**.

The **Report Results** page appears.

2. Right-click the row for the report result you want to copy.

The actions menu appears.

3. Click **Copy**.

4. In the **Group** box, select the group you want to grant access to a copy of the report result.

5. Specify a user or users that you want to grant access to a copy of the report result.

6. Click **Copy**.

Tenable Security Center copies the report result to the other accounts you specified. The copy appears, named **Copy of *ResultName***.





---

## View Errors for a Failed Report

---

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

To view error conditions for a failed report:

1. Click **Reporting** > **Report Results**.

The **Report Results** page appears.

2. Click the name of the failed result in the results table.

The **View Report Results** page appears.

3. Review the **Error Details** section.



## Delete a Report Result

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

To delete a report result:

1. Click **Reporting** > **Report Results**.

The **Report Results** page appears.

2. Right-click the row for the report result you want to delete.

The actions menu appears.

3. Click **Delete**.

A confirmation window appears.

4. Click **Delete** to confirm the deletion.

Tenable Security Center deletes the report result.



## CyberScope and DISA Report Attributes

Report attributes are used for adding required information to CyberScope or DISA report types. After you create an attribute, you can select it during CyberScope, DISA ARF, or DISA Consolidated ARF report creation. For more information, see [Create a Custom Report](#).

To filter the **Report Attributes** page, see [Apply a Filter](#).

Configure the following options, including options specific for your attribute type: [CyberScope Options](#) or [DISA Options](#).

General Option	Description
Name	A name for the attribute.
Description	(Optional) A description for the attribute.
Type	The type of attribute you want to create. Your <b>Type</b> selection determines the other options you must configure: <a href="#">CyberScope Options</a> or <a href="#">DISA Options</a> .

### CyberScope Options

The following table describes the additional options to configure when configuring a **CyberScope** attribute.

Option	Description
Reporting Component	The CyberScope value for a reporting component (e.g., <b>Department of Justice</b> ).
Component Bureau	The CyberScope value for a FISMA reporting entity within the <b>Reporting Component</b> (e.g., <b>Justice Management Division</b> ).
Enclaves	The CyberScope value for an enclave associated with the <b>Reporting Component</b> or <b>Component Bureau</b> .

### DISA Options

The following table describes the additional options to configure when configuring a **DISA** attribute.



Option	Description
<b>Owning Unit</b>	
Name	(Required) The Cyber Operational Attributes Management System (COAMS) fully qualified hierarchy name of the owning organization.
<b>Owning Service</b>	
Name	The COAMS fully qualified hierarchy name of the owning combatant command, service, or agency.
Current AOR	The COAMS fully qualified hierarchy name of the appropriate combatant command area of responsibility (COCOM AOR).
Region	A region for the owning service.
<b>Administration Unit</b>	
Name	The COAMS fully qualified hierarchy name of the administering organization.
<b>Administration POC</b>	
Any required information you need to provide about the administration unit's point of contact (POC).	
<b>Tip:</b> Tenable recommends leaving the <b>Generational Qualifier</b> option blank.	
<b>CND Service Provider</b>	
Name	The COAMS fully qualified hierarchy name of the Computer Network Defense Service Provider (CNDSP).
Por Managed	(Required) Specifies if the reported assets are centrally managed by a program management office (PMO): <b>true</b> or <b>false</b> .
System Affiliation	The COAMS <b>operationalcredit</b> value that specifies the fully qualified hierarchy name of the system affiliation.



Option	Description
Location	<p><b>Tip:</b> Tenable recommends leaving all options blank except the <b>Street Address</b>. The <b>Street Address</b> specifies the COAMS geolocation area.</p>



## Report Images

In Tenable Security Center, the **Report Images** interface allows a user with permissions to view details, add, edit, or delete PDF report images. From this interface, you can manage two types of images: logos and watermarks. Logos appear at the bottom of each page, while watermarks appear prominently across the center of the report page.

**Note:** Image files must be of type .png or .jpg. Images used must be consistent when selecting the bit depth (8-bit, 16-bit, 24-bit, etc.). Otherwise, errors might be encountered when generating reports.

To filter the **Report Images** page, see [Apply a Filter](#).

### Report Image Options

Option	Description
<b>Add</b>	<p>Add a new logo or watermark image. Note that only PNG and JPEG formats are supported. The default image sizes are as follows, all at 300 DPI:</p> <ul style="list-style-type: none"><li>• default-cover-logo = 987x130</li><li>• default-footer-logo = 380x100</li><li>• default-page-logo = 579x84</li><li>• default-watermark = 887x610</li></ul> <p>While there are no set limitations on image size or resolution, using images that are different from these specifications can have a negative impact on report appearance.</p> <p><b>Note:</b> The image size must be set to 300 DPI to prevent image breaks.</p>
<b>Edit</b>	<p>Edit any of the selected image's options, including name, description, type and file.</p>
<b>Detail</b>	<p>View image details, including name, description, date uploaded, last modified, and type.</p>
<b>Delete</b>	<p>Delete the highlighted image.</p>



---

## Assurance Report Cards

---

*Assurance Report Cards (ARCs)* provide an overview of the security posture of your network. These configurable reports provide quick visible feedback using a pass or fail methodology for each policy statement in the ARC.

Organizational users with appropriate permissions can add a template-based ARC using Tenable-provided templates or you can add a custom ARC. For more information about Tenable-provided ARC templates, see the [Assurance Report Cards](#) blog. For more information about user permissions, see [User Roles](#).

- [Add a Template-Based Assurance Report Card](#)
- [Add a Custom Assurance Report Card](#)
- [Assurance Report Card Options](#)
- [Edit an Assurance Report Card](#)
- [View Your Assurance Report Cards](#)
- [View Details for an Assurance Report Card](#)
- [Share or Revoke Access to an Assurance Report Card](#)
- [Export an Assurance Report Card](#)
- [Copy an Assurance Report Card](#)
- [Delete an Assurance Report Card](#)



## Add a Template-Based Assurance Report Card

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can use a Tenable-provide template to add an Assurance Report Card (ARC). For more information about Tenable-provided ARC templates, see the [Assurance Report Cards](#) blog. To create a custom ARC, see [Add a Custom Assurance Report Card](#).

For more information, see [Assurance Report Cards](#).

To add a template-based Assurance Report Card:

1. Log in to Tenable Security Center via the user interface.

2. Click **Dashboard > Assurance Report Cards**.

The **Assurance Report Cards** page appears.

3. At the top of the table, click **Add**.

The **Assurance Report Card Templates** page appears.

4. Click a template category tile.

The list of templates for the selected category appears.

5. Click a template.

The **Add Assurance Report Card Template** page updates to reflect the template you selected.

6. Modify the ARC template. For more information, see [Assurance Report Card Options](#).

- To edit the ARC name, click ARC template title.
- To edit the ARC description, click the **Description** box.
- To edit the required assets, click an item in the **Required Assets** section.
- To restrict the target data displayed in the ARC, click the **Targets** drop-down box.
- To set how often the ARC polls data sources to obtain updates, click **Schedule**.

7. Click **Add**.

Tenable Security Center saves your configuration.





## Add a Custom Assurance Report Card

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can create a fully customized Assurance Report Card (ARC). To add an ARC from a Tenable-provided template, see [Add a Template-Based Assurance Report Card](#).

For more information, see [Assurance Report Cards](#).

To add a custom Assurance Report Card:

1. Log in to Tenable Security Center via the user interface.
2. Click **Dashboard > Assurance Report Cards**.

The **Assurance Report Cards** page appears.

3. In the **Options** dropdown box, click **Advanced Add**.

The **Advanced Add Assurance Report Cards** page appears.

4. Configure the ARC options. For more information, see [Assurance Report Card Options](#).
5. Click **Submit**.

Tenable Security Center saves your configuration.



## View Your Assurance Report Cards

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can view a summary that displays each Assurance Report Card (ARC), the overall status of the ARC, and the status of each policy statement in each ARC. To view details for an ARC, see [View Details for an Assurance Report Card](#).

For more information, see [Assurance Report Cards](#).

**Tip:** To change the position of an ARC in the list, click the icon next to the ARC and drag it to a new position.

Before you begin:

- Add an ARC, as described in [Add a Template-Based Assurance Report Card](#) or [Add a Custom Assurance Report Card](#).

To view a summary of your Assurance Report Cards:

1. Log in to Tenable Security Center via the user interface.
2. Click **Dashboard > Assurance Report Cards**.

The **Assurance Report Cards** page appears.

3. Click the row for the ARC.

The ARC expands to display each policy statement in the ARC.

4. View the status of each ARC and its policy statements.
  - A green icon (✓) next to an ARC indicates all policy statement in the ARC passed.
  - A red icon (✗) next to an ARC indicates one or more policy statements in the ARC failed.
  - A green check mark (✓) next to a policy statement indicates the policy statement passed.
  - A red x (✗) next to a policy statement indicates the policy statement failed.

What to do next:



- (Optional) Click a policy statement to view vulnerability analysis for the policy statement data. For more information, see [Vulnerability Analysis](#).



## View Details for an Assurance Report Card

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information, see [Assurance Report Cards](#).

Before you begin:

- Add an Assurance Report Card (ARC), as described in [Add a Template-Based Assurance Report Card](#) or [Add a Custom Assurance Report Card](#).

To view details for an Assurance Report Card:

1. Log in to Tenable Security Center via the user interface.
2. Click **Dashboard > Assurance Report Cards**.

The **Assurance Report Cards** page appears.

3. In the **Options** drop-down menu, click **Manage ARCs**.

The **Manage Assurance Report Cards** page appears.

4. Right-click the row for the ARC.

The actions menu appears.

5. Click **View**.

The **View Assurance Report Card** page appears. For more information, see [Assurance Report Card Options](#).

Section	Action
<b>Options</b> drop-down box	<ul style="list-style-type: none"><li>• To <a href="#">edit</a> the ARC, click <b>Edit</b>.</li><li>• To <a href="#">delete</a> the ARC, click <b>Delete</b>.</li></ul>
<b>General</b>	<p>View general information about the ARC.</p> <ul style="list-style-type: none"><li>• <b>Name</b> —The ARC name.</li><li>• <b>Description</b> —The ARC description.</li></ul>



Section	Action
	<ul style="list-style-type: none"><li>• <b>Schedule</b> —TheARC schedule.</li><li>• <b>Created</b> —The date the ARC was created.</li><li>• <b>Last Modified</b> —The date the ARC was last modified.</li><li>• <b>Owner</b> —The user who created or owns the ARC.</li><li>• <b>Group</b> —The group associated with the <b>Owner</b>.</li><li>• <b>ID</b> —The unique identifier for the ARC.</li></ul>
<b>Policy Statements</b>	View the policy statements in the ARC.
<b>Focus</b>	View the targets configured for the ARC.

---

## Edit an Assurance Report Card

---

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information, see [Assurance Report Cards](#).

Before you begin:

- Add an Assurance Report Card (ARC), as described in [Add a Template-Based Assurance Report Card](#) or [Add a Custom Assurance Report Card](#).

To edit an Assurance Report Card:

1. Log in to Tenable Security Center via the user interface.
2. Click **Dashboard > Assurance Report Cards**.

The **Assurance Report Cards** page appears.

3. In the **Options** drop-down menu, click **Manage ARCs**.

The **Manage Assurance Report Cards** page appears.

4. Right-click the row for the ARC.

The actions menu appears.

5. Click **More > Edit**.

The **Edit Report Card** page appears.

6. Modify the ARC options. For more information, see [Assurance Report Card Options](#).

7. Click **Submit**.

Tenable Security Center saves your configuration.



## Share or Revoke Access to an Assurance Report Card

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can share access to an Assurance Report Card (ARC) to give users in a group the ability to view the ARC. The user's role and custom permissions determine if they can drill down into other pages with more information. For more information, see [Assurance Report Cards](#).

Before you begin:

- Add an ARC, as described in [Add a Template-Based Assurance Report Card](#) or [Add a Custom Assurance Report Card](#).

To share or revoke access to an Assurance Report Card:

1. Log in to Tenable Security Center via the user interface.
2. Click **Dashboard > Assurance Report Cards**.

The **Assurance Report Cards** page appears.

3. In the **Options** drop-down menu, click **Manage ARCs**.

The **Manage Assurance Report Cards** page appears.

4. Right-click the row for the ARC.

The actions menu appears.

5. Click **Share**.

The **Share Assurance Report Card** page appears.

6. In the box, search for and select the groups for which you want to share or revoke access.

7. Click **Submit**.

Tenable Security Center saves your configuration.



# Export an Assurance Report Card

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can export an Assurance Report Card (ARC) to share with other users in your organization. For more information, see [Assurance Report Cards](#).

Before you begin:

- Add an ARC, as described in [Add a Template-Based Assurance Report Card](#) or [Add a Custom Assurance Report Card](#).

To export an Assurance Report Card:

1. Log in to Tenable Security Center via the user interface.
2. Click **Dashboard > Assurance Report Cards**.

The **Assurance Report Cards** page appears.

3. In the **Options** drop-down menu, click **Manage ARCs**.

The **Manage Assurance Report Cards** page appears.

4. To export a single ARC:

- a. In the table, right-click the row for the ARC you want to export.

The actions menu appears.

To export multiple ARCs:

- a. In the table, select the check box for each ARC you want to export.

The available actions appear at the top of the table.

5. Click **Export**.

The export options appear.





6. Click the export option you want to use:

Option	Description
<b>Keep All References</b>	Export the ARC with object references intact.  Users who meet the following requirements can use an imported ARC with intact object references: <ul style="list-style-type: none"><li>• The user must be in the same organization as the user who exported the ARC.</li><li>• The user must have access to all relevant objects in the ARC.</li></ul>
<b>Remove All References</b>	Export the ARC with object references removed, altering the definitions of the components.  Any user can use an imported ARC with object references removed.
<b>Replace With Placeholders</b>	Export the ARC with object references replaced with their respective names.  Users must replace the placeholder names with applicable objects available to their organization in order to use an imported ARC with placeholder names.
<b>Template</b>	Export the ARC as a template.

Tenable Security Center exports the ARC as an .xml file.



# Copy an Assurance Report Card

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information, see [Assurance Report Cards](#).

Before you begin:

- Add an Assurance Report Card (ARC), as described in [Add a Template-Based Assurance Report Card](#) or [Add a Custom Assurance Report Card](#).

To copy an Assurance Report Card:

1. Log in to Tenable Security Center via the user interface.
2. Click **Dashboard > Assurance Report Cards**.

The **Assurance Report Cards** page appears.

3. In the **Options** drop-down menu, click **Manage ARCs**.

The **Manage Assurance Report Cards** page appears.

4. Right-click the row for the ARC.

The actions menu appears.

5. Click **Copy**.

Tenable Security Center copies the ARC. The copy appears, named **Copy of ARC Name**.



## Delete an Assurance Report Card

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information, see [Assurance Report Cards](#).

To delete an Assurance Report Card (ARC):

1. Log in to Tenable Security Center via the user interface.
2. Click **Dashboard > Assurance Report Cards**.

The **Assurance Report Cards** page appears.

3. In the **Options** drop-down menu, click **Manage ARCs**.

The **Manage Assurance Report Cards** page appears.

4. To delete a single ARC:

- a. In the table, right-click the row for the ARC you want to delete.

The actions menu appears.

To delete multiple ARCs:

- a. In the table, select the check box for each ARC you want to delete.

The available actions appear at the top of the table.

5. Click **Delete**.

A confirmation window appears.

6. Click **Delete**.

Tenable Security Center deletes the ARC.



## Assurance Report Card Options

You can configure the following options for Assurance Report Cards (ARCs). For more information, see [Assurance Report Cards](#).

- [Assurance Report Card Options](#)
- [Policy Statement Options](#)

### Assurance Report Card Options

Option	Description
<b>General</b>	
<b>Name</b>	The name of the ARC.
<b>Description</b>	(Optional) A description for the ARC.
<b>Schedule</b>	<p>Specifies how often the ARC polls data sources to obtain updates.</p> <ul style="list-style-type: none"><li>• <b>Daily</b> (default) —The ARC polls data sources every 1-20 days at the specified time.</li><li>• <b>Weekly</b> —The ARC polls data sources every 1-20 weeks at the specified time and day of the week.</li><li>• <b>Monthly</b> —The ARC polls data sources every 1-20 months at the specified time and day of the month.</li></ul> <p>For example, <i>Every 2 months on the fourth Thursday at 15:00 -4:00</i> indicates the ARC will poll data sources to obtain updates every two months, on the fourth Thursday of the month, at 15:00 in the America/New York timezone.</p>
<b>Policy Statements</b>	
<b>Add Policy Statement</b>	Click to add a custom policy statement to the ARC. For more information, see <a href="#">Policy Statement Options</a> .
<b>Focus</b>	
<b>Targets</b>	Specifies the target hosts for the ARC to analyze:



Option	Description
	<ul style="list-style-type: none"><li>• <b>All Systems</b> —Targets all available hosts.</li><li>• <b>Assets</b> —Targets the specified assets. For more information, see <a href="#">Assets</a>.</li></ul> <div style="border: 1px solid green; padding: 5px;"><p><b>Tip:</b> Use NOT, OR, and AND operators to exclude unwanted assets from the view.</p></div> <ul style="list-style-type: none"><li>• <b>IPs</b> —Targets the specified IP addresses. You can specify single addresses, IP addresses in CIDR notation, and IP ranges.</li><li>• <b>Repositories</b> —Targets the specified repositories. For more information, see <a href="#">Repositories</a>.</li></ul> <p>If you want to match the specified assets or IP addresses against one or more repositories, select the repositories you want to match against.</p> <div style="border: 1px solid blue; padding: 5px;"><p><b>Note:</b> If an IP address you specified appears in two or more repositories you selected, the duplicated IP address negatively skews the ARC results.</p></div>

## Policy Statement Options

Option	Description
<b>Basic</b>	
<b>Statement</b>	Specifies pass/fail criteria for the policy statement.
<b>Display</b>	Specifies how the ARC displays the policy statement: <b>Ratio (x/y)</b> , <b>Percentage (%)</b> , or <b>Compliant/ Non-Compliant</b> .
<b>Advanced</b>	
<b>Data Type</b>	The type of data you want the ARC to analyze: <b>Vulnerabilities</b> or <b>Events</b> .
<b>Base Filters</b>	The filters used as the basis for data analysis. <ul style="list-style-type: none"><li>• If the <b>Data Type</b> is <b>Vulnerabilities</b>, you can select from the list of <a href="#">vulnerability analysis filter components</a>.</li></ul>



Option	Description
<b>Compliant Filters</b>	<ul style="list-style-type: none"><li>• If the <b>Data Type</b> is <b>Events</b>, you can select from a list of <a href="#">event analysis filter components</a>.</li></ul> <p>The filters used to determine the compliance conditions for the data analysis. For more information, see <a href="#">Vulnerability Analysis</a> and <a href="#">Event Analysis</a>.</p> <ul style="list-style-type: none"><li>• If the <b>Data Type</b> is <b>Vulnerabilities</b>, you can select from the list of <a href="#">vulnerability analysis filter components</a>.</li><li>• If the <b>Data Type</b> is <b>Events</b>, you can select from a list of <a href="#">event analysis filter components</a>.</li></ul> <div data-bbox="396 730 1479 888" style="border: 1px solid #0070C0; padding: 5px;"><p><b>Note:</b> Filters set in <b>Base Filters</b> are not present in <b>Compliant Filters</b>, with exception of the Assets and Plugin IDs. All filters set in <b>Base Filters</b> are carried over into <b>Compliant Filters</b>.</p></div>
<b>Compliant Condition</b>	<p>Specifies the conditions to match for determining compliance. For more information, see <a href="#">Vulnerability Analysis</a> and <a href="#">Event Analysis</a>.</p> <p>Specify a quantity: <b>All</b>, <b>No</b>, <b>Any</b>, <b>&gt;</b> (greater than), <b>&lt;</b> (less than), <b>&gt;=</b> (greater than or equal to), and <b>&lt;=</b> (less than or equal to).</p> <p>Specify hosts: <b>Hosts</b>, <b>Vulnerabilities</b>, and <b>Ports</b>.</p>
<b>Drilldown Filters</b>	<p>The filters to apply when clicking on the ARC policy statement for more details. For more information, see <a href="#">Vulnerability Analysis</a> and <a href="#">Event Analysis</a>.</p> <ul style="list-style-type: none"><li>• If the <b>Data Type</b> is <b>Vulnerabilities</b>, you can select from the list of <a href="#">vulnerability analysis filter components</a>.</li><li>• If the <b>Data Type</b> is <b>Events</b>, you can select from a list of <a href="#">event analysis filter components</a>.</li></ul>



---

## Filters

---

You can apply filters on many pages of the Tenable Security Center web interface to filter the data displayed on the page.

You can build filters using one or more *filter components* with defined *filter component criteria*. Filter components are types of data (e.g., **CVE ID** or **Severity**). After you select a filter component, you specify the filter component criteria (e.g., a specific CVE ID or a specific severity level).

If you want to save a filter for repeated use, create a query, as described in [Queries](#).

For more information, see:

- [Apply a Filter](#)
- [Filter Components](#)
- [Vulnerability Analysis Filter Components](#)
- [Event Analysis Filter Components](#)
- [Mobile Analysis Filter Components](#)
- [Host Asset Filter Components](#)



## Apply a Filter


**Required User Role:** Any

You can use filters to narrow the data displayed on specific pages.


Each filterable page in Tenable Security Center has a different set of filter components. On the **Vulnerabilities**, **Events**, and **Mobile** pages, you can add and remove filter components.

For more information, see [Filters](#) and [Filter Components](#).

To filter data:

1. Log in to Tenable Security Center via the user interface.
2. Navigate to any page that supports filtering.
3. On the left side of the page, click the  button.

The filter panel appears.



4. (Optional) To customize the filter components on an analysis page, do the following:

- a. Click **Customize**.

The filter components selection window appears.

- b. Select one or more filter component check boxes. For more information about the components supported for your analysis view, see [Vulnerability Analysis Filter Components](#), [Event Analysis Filter Components](#), [Mobile Analysis Filter Components](#), and [Host Asset Filter Components](#).

- c. Click **Apply**.

The filter panel updates to show the filter components you selected.





5. To modify the criteria for a filter component, click the box for the filter component.

The filter component criteria selection window appears.

6. Modify the filter component criteria.

7. Click **OK**.

The filter panel updates to show the filter component criteria you modified.

8. Click **Apply**.

The page updates to reflect the filter you applied.

What to do next:

- (Optional) Save a filter on the **Vulnerabilities** page, **Events** page, and **Mobile** page as a reusable query, as described in [Add or Save a Query](#).



## Filter Components

For general information about using filters, see [Filters](#).

Filter Component	Description
<b>Access</b>	The level of object access to include in the filter: <ul style="list-style-type: none"><li>• <b>Manageable</b> —Shows the objects your user account can modify. For example, set the filter to show only the credentials you can edit.</li><li>• <b>Usable</b> —Shows the objects your user account can view or use. For example, set the filter to show only the credentials you can use in a scan.</li></ul>
<b>Actions</b>	The alert actions to include in the filter: <b>Email, Notify, Report, Scan, SysLog, or Ticket</b> . For more information, see <a href="#">Alerts</a> and <a href="#">Alert Actions</a> .
<b>Agent Scanner</b>	The agent scanners to include in the filter. For more information, see <a href="#">Agent Scanning</a> .
<b>Assignee</b>	The ticket assignees to include in the filter. For more information, see <a href="#">Tickets</a> .
<b>Authorized</b>	The Log Correlation Engine Client authorization status to include in the filter: <b>yes</b> or <b>no</b> .
<b>Client IP</b>	The Log Correlation Engine Client IP addresses to include in the filter. For more information, see <a href="#">Tenable Log Correlation Engine Clients</a> .
<b>Completion Time</b>	The date range for scan results to include in the filter: <ul style="list-style-type: none"><li>• <b>Explicit</b> —Choose start and end dates and times to filter for a specific date range.</li><li>• <b>Last x Minutes</b> —Filter for the last 15, 20, or 30 minutes.</li><li>• <b>Last x Hours</b> —Filter for the last 1, 2, 4, 6, 12, 24, 48, or 72 hours.</li><li>• <b>Last x Days</b> —Filter for the last 5, 7, 15, 25, 30, 60, 90, 120, or 180 days.</li></ul>



Filter Component	Description
	<ul style="list-style-type: none"><li>• <b>Last 12 Months</b> —Filter for the last year.</li><li>• <b>All</b> —Show all results.</li></ul>
<b>Creator</b>	The ticket creators to include in the filter. For more information, see <a href="#">Tickets</a> .
<b>Data Type</b>	The repository data type to include in the filter: <b>Agent</b> , <b>IPv4</b> , <b>IPv6</b> , or <b>Mobile</b> . For more information, see <a href="#">Repositories</a> .
<b>Date</b>	The date range to include in the system log filter (for example, <i>Oct 2021</i> ). For more information, see <a href="#">System Logs</a> .
<b>Filter By</b>	The type of plugin data to include in the plugin filter. For more information, see <a href="#">Vulnerability Analysis Filter Components</a> .
<b>Finish Time</b>	The date range for report results to include in the filter: <ul style="list-style-type: none"><li>• <b>Explicit</b> —Choose start and end dates and times to filter for a specific date range.</li><li>• <b>Last x Minutes</b> —Filter for the last 15, 20, or 30 minutes.</li><li>• <b>Last x Hours</b> —Filter for the last 1, 2, 4, 6, 12, 24, 48, or 72 hours.</li><li>• <b>Last x Days</b> —Filter for the last 5, 7, 15, 25, 30, 60, 90, 120, or 180 days.</li><li>• <b>Last 12 Months</b> —Filter for the last year.</li><li>• <b>All</b> —Show all results.</li></ul>
<b>Group</b>	The groups to include in the filter. For more information, see <a href="#">Groups</a> .
<b>Host</b>	The name of the host to include in the filter. For more information, see <a href="#">Host</a> .
<b>Initiator</b>	The username for a user who initiated a job to include in the filter. For more information, see <a href="#">Job Queue Events</a> .
<b>Keywords</b>	The keywords to include in the system logs filter (for example, <i>login</i> ). For



Filter Component	Description
	more information, see <a href="#">System Logs</a> .
<b>Log Correlation Engine Server</b>	The Log Correlation Engine servers to include in the filter. For more information, see <a href="#">Tenable Log Correlation Engines</a> .
<b>Module</b>	The type of logs to include in the system logs filter. For more information, see <a href="#">System Logs</a> .
<b>Name</b>	The name of the object or user to include in the filter. For example, the name of a Tenable Nessus scanner or the name of a repository.
<b>Organization</b>	The organization to include in the filter. For more information, see <a href="#">Organizations</a> .
<b>OS</b>	The operating systems to include in the filter. For more information, see <a href="#">Tenable Log Correlation Engine Clients</a> and <a href="#">Tenable Log Correlation Engine Client Policies</a> .
<b>Owner</b>	The object owners to include in the filter. The object owner is the user who created an object or inherited objects from a deleted user.
<b>Plugin</b>	The plugin IDs to include in the filter.
<b>Plugin Family</b>	The plugin family to include in the plugin filter.
<b>Repositories</b>	The repositories to include in the filter. For more information, see <a href="#">Repositories</a> .
<b>Repository</b>	The repository to include in the filter. For more information, see <a href="#">Repositories</a> .
<b>Role</b>	The user roles to include in the filter. For more information, see <a href="#">User Roles</a> .
<b>Scan Policy</b>	The scan policies to include in the filter. For more information, see <a href="#">Scan Policies</a> .
<b>Schedule</b>	The schedules to include in the filter. For more information, see <a href="#">Active Scan Settings</a> , <a href="#">Agent Scan Settings</a> , <a href="#">Agent Synchronization Job Settings</a> ,



Filter Component	Description
	and <a href="#">Report Options</a> .
<b>Severity</b>	The severity to include in the filter. For more information, see <a href="#">CVSS vs. VPR</a> .
<b>State</b>	The Log Correlation Engine Client state to include in the filter: <b>Alive</b> or <b>Dead</b> . For more information, see <a href="#">Tenable Log Correlation Engine Clients</a> .
<b>Status</b>	The statuses to include in the filter.
<b>Tags</b>	The tags to include in the filter. For more information, see <a href="#">Tags</a> .
<b>Timeframe</b>	The date range to include in the notification filter: <b>Last 24 Hours</b> , <b>Last 7 Days</b> , or <b>Last 30 Days</b> .
<b>Type</b>	The object type (for example, <b>Active</b> or <b>Agent</b> scan results).
<b>Username</b>	The username to include in the filter. For more information, see <a href="#">User Account Options</a> .
<b>Version</b>	The Log Correlation Engine version to include in the filter. For more information, see <a href="#">Tenable Log Correlation Engines</a> .



---

## Queries

---

The **Queries** page displays a list of queries available for use. The information on this page includes **Name**, **Type**, **Group**, **Owner**, and the **Last Modified** time. You can use a filter to narrow the list by any of the columns (except **Last Modified**). For more information, see [Filters](#).

For more information about queries, see:

- [Add or Save a Query](#)
- [Load a Query](#)
- [Query Options](#)
- [Edit a Query](#)



## Add or Save a Query

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can add queries from the **Queries** page or from the **Vulnerabilities** page, **Events** page, or **Mobile** page. For more information about query options, see [Queries](#).

**Note:** If you want to create a mitigated vulnerabilities query, you must add the query from the **Vulnerabilities** page.

To add a query from the **Queries** page:

1. Log in to Tenable Security Center via the user interface.
2. Click **Analysis > Queries**.  
The **Queries** page appears.
3. At the top of the table, click **Add**.
4. Type a **Name** and **Description**.
5. (Optional) If you want to add a tag, type select a **Tag** from the drop-down. For more information, see [Tags](#).
6. Select a **Type**.  
The **Tool** drop-down updates with options for that type.
7. Select a **Tool**.
8. Click **Add Filter**.  
The **Filters** section expands. For more information, see [Filters](#).
9. Select a filter component from the **Select a Filter** drop-down.  
The filter component criteria box appears.
10. In the filter component criteria box, type or select filter component criteria.
11. Click the **✓** button.



Tenable Security Center adds the filter component.

12. (Optional) To add other filter components, repeat step 8.
13. Click **Submit**.

Tenable Security Center saves your configuration.

To save a query from an analysis page:

1. Log in to Tenable Security Center via the user interface.
2. Do one of the following to navigate to an analysis page:
  - Click **Analysis > Vulnerabilities**
  - Click **Analysis > Events**
  - Click **Analysis > Mobile**

The analysis page appears.

3. Apply a filter for the query, as described in [Apply a Filter](#).

The page updates to reflect the filter you applied.

4. Click **Save > Save Query**.

The **Save Query** panel appears.

5. In the **Name** box, type a name for the query.
6. In the **Description** box, type a description for the query.
7. (Optional) If you want to add a tag, type or select a **Tag** from the drop-down. For more information, see [Tags](#).
8. Click **Submit**.

Tenable Security Center saves your configuration.






## Load a Query

**Required User Role:** Any

You can load queries from any page that supports filtering. For more information, see [Queries](#) and [Filters](#).

To load a query:

1. Log in to Tenable Security Center via the user interface.
2. Navigate to any page that supports filtering.
3. On the left side of the page, click the filter icon (.

The filter panel appears.

4. Click **Load Query**.
5. Select the query you want to load.
6. Click **Apply**.

The page updates, filtered by the query you selected.



## Query Options

Queries provide the ability to save custom views of vulnerability, event, ticket, user, and alert data for repeated access.

Option	Description
<b>Name</b>	A name for the query.
<b>Description</b>	A description for the query.
<b>Tag</b>	A tag for the query. For more information, see <a href="#">Tags</a> .
<b>Type</b>	<p>The type of data you want the query to use.</p> <p>For more information about the filter components for <b>Vulnerability</b>, <b>Event</b>, and <b>Mobile</b> data types, see <a href="#">Vulnerability Analysis Filter Components</a>, <a href="#">Event Analysis Filter Components</a>, and <a href="#">Mobile Analysis</a>.</p> <p>For more information about the filter components for <b>Ticket</b>, <b>User</b>, and <b>Alert</b> data types, see <a href="#">Ticket-Specific Query Options</a>, <a href="#">User-Specific Query Options</a>, and <a href="#">Alert-Specific Query Options</a>.</p>
<b>Tool</b>	Chooses the analysis tool used by the query.

## Ticket-Specific Query Options

Ticket queries are a useful way of determining what tickets to alert against. For example, if you want to be alerted when a specific user receives a ticket, you could create a query with a ticket filter where the **Assignee** value is the user's name. You could then create an alert to email you when the user receives a ticket. The table below contains a list of the ticket query options.

Option	Description
<b>Name</b>	Ticket name to filter against
<b>Status</b>	Ticket status to filter against.
<b>Classification</b>	The ticket classification to filter against.
<b>Owner</b>	The manager (owner) of the ticket assignee.



Option	Description
<b>Assignee</b>	The ticket assignee to filter against.
<b>Created Time-frame</b>	Ticket creation date/time to filter against. Either specify an explicit time-frame, including the start and end time or choose one of the predefined periods (e.g., last 15 minutes, last hour, etc.)
<b>Assigned Time-frame</b>	Ticket assigned date/time to filter against. Either specify an explicit time-frame, including the start and end time or choose one of the predefined periods (e.g., last 15 minutes, last hour, etc.)
<b>Modified Time-frame</b>	Ticket modified date/time to filter against. Either specify an explicit time-frame, including the start and end time or choose one of the predefined periods (e.g., last 15 minutes, last hour, etc.)
<b>Resolved Time-frame</b>	Ticket resolution date/time to filter against. Either specify an explicit time-frame, including the start and end time or choose one of the predefined periods (e.g., last 15 minutes, last hour, etc.)
<b>Closed Time-frame</b>	Ticket closed date/time to filter against. Either specify an explicit time-frame, including the start and end time or choose one of the predefined periods (e.g., last 15 minutes, last hour, etc.)

## User-Specific Query Options

User queries are useful for reporting, dashboards and alerts based on user actions. For example, they can track user logins and locked accounts. They can also track user logins from accounts not authorized on the monitored systems.

Option	Description
<b>First Name</b>	User first name to filter against.
<b>Last Name</b>	User last name to filter against.
<b>Username</b>	Actual username to filter against.
<b>Group</b>	Filter against the group the user(s) belong to.



Option	Description
<b>Role</b>	Filters against users who have the specified role.
<b>Email</b>	Filters against users based on their email address.
<b>Last Login Timeframe</b>	Filters against users whose last login was that the timeframe specified. Either specify an explicit timeframe, including the start and end time or choose one of the predefined periods (e.g., last 15 minutes, last hour, etc.).
<b>Account State</b>	Filters against the user account state (locked vs. unlocked).

## Alert-Specific Query Options

The alert query is useful for reporting, dashboards and alerting when an alert has triggered. This is useful for situations where you want a report, dashboard element, or conditional alert after the specified alert filter conditions have been met. For example, you can schedule a daily report containing a query of all active alerts and their details.

Option	Description
<b>Name</b>	Filter against alerts with the specified name.
<b>Description</b>	Filter against alerts with the specified description.
<b>State</b>	Choose from <b>All</b> , <b>Triggered</b> , or <b>Not Triggered</b> .
<b>Created Timeframe</b>	Filters against the alert creation timeframe specified. Either specify an explicit timeframe, including the start and end time or choose one of the predefined periods (e.g., last 15 minutes, last hour, etc.).
<b>Modified Timeframe</b>	Filters against the most recent alert modification timeframe specified. Either specify an explicit timeframe, including the start and end time or choose one of the predefined periods (e.g., last 15 minutes, last hour, etc.).
<b>Last Triggered Timeframe</b>	Filters against the most recent alert trigger timeframe specified. Either specify an explicit timeframe, including the start and end time or choose one of the predefined periods (e.g., last 15 minutes, last hour, etc.).
<b>Last Evaluated Timeframe</b>	Filters against the most recent alert evaluation timeframe specified. Either specify an explicit timeframe, including the start and end time or choose one of the predefined periods (e.g., last 15 minutes, last hour, etc.).



## Edit a Query

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information, see [Query Options](#).

To edit a query:

1. Log in to Tenable Security Center via the user interface.
2. Click **Analysis > Queries**.

The **Queries** page appears.

3. In the table, right-click the row for the query you want to edit.

The actions menu appears.

-or-

In the table, select the check box for the query you want to edit.

The available actions appear at the top of the table.

4. Click **Edit**.

The **Edit Query** page appears.

5. Modify the query options.
6. Click **Submit**.

Tenable Security Center saves the modified query.



---

## Workflow Actions

---

Workflow actions allow organizational users to configure and manage alerting, ticketing, and accept risk or recast risk rules. These functions allow the user to be notified of and properly handle vulnerabilities and events as they come in.

For more information, see [Alerts](#), [Tickets](#), [Accept Risk Rules](#), and [Recast Risk Rules](#).



---

## Alerts

---

Tenable Security Center can be configured to perform actions, such as email alerts, for select vulnerability or alert occurrences to various users regardless of whether the events correlate to a local vulnerability or not. Other alert actions include UI notifications, creating or assigning tickets, remediation scans, launching a report, email notifications, and syslog alerting. Multiple actions can be assigned for each ticket.

For more information, see:

- [Alert Actions](#)
- [Add an Alert](#)
- [View Alert Details](#)
- [Alert Options](#)
- [Edit an Alert](#)
- [Evaluate an Alert](#)
- [Delete an Alert](#)



## Alert Actions

Tenable Security Center automatically performs *alert actions* when an alert triggers. You can configure the following types of alert actions:

- [Assign Ticket](#)
- [Email](#)
- [Generate Syslog](#)
- [Launch Scan](#)
- [Launch Report](#)
- [Notify Users](#)

**Tip:** Use email alerts to interface with third-party ticketing systems by adding variables in the message option.

For more information, see [Alerts](#).

### Assign Ticket

When the alert triggers, Tenable Security Center creates a ticket and assigns the ticket to a user. For more information, see [Tickets](#).

Option	Description	Default
<b>Name</b>	(Required) The name of the ticket.	Ticket opened by alert
<b>Description</b>	A description for the ticket.	--
<b>Assignee</b>	(Required) The user who receives the ticket.	--

### Email

When the alert triggers, Tenable Security Center sends an email.

Option	Description	Default
<b>Email</b>		





Subject	The alert email subject line.	Email Alert
<b>Message</b>	<p>The body of the email message. You can include the following variables to customize the email:</p> <ul style="list-style-type: none"><li>• <b>Alert ID</b> —Designated with the variable: %alertID%, this specifies the unique identification number assigned to the alert by Tenable Security Center.</li><li>• <b>Alert name</b> —Designated with the variable: %alertName%, this specifies the name assigned to the alert (for example, “Test email alert”).</li><li>• <b>Trigger Name</b> —Designated with the variable: %triggerName%, this specifies if the trigger is IP address count, Vulnerability count, or Port count.</li><li>• <b>Trigger Operator</b> —Designated with the variable: %triggerOperator%, this specifies the operator used for the count: &gt;=, =, &lt;= or !=</li><li>• <b>Trigger value</b> —Designated with the variable: %triggerValue%, this specifies the specific threshold value set that triggers the alert.</li><li>• <b>Calculated value</b> —Designated with the variable: %calculatedValue%, this specifies the actual value that triggered the alert.</li><li>• <b>Alert Name</b> —Designated with the variable: %alertName%, this specifies the name given to the alert within Tenable Security Center.</li><li>• <b>Alert owner</b> —Designated with the variable: %owner%, this specifies the user that created the alert.</li><li>• <b>Tenable Security Center URL</b> —Designated with the variable: %url%, this specifies the URL that you use</li></ul>	(see description)



	<p>to access Tenable Security Center. This is useful where the URL that users use to access Tenable Security Center differs from the URL known by Tenable Security Center.</p> <p>The following sample email alert contains some of these keywords embedded into an HTML email:</p> <pre>Alert &lt;strong&gt;%alertName%/strong&gt; (id #%alertID%) has triggered.  &lt;strong&gt;Alert Definition:&lt;/strong&gt; %triggerName% %triggerOperator% %triggerValue% &lt;strong&gt;Calculated Value:&lt;/strong&gt; %calculatedValue%  Please visit your <b>Tenable Security Center</b> (&lt;a href="%url%"&gt;%url%/a&gt;) for more information. This e-mail was automatically generated by <b>Tenable Security Center</b> as a result of alert &lt;strong&gt;%alertName%/strong&gt; owned by &lt;strong&gt;%owner%/strong&gt;.<!--  If you do not wish to receive this email, contact the alert owner.</pre--></pre>	
<b>Include Results</b>	When enabled, Tenable Security Center includes the query results that triggered the alert (maximum of 500).	Disabled
<b>Recipients</b>		
<b>Users</b>	The users who receive the alert email. <div data-bbox="394 1583 1206 1818" style="border: 1px solid green; padding: 5px;"><b>Tip:</b> If you delete a user who receives alert emails, the action option for the alert turns red and Tenable Security Center displays a notification to the new alert owner with the new alert status. To resolve this, update the list of users in the alert email.</div>	--



<b>Email Addresses</b>	Specifies additional email addresses to include in the alert email. For multiple recipients, add one email address per line or use a comma-separated list.	--
------------------------	--	----

## Generate Syslog

When the alert triggers, Tenable Security Center sends a custom message to a syslog server.

Option	Description	Default
<b>Host</b>	(Required) The host that receives the syslog alert.	--
<b>Port</b>	The UDP port used by the remote syslog server.	514
<b>Severity</b>	The severity level of the syslog messages ( <b>Critical</b> , <b>Notice</b> , or <b>Warning</b> ).	Critical
<b>Message</b>	(Required) The message Tenable Security Center sends with the syslog alert.	--

## Launch Scan

When the alert triggers, Tenable Security Center launches an active scan from an existing active scan template. The active scan **Schedule** must be **On Demand**. For more information, see [Active Scans](#) and [Active Scan Settings](#).

Option	Description	Default
<b>Scan</b>	(Required) The scan template Tenable Security Center uses for the alert scan. <div style="border: 1px solid blue; padding: 5px; margin-top: 10px;"><b>Note:</b> Tenable Security Center scans the host that triggered the scan, not the host within the scan template. Tenable Security Center uses the top 100 IP results from the alert query for the scan targets.</div>	--

## Launch Report

When the alert triggers, Tenable Security Center generates a report from an existing report template. For more information, see [Reports](#).



Option	Description	Default
<b>Report Template</b>	(Required) The report template Tenable Security Center uses to generate a report based on the triggered alert data.	--

## Notify Users

When the alert triggers, Tenable Security Center displays a notification to the specified users.

Option	Description	Default
<b>Message</b>	(Required) The notification message Tenable Security Center sends when the alert triggers.	--
<b>Users</b>	(Required) The users who receive the notification message.	--



## Add an Alert

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can configure Tenable Security Center to send alerts for vulnerability occurrences.

For more information about the available options for alerts, see [Alert Options](#).

To add an alert:

1. Log in to Tenable Security Center via the user interface.
2. Click **Workflow > Alerts**.  
The **Alerts** page appears.
3. Click **Add**.  
The **Add Alert** page appears.
4. In the **Name** box, type a name.
5. (Optional) In the **Description** box, type a description.
6. (Optional) Click the **Schedule** field to select the frequency of alerts, time, timezone, and whether to repeat sending alerts at the specified time.
7. (Optional) In the **Behavior** drop-down box, select the condition you want to trigger the alert.  
The default is **Perform actions only on first trigger**.
8. (Optional) In the **Type** drop-down box, select the data type for the condition.
9. In the **Trigger** drop-down box, select the trigger for the alerts.
10. (Optional) In the **Query** drop-down box, select the dataset to compare with the trigger condition.
11. (Optional) Click **Add Filter** and provide the details of the selected filter.
12. Click **Add Actions** to specify an action that occurs when the alert triggers. For more information, see [Alert Actions](#).
13. Click **Submit**.  
Tenable Security Center creates the alert.



## View Alert Details

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can view the summary details of an alert with the name, behavior, condition applied, status, created date, owner, and ID.

To view the details of an alert:

1. Log in to Tenable Security Center via the user interface.
2. Click **Workflow > Alerts**.

The **Alerts** page appears.

3. In the table, right-click the row for the alert you want to view.

The actions menu appears.

-or-

In the table, select the check box for the alert you want to view.

The available actions appear at the top of the table.

4. Click **View**.

The **View Alert** page appears. For more information about the following fields, see [Alert Options](#).

Section	Action
<b>Options</b> drop-down box	<ul style="list-style-type: none"><li>• To edit the alert, click <b>Edit</b>. For more information, see <a href="#">Edit an Alert</a>.</li><li>• To delete the alert, click <b>Delete</b>. For more information, see <a href="#">Delete an Alert</a>.</li></ul>
<b>General</b>	<p>View general information about the alert.</p> <ul style="list-style-type: none"><li>• <b>Name</b> —Alert name.</li><li>• <b>Description</b> —Descriptive text for the alert.</li></ul>



Section	Action
	<ul style="list-style-type: none"><li>• <b>Schedule</b> —The schedule for how often the alert checks for matching conditions.</li><li>• <b>Behavior</b> —The setting for how the alert behaves once it is triggered.</li><li>• <b>Last Evaluated</b> —The date on which the alert was last evaluated.</li><li>• <b>Last Triggered</b> —The date on which the alert was last triggered.</li><li>• <b>Status</b> —The status of the alert.</li><li>• <b>Created</b> —The date on which the alert was created.</li><li>• <b>Last Modified</b> —The date on which the alert was last modified.</li><li>• <b>Owner</b> —The user who created or owns the alert.</li><li>• <b>Group</b> —The group associated with the <b>Owner</b>.</li><li>• <b>ID</b> —The unique identifier of the alert.</li></ul>
<b>Condition</b>	View the conditions specified for the alert: <ul style="list-style-type: none"><li>• <b>Type</b> —The type of the alert. For example, vulnerability, event, or ticket.</li><li>• <b>Trigger</b> —The condition that triggers the alert. For example, IP count, unique vulnerability/event count, or port count.</li><li>• <b>Query</b> —The dataset to which the trigger condition is compared.</li><li>• <b>Filters</b> —The filters added for vulnerability or event data.</li></ul>
<b>Actions</b>	The actions performed once the alert is triggered.



## Alert Options

The following options are available when you create or edit an alert in Tenable Security Center.

Option	Description
<b>General</b>	
<b>Name</b>	The name of the alert.
<b>Description</b>	A description for the alert.
<b>Schedule</b>	Specifies how often the alert checks for the conditions to be matched: <b>Minutely, Hourly, Daily, Weekly, Monthly, or Never</b> .  Select <b>Never</b> to create an alert that you trigger manually on demand.
<b>Behavior</b>	Specifies how many times Tenable Security Center performs the alert actions: <ul style="list-style-type: none"><li>• <b>Perform actions only on first trigger</b> —Tenable Security Center performs the alert actions only the first time the alert conditions match the trigger configuration.</li><li>• <b>Perform action on every trigger</b> —Tenable Security Center performs the alert actions every time the alert conditions match the trigger configuration.</li></ul>
<b>Condition</b>	
<b>Type</b>	The type of data to use for the condition: <b>Vulnerability, Event, or Ticket</b> .
<b>Trigger</b>	<ul style="list-style-type: none"><li>• <b>IP Count</b> —Trigger on vulnerabilities or events whose IP address count matches the given parameters.</li><li>• <b>Unique Vulnerability Count</b> —Trigger an alert when the unique vulnerability count matches the given parameters. This option appears when you select <b>Vulnerability</b> for the <b>Type</b> option.</li><li>• <b>Event Count</b> —Trigger an alert when the event count matches the given parameters. This option appears when you select <b>Event</b> for the <b>Type</b> option.</li></ul>





Option	Description
<b>General</b>	
	<ul style="list-style-type: none"><li>• <b>Port Count</b> —Trigger an alert when the events or vulnerabilities using a certain port number match the given parameters.</li></ul>
<b>Query</b>	The dataset Tenable Security Center uses to determine if trigger conditions have been met.
<b>Filters</b>	Apply advanced filters to the vulnerability or event data. For more information, see <a href="#">Filters</a> .
<b>Actions</b>	
<b>Add Actions</b>	Specifies the actions that occur when the alter triggers: <b>Assign Ticket</b> , <b>Email</b> , <b>Generate Syslog</b> , <b>Launch Scan</b> , <b>Launch Report</b> , or <b>Notify Users</b> . For more information, see <a href="#">Alert Actions</a> .



## Edit an Alert

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

For more information, see [Alert Options](#).

To edit an alert:

1. Log in to Tenable Security Center via the user interface.

2. Click **Workflow > Alerts**.

The **Alerts** page appears.

3. In the table, right-click the row for the alert you want to edit.

The actions menu appears.

-or-

In the table, select the check box for the alert you want to edit.

The available actions appear at the top of the table.

4. Click **More > Edit**.

The **Edit Alert** page appears.

5. Modify the alert options.

6. Click **Submit**.

Tenable Security Center saves the modified alert.



## Evaluate an Alert

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can submit an alert for evaluation to test whether the alert has met the configured time criteria or not.

To evaluate an alert:

1. Log in to Tenable Security Center via the user interface.

2. Click **Workflow > Alerts**.

The **Alerts** page appears.

3. In the table, right-click the row for the alert you want to evaluate.

The actions menu appears.

-or-

In the table, select the check box for the alert you want to evaluate.

The available actions appear at the top of the table.

4. Click **Evaluate**.

The alert is submitted for evaluation.

Tenable Security Center returns the evaluation results for the alert.



## Delete an Alert

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

To delete an alert:

1. Log in to Tenable Security Center via the user interface.

2. Click **Workflow > Alerts**.

The **Alerts** page appears.

3. In the table, right-click the row for the alert you want to delete.

The actions menu appears.

-or-

In the table, select the check box for the alert you want to delete.

The available actions appear at the top of the table.

4. Click **More > Delete**.

A confirmation window appears.

5. Click **Delete**.

Tenable Security Center deletes the alert.



---

# Tickets

---

In Tenable Security Center, you can create tickets manually or automatically using the [Alerts](#) feature. This section describes how to manage your tickets.

For more information, see:

- [Open a Ticket](#)
- [View Ticket Details](#)
- [Ticket Options](#)
- [Edit a Ticket](#)
- [Resolve and Close a Ticket](#)



## Open a Ticket

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can use tickets within Tenable Security Center to coordinate the assessment and remediation of vulnerabilities and security events.

You can configure a ticket from an analysis page, or from the **Tickets** page. For more information about the options to configure, see [Tickets](#).

To open a ticket from an analysis page:

1. Log in to Tenable Security Center via the user interface.
2. Click **Analysis > Vulnerabilities** or **Analysis > Events**.  
The **Vulnerabilities** or **Events** page appears.
3. From the toolbar, click **More > Open Ticket**.  
The **Open Ticket** pane appears.
4. In the **Name** box, type a name.
5. (Optional) In the **Description** box, type a description.
6. (Optional) In the **Notes** box, type a note to the assignee.
7. In the **Assignee** drop-down box, select an assignee.
8. In the **Classification** drop-down box, select a classification.
9. Click **Submit**.

Tenable Security Center creates the ticket.

To open a ticket from the **Tickets** page:

1. Log in to Tenable Security Center via the user interface.
2. Click **Workflow > Tickets**.

The **Tickets** page appears.



3. Click **Add**.
4. In the **Name** box, type a name.
5. (Optional) In the **Description** box, type a description.
6. (Optional) In the **Notes** box, type a note to the assignee.
7. In the **Assignee** drop-down box, select an assignee.
8. In the **Classification** drop-down box, select a classification.
9. (Optional) Click **Add Query View**.
10. Click **Submit**.

Tenable Security Center creates the ticket.



## View Ticket Details

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

You can view the summary details of a ticket with the name, status, creator, assignee, history, queries, description, and ticket notes.

Before you begin:

- Add a ticket, as described in [Open a Ticket](#).

To edit a ticket:

1. Log in to Tenable Security Center via the user interface.
2. Click **Workflow > Tickets**.

The **Tickets** page appears.

3. In the table, right-click the row for the ticket you want to view.

The actions menu appears.

-or-

In the table, select the check box for the ticket you want to view.

The available actions appear at the top of the table.

4. Click **View**.

The **View Ticket** page appears. For more information, see [Ticket Options](#).

Section	Action
<b>Options</b> drop-down box	<ul style="list-style-type: none"><li>• To edit the ticket, click <b>Edit</b>. For more information, see <a href="#">Edit a Ticket</a>.</li></ul>
<b>General</b>	<p>View general information about the ticket.</p> <ul style="list-style-type: none"><li>• <b>Name</b> —The ticket name.</li><li>• <b>Description</b> —The ticket description.</li></ul>





Section	Action
	<ul style="list-style-type: none"><li>• <b>Notes</b> —The notes added for the ticket.</li><li>• <b>Status</b> —The status of the ticket.</li><li>• <b>Assignee</b> —The user assigned to the ticket.</li><li>• <b>Classification</b> —The classification selected for the ticket.</li><li>• <b>Created</b> —The date on which the ticket was created.</li><li>• <b>Last Modified</b> —The date on which the ticket was last modified.</li><li>• <b>Owner</b> —The user who created or owns the ticket.</li><li>• <b>Group</b> —The group associated with the <b>Owner</b>.</li><li>• <b>ID</b> —The unique identifier of the ticket.</li></ul>
<b>Query Views</b>	The query added to help provide context for coming up with a resolution.



# Ticket Options

The following options are available when you create or edit a ticket in Tenable Security Center.

Option	Description
<b>General</b>	
<b>Name</b>	Name assigned to the ticket.
<b>Description</b>	Descriptive text for the ticket.
<b>Notes</b>	Notes for the ticket assignee.
<b>Assignee</b>	User that the ticket is assigned to. <div style="border: 1px solid blue; padding: 5px; margin-top: 10px;"><b>Note:</b> If the ticket assignee is deleted, the ticket is automatically reassigned to the assignee's owner along with a notification message indicating that the ticket has been reassigned.</div>
<b>Status</b> (Available during edit)	The following ticket statuses become available after a ticket has been created and are available from the <b>Edit Ticket</b> page: <ul style="list-style-type: none"><li>• <b>Assigned</b></li><li>• <b>Resolved</b></li><li>• <b>More Information</b></li><li>• <b>Not Applicable</b></li><li>• <b>Duplicate</b></li><li>• <b>Closed</b></li></ul>
<b>Classification</b>	The ticket classification: <b>Information, Configuration, Patch, Disable, Firewall, Schedule, IDS, Accept Risk, Recast Risk, Re-scan Request, False Positive, System Probe, External Probe, Investigation Needed, Compromised System, Virus Incident, Bad Credentials, Unauthorized Software, Unauthorized System, Unauthorized User, and Other.</b>
<b>Query Views</b>	



Option	Description
<b>Add Query View</b>	Click to choose a query for the ticket assignee to help provide context for coming up with a resolution.



## Edit a Ticket

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

Before you begin:

- Add a ticket, as described in [Open a Ticket](#).

To edit a ticket:

1. Log in to Tenable Security Center via the user interface.

2. Click **Workflow > Tickets**.

The **Tickets** page appears.

3. In the table, right-click the row for the ticket you want to edit.

The actions menu appears.

-or-

In the table, select the check box for the ticket you want to edit.

The available actions appear at the top of the table.

4. Click **More > Edit**.

The **Edit Ticket** page appears.

5. Modify the ticket options. For more information, see [Ticket Options](#).

6. Click **Submit**.

Tenable Security Center saves your configuration.



## Resolve and Close a Ticket

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

When a ticket is mitigated, you can change the ticket status to **Resolved**. Once the ticket is resolved, you can change the status to **Closed**. Tickets in the **Resolved** or **Closed** state can always be reopened as needed.

Before you begin:

- Add a ticket, as described in [Open a Ticket](#).

To resolve a ticket:

1. Log in to Tenable Security Center via the user interface.
2. Click **Workflow > Tickets**.

The **Tickets** page appears.

3. In the table, right-click the row for the ticket you want to resolve.

The actions menu appears.

-or-

In the table, select the check box for the ticket you want to resolve.

The available actions appear at the top of the table.

4. Click **Resolve**.

The **Resolve Ticket** page appears.

5. Change the status to **Resolved**. Optionally, you can add notes to provide details of the resolution.
6. Click **Submit**.
7. To close the ticket, click the resolved ticket name and change the status to **Closed**.



Tenable Security Center updates the ticket status. Resolved tickets still show up in your ticket queue with an **Active** status. Closing a ticket removes the ticket from the **Active** status filter view, but does not provide the option to add notes similar to editing a ticket.



---

## Accept Risk Rules

---

The **Accept Risk Rules** page displays a list of accept risk rules configured in Tenable Security Center. Organizational users must add accept risk rules before the rules appear on this page. For more information, see [Add an Accept Risk Rule](#).

Adding a rule moves vulnerabilities from the unfiltered cumulative database view. These vulnerabilities are not deleted, but only display in the cumulative database vulnerability view if the **Accepted Risk** filter option is checked. For more information, see [Filters](#).

Administrator and organizational users can manage accept risk rules. You can access information on what particular vulnerabilities or hosts have been declared to be accepted and, if noted in the comments, the reason.

To view details for a rule, click the row. To delete a rule, see [Delete an Accept Risk Rule](#).



## Add an Accept Risk Rule

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

If you create an accept risk rule, Tenable Security Center automatically accepts the risk associated with any vulnerabilities that match the rule. Risk-accepted vulnerabilities do not appear in a vulnerability search if your filter excludes **Accepted Risk** vulnerabilities.

For more information, see [Accept Risk Rules](#).

To add an accept risk rule:

1. Log in to Tenable Security Center via the user interface.
2. Click **Analysis > Vulnerabilities**.

The **Vulnerabilities** page appears.

3. In the analysis tools drop-down box, select **Vulnerability Detail List**, **Vulnerability List**, or **Vulnerability Summary**.

The page refreshes to show the analysis tool view you selected.

4. To accept risk, do one of the following:

Accept Risk Rule	Actions
To accept risk rule for a single vulnerability	<ul style="list-style-type: none"><li>• Right-click any row for which you want to accept risk and select <b>Accept Risk</b>.</li><li>• Select the check box next to the vulnerability for which you want to accept risk and in the toolbar, click <b>Accept Risk</b>.</li></ul>
To accept risk rule for multiple vulnerabilities	<ul style="list-style-type: none"><li>• Select more than one row and in the toolbar, click <b>Accept Risk</b>.</li></ul>

The **Accept Risk** pane appears.

5. (Optional) In the **Comment** box, add a comment.





6. (Optional) In the **Expires** box, select the date you want the accept risk rule to expire.
7. In the **Repository** section, select one or more repositories where you want to apply the rule.
8. Click **Submit**.

Tenable Security Center saves your configuration.

**Note:** There can be a short delay between clicking on **Submit** and vulnerabilities showing the new risk acceptance. You may need to reload the filters to view the applied changes.

What to do next:

- (Optional) Enable **Recast and Accept Risk Rule Comments** to display contents of the **Comment** field in reports and vulnerability analysis views. For more information, see [Risk Rule Comments](#).



## Delete an Accept Risk Rule

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

You can delete an accept risk rule to stop accepting the risk associated with a vulnerability.

To delete an accept risk rule:

1. Log in to Tenable Security Center via the user interface.
2. Click **Workflow > Accept Risk Rules** (Organizational users) or **Repositories > Accept Risk Rules** (Administrator users).

The **Accept Risk Rules** page appears.

3. To delete a single rule:
  - a. In the table, right-click the row for the rule you want to delete.

The actions menu appears.

To delete multiple rules:

- a. In the table, select the check box for each rule you want to delete.

The available actions appear at the top of the table.

4. Click **Delete**.

A confirmation window appears.

5. Click **Delete**.

Tenable Security Center deletes the rule.

6. Click **Apply Rules**.

Tenable Security Center stops accepting the risk associated with the vulnerability.



---

## Recast Risk Rules

---

A list of recast rules configured in Tenable Security Center appears on the **Recast Risk Rules** page. Organizational users must add recast risk rules before the rules appear on this page. For more information, see [Add a Recast Risk Rule](#).

Administrator and organizational users can manage recast risk rules. You can access information on what particular vulnerabilities or hosts have had risk levels recast, their new severity level and, if noted in the comments, the reason for the severity change. You can search for rules by Plugin ID or Repository.

To view details for a rule, click the row. To delete a rule, see [Delete a Recast Risk Rule](#).



## Add a Recast Risk Rule

**Required User Role:** Organizational user with appropriate permissions. For more information, see [User Roles](#).

If you create a recast risk rule, Tenable Security Center automatically updates the severity for any vulnerabilities that match the rule to the severity you specified in the rule.

For more information, see [Recast Risk Rules](#).

To add a recast risk rule:

1. Log in to Tenable Security Center via the user interface.
2. Click **Analysis > Vulnerabilities**.

The **Vulnerabilities** page appears.

3. In the analysis tools drop-down box, select **Vulnerability Detail List**, **Vulnerability List**, or **Vulnerability Summary**.

The page refreshes to show the analysis tool view you selected.

4. To recast risk, do one of the following:

Recast Risk Rule	Actions
To recast risk rule for a single vulnerability	<ul style="list-style-type: none"><li>• Right-click any row that you want to recast and select <b>Recast Risk</b>.</li><li>• Select the check box next to the vulnerability that you want to recast and in the toolbar, click <b>Recast Risk</b>.</li></ul>
To recast rule for multiple vulnerabilities	<ul style="list-style-type: none"><li>• Select more than one row and in the toolbar, click <b>Recast Risk</b>.</li></ul>

The **Recast Risk** pane appears.

5. In the **New Severity** drop-down box, select a new severity for the vulnerability.
6. (Optional) In the **Comment** box, add a comment.
7. In the **Repository** section, select one or more repositories where you want to apply the rule.



8. Click **Submit**.

Tenable Security Center saves your configuration.

**Note:** There can be a short delay between clicking on **Submit** and vulnerabilities showing the new risk. It may be necessary to reload the filters to view the applied changes.

What to do next:

- (Optional) Enable **Recast and Accept Risk Rule Comments** to display contents of the **Comment** field in reports and vulnerability analysis views. For more information, see [Risk Rule Comments](#).



## Delete a Recast Risk Rule

**Required User Role:** Administrator or organizational user with appropriate permissions. For more information, see [User Roles](#).

You can delete a recast risk rule to remove your custom severity for a vulnerability. Then, if Tenable Security Center sees the vulnerability again, the vulnerability receives the severity currently associated with the plugin.

To delete a recast risk rule and remove your custom severity:

1. Log in to Tenable Security Center via the user interface.
2. Click **Workflow > Recast Risk Rules** (Organizational users) or **Repositories > Recast Risk Rules** (Administrator users).

The **Recast Risk Rules** page appears.

3. To delete a single rule:
  - a. In the table, right-click the row for the rule you want to delete.

The actions menu appears.

To delete multiple rules:

- a. In the table, select the check box for each rule you want to delete.

The available actions appear at the top of the table.

4. Click **Delete**.

A confirmation window appears.

5. Click **Delete**.

Tenable Security Center deletes the rule.

6. Click **Apply Rules**.

If Tenable Security Center sees the vulnerability again, the vulnerability receives the severity currently associated with the plugin.



---

## Additional Resources

---

The topics in this section offer guidance in areas related to Tenable Security Center.

- [Start, Stop, or Restart Tenable Security Center](#)
- [License Declarations](#)
- [Encryption Strength](#)
- [File and Process Allow List](#)
- [Manual Log Correlation Engine Key Exchange](#)
- [Manual Tenable Nessus SSL Certificate Exchange](#)
- [Offline Tenable Security Center Plugin and Feed Updates](#)
- [Troubleshooting](#)



# Start, Stop, or Restart Tenable Security Center

**Required User Role:** Root user

When Tenable Security Center is installed, the required services are started by default.

To change the status of Tenable Security Center:

1. Log in to Tenable Security Center via the command line interface (CLI).
2. In the CLI in Tenable Security Center, run the following command to check the status of your Tenable Security Center:

```
# service SecurityCenter status
```

The system indicates whether Tenable Security Center is running or stopped.

3. Run one of the following commands to change the status of your Tenable Security Center:

- To start Tenable Security Center, run:  

```
# /bin/systemctl start SecurityCenter
```
- To stop Tenable Security Center, run:  

```
# /bin/systemctl stop SecurityCenter
```
- To restart Tenable Security Center, run:  

```
# /bin/systemctl restart SecurityCenter
```





---

## License Declarations

---

Tenable Security Center's Software License Agreement can be found on Tenable Security Center in the `/opt/sc/docs` directory.

For a list of third-party software packages that Tenable utilizes with Tenable Security Center, see [Tenable Third-Party License Declarations](#).



## Encryption Strength

Tenable Security Center uses the following default encryption for storage and communications.

Function	Encryption
Storing TNS user account passwords	SHA-512 and the PBKDF2 function
Storing user and service accounts for scan credentials, as described in <a href="#">Credentials</a> .	AES-256-CBC
Storing scan data, as described in <a href="#">Repositories</a> .	None
Communications between Tenable Security Center and clients (Tenable Security Center users).	SSL/TLS 1.2 with the strongest encryption method supported by Tenable Security Center Apache and your browser, CLI program, or API program: ECDHE+AESGCM, EDH+AESGCM, AES256+ECDHE, or AES256+EDH.  For more information about strong encryption, see <a href="#">Configure SSL/TLS Strong Encryption</a> .
Communications between Tenable Security Center and the Tenable product registration server.	SSL/TLS 1.2 with ECDHE-RSA-AES256-GCM-SHA384
Communications between Tenable Security Center and the Tenable plugin update server.	SSL/TLS 1.2 with ECDHE-RSA-AES256-GCM-SHA384
Communications	SSL/TLS 1.2 with the strongest encryption method supported by



Function	Encryption
<p>between Tenable Security Center and:</p> <ul style="list-style-type: none"><li>• Tenable Nessus or Tenable Nessus Manager</li><li>• Tenable Vulnerability Management</li><li>• Tenable Nessus Network Monitor</li><li>• Tenable Log Correlation Engine</li></ul>	<p>Tenable Security Center Apache and your browser, CLI program, or API program: ECDHE-RSA-AES128-SHA256, ECDHE-RSA-AES128-GCM-SHA256, ECDHE-RSA-AES256-SHA384, or ECDHE-RSA-AES256-GCM-SHA384.</p>
<p>Synchronizations between Tenable Security Center and Tenable Vulnerability Management for Tenable Lumin.</p>	<p>SSL/TLS 1.2</p>



## Configure SSL/TLS Strong Encryption

You can configure SSL/TLS strong encryption for Tenable Security Center-client communications to meet the security needs of your organization. For more information about Tenable Security Center encryption, see [Encryption Strength](#).

To configure SSL/TLS strong encryptions for Tenable Security Center communications:

1. Open the `/opt/sc/support/conf/sslciphers.conf` file in a text editor.
2. Add the following content at the end of the file:

```
SSLCipherSuite <cipher you want to use for SSL/TLS encryption>
```

For example:

```
# SSL Ciphers
SSLProtocol ALL -SSLv2 -SSLv3
SSLHonorCipherOrder On
SSLCompression off
SSLCipherSuite ECDHE-RSA-AES128-SHA256:ECDHE-RSA-AES128-GCM-SHA256:ECDHE-RSA-
AES256-SHA384:ECDHE-RSA-AES256-GCM-SHA384
```

3. Restart Tenable Security Center, as described in [Start, Stop, or Restart Tenable Security Center](#).

Tenable Security Center restarts.

4. In `/opt/sc/support/logs`, open `ssl_request_log`.

The log file text appears.

5. Verify the configuration in `ssl_request_log` matches the cipher you specified. If the configuration and cipher do not match, investigate the following:
  - Confirm that you provided the cipher using correct syntax.
  - Confirm that your browser supports the cipher you provided.



- Confirm that you do not have other applications installed that redirect or layer additional encryption for SSL traffic.



## Configure Tenable Security Center for NIAP Compliance

If your organization requires that your instance of Tenable Security Center meets National Information Assurance Partnership (NIAP) standards, you can configure relevant settings to be compliant with NIAP standards.

You must run Tenable Security Center 5.15.0 or later to fully configure Tenable Security Center for NIAP compliance. If you are running Tenable Security Center 5.15.0, you must install a patch to configure Tenable Security Center for NIAP compliance. Contact Tenable Support for assistance with the required patch. For more information about upgrading Tenable Security Center, see [Before You Upgrade](#) and [Upgrade Tenable Security Center](#).

For more information about Tenable Security Center storage and communications encryption, see [Encryption Strength](#).

Before you begin:

- If you are running Tenable Security Center 5.15.0, contact Tenable Support for assistance with the required patch.
- If you are using SSL certificates to log in to Tenable Security Center, ensure your server and client certificates are NIAP-compliant. For more information about certificate authentication, see [Certificate Authentication](#).
- Confirm you have enabled the full disk encryption capabilities provided by the operating system on the host running Tenable Security Center.

To configure Tenable Security Center for NIAP compliance:

1. Log in to Tenable Security Center via the command line interface (CLI).
2. In the CLI in Tenable Security Center, as the root or tns user, run the following commands to configure strong SSL/TLS encryption for Tenable Security Center communications:

```
# /opt/sc/support/bin/sqlite3 /opt/sc/application.db "INSERT INTO Configuration (
type,name,value,visible,editable ) VALUES ( 64, 'SSLVersion', 'TLSv1_2', 'false',
'false' )"
```



```
# /opt/sc/support/bin/sqlite3 /opt/sc/application.db "INSERT INTO Configuration (
type,name,value,visible,editable ) VALUES ( 64, 'SSLCipherList', 'ECDHE-RSA-
AES128-SHA256:ECDHE-RSA-AES128-GCM-SHA256:ECDHE-RSA-AES256-SHA384:ECDHE-RSA-
AES256-GCM-SHA384', 'false', 'false' )"
```

3. Configure the Tenable Security Center web server to use strong encryption for storage and communications, as described in [Configure SSL/TLS Strong Encryption](#).

**Note:** For NIAP compliance, you must configure TLS 1.2 encryption with any of the following ciphers: ECDHE-RSA-AES128-SHA256, ECDHE-RSA-AES128-GCM-SHA256, ECDHE-RSA-AES256-SHA384, or ECDHE-RSA-AES256-GCM-SHA384.

4. If you connect Tenable Security Center to Tenable Nessus, Tenable Nessus Manager, Tenable Nessus Network Monitor, or Tenable Log Correlation Engine, you must use certificates to authenticate the connection. For more information, see [Manual Tenable Nessus SSL Certificate Exchange](#) and [Manual Log Correlation Engine Key Exchange](#).



## File and Process Allow List

If you use third-party endpoint security products such as anti-virus applications and host-based intrusion and prevention systems, Tenable recommends adding Tenable Security Center to the allow list.

If you configured supporting resources for Tenable Security Center, see the product documentation for each resource you added for more file and process allow list information. For more information about supporting resources in Tenable Security Center, see [Resources](#).

Tenable recommends allowing the following Tenable Security Center files and processes.

Allow List
Files
/opt/sc/*
Processes
/opt/sc/bin/*
/opt/sc/src/*
/opt/sc/support/bin/*
/opt/sc/www/*





# Manual Log Correlation Engine Key Exchange

**Required User Role:** Administrator

You are not normally required to make a manual key exchange between Tenable Security Center and the Log Correlation Engine; however, in some cases where you are prohibited from remote root login or required to do key exchange debugging, you must manually exchange the keys.

For the remote Log Correlation Engine to recognize Tenable Security Center, copy the SSH public key of Tenable Security Center and append it to the `/opt/lce/.ssh/authorized_keys` file. The `/opt/lce/daemons/lce-install-key.sh` script performs this function.

**Note:** The Log Correlation Engine server must have a valid license key installed and the Log Correlation Engine daemon must be running before you perform the steps below.

To perform manual Log Correlation Engine key exchange:

1. Log in to Tenable Security Center via the user interface.
2. Download the Tenable Security Center key, as described in [Download the Tenable Security Center SSH Key](#).
3. Save the file locally as **SSHKey.pub**.

**Caution:** Do not edit the file or save it to any specific file type.

4. From the workstation where you downloaded the key file, use a secure copy program (e.g., WinSCP) to copy the **SSHKey.pub** file to the Log Correlation Engine system.

**Note:** You must have the credentials of an authorized user on the Log Correlation Engine server to perform this step.

For example, if you have a user **username** configured on the Log Correlation Engine server (hostname **lceserver**) whose home directory is `/home/username`, the command on a Unix system is as follows:

```
# scp SSHKey.pub username@lceserver:/home/username
```



5. After you copy the file to the Log Correlation Engine server, in the CLI, run the following command to move the file to `/opt/lce/daemons`:

```
# mv /home/username/SSHKey.pub /opt/lce/daemons
```

6. On the Log Correlation Engine server, as the root user, run the following command to change the ownership of the SSH key file to `lce`:

```
# chown lce /opt/lce/daemons/SSHKey.pub
```

7. Run the following command to append the SSH public key to the `/opt/lce/.ssh/authorized_keys` file:

```
# su lce  
# /opt/lce/daemons/lce-install-key.sh /opt/lce/daemons/SSHKey.pub
```

8. To test the communication, as the user `tns` on the Tenable Security Center system, attempt to run the `id` command:

```
# su tns  
# ssh -C -o PreferredAuthentications=publickey lce@<LCE-IP> id
```

If you have not previously established a connection, a warning appears that is similar to the following:

```
The authenticity of host '198.51.100.28 (198.51.100.28)' can't be established.  
RSA key fingerprint is 86:63:b6:c3:b4:3b:ba:96:5c:b6:d4:42:b5:45:37:7f.  
Are you sure you want to continue connecting (yes/no)?
```

9. Answer `yes` to this prompt.

If the key exchange worked correctly, a message similar to the following appears:

```
# uid=251(lce) gid=251(lce) groups=251(lce)
```



10. You can add the IP address of Tenable Security Center to the Log Correlation Engine system's `/etc/hosts` file. This prevents the SSH daemon from performing a DNS lookup that can add seconds to your query times.
11. You can add the Log Correlation Engine to Tenable Security Center via the normal administrator process, described in [Log Correlation Engines](#).



---

## Manual Tenable Nessus SSL Certificate Exchange

---

If you want to use self-signed certificates for the Tenable Security Center-Tenable Nessus connection, you can perform manual Tenable Nessus SSL certificate exchange.

**Caution:** Please note that users should be familiar with PKI deployments and it is not recommended that the Nessus server be used as the site's PKI system. The method described here is intended to assist in testing the functionality of the certificate exchange to assist users in the incorporation of the certificates into their current PKI system. In this method, the same key is shared between multiple servers. This may not be acceptable in some installations.

- [Overview of Tenable Nessus SSL Certificates and Keys](#)
- [Tenable Nessus Certificate Configuration for Unix](#)
- [Tenable Nessus Certificate Configuration for Windows](#)



---

## Overview of Tenable Nessus SSL Certificates and Keys

---

Nessus supports authentication protocols based on the OpenSSL toolkit (for more information about the toolkit, see <http://www.openssl.org/>). This provides cryptographic protection and secure authentication.

In the example described in this document, there are three key system components: the certificate authority, the Nessus server and the Nessus client (Tenable Security Center). It is necessary to generate the keys required for the SSL communication and copy them to the appropriate directories.

### Certificate Authority

The certificate authority (CA) ensures that the certificate holder is authentic and not an impersonator. The CA holds a copy of the certificates for registered users to certify that the certificate is genuine. When the CA receives a certificate signing request (CSR), it validates and signs the certificate.

In the example provided in this document, the CA resides on the Nessus server (which is not the recommended method for a production environment). In a proper PKI deployment, the CA would be a separate system or entity, such as Thawte or Verisign.

### Nessus Server

In the example described in this document, the Nessus server is the same physical system that holds the CA, but this will not likely be the case in a production environment. The Nessus server is the target of the secure communication and its keys must be generated locally and copied to the systems that will need to communicate with it using the SSL protocol. The Nessus server has users defined that authenticate to it either by simple login and password or via SSL. These users will also have keys associated with them.

### Nessus Client (Tenable Security Center)

The Nessus client, Tenable Security Center, communicates with the Nessus server via SSL. It uses keys generated for a Nessus client and stores these keys and the certificate for the CA in the `/opt/sc/daemons` directory. These keys must be owned by the “tns” userid.



## Tenable Nessus Certificate Configuration for Unix

The following topic describes the commands and relevant files involved in the Nessus SSL process on a Red Hat Linux system. This process creates the following files:

File Name Created	Purpose	Where to Copy to
<code>/opt/nessus/com/nessus/CA/cacert.pem</code>	This is the certificate for the Certificate Authority. If using an existing PKI, this will be provided to you by the PKI and must be copied to this location.	<code>/opt/nessus/com/nessus/CA</code> on the initial Nessus server and any additional Nessus servers that need to authenticate using SSL.
<code>/opt/nessus/com/nessus/CA/servercert.pem</code>	This is the public certificate for the Nessus server that is sent in response to a CSR.	<code>/opt/nessus/com/nessus/CA</code> on any additional Nessus servers that need to authenticate using SSL.
<code>/opt/nessus/var/nessus/CA/cakey.pem</code>	This is the private key of the Certificate Authority. It	<code>/opt/nessus/var/nessus/CA</code> on any additional Nessus servers that need to authenticate using SSL.



File Name Created	Purpose	Where to Copy to
	may or may not be provided by the Certificate Authority, depending on if they allow the creation of sub users.	
<code>/opt/nessus/var/nessus/CA/serverkey.pem</code>	This is the private key of the Nessus server.	<code>/opt/nessus/var/nessus/CA</code> on any additional Nessus servers that need to authenticate using SSL.

## Create Nessus Client Keys

The Nessus user, in this case the user ID that Tenable Security Center uses to communicate with the Nessus server, is created by the following command:

```
# /opt/nessus/sbin/nessuscli mkcert-client
```

This command creates the keys for the Nessus clients and optionally registers them appropriately with the Nessus server by associating a distinguished name (dname) with the user ID. It is important to respond **y** (yes) when prompted to register the user with the Nessus server for this to take effect. The user name may vary and is referred to here as **user**.

The certificate filename is a concatenation of **cert\_**, the user name you entered and **.pem**. Additionally, the key filename is a concatenation of **key\_**, the user name you entered and **.pem**.

If the user was previously added via the `/opt/nessus/sbin/nessuscli adduser` command, you will still need to run this program to register the user. If you have not previously created the user, it



is not necessary to also run the `nessuscli adduser` command; the user is created if it does not already exist. The following files are created by this command:

File Name Created	Purpose
<code>/tmp/nessus-xxxxxxx/cert_{user-}.pem</code>	This is the public certificate for the specified user.
<code>/tmp/nessus-xxxxxxx/key_{user-}.pem</code>	This is the private key for the specified user.
<code>/opt/nessus/var/nessus/users/{user}/auth/dname</code>	This is the distinguished name to be associated with this user. The distinguished name consists of a number of options separated by commas in the following format:  <b><code>/C={country}/ST={state}/L={location}/OU={organizational unit}/O={organization}/CN={common name}</code></b>

## Create and Deploy SSL Authentication for Nessus

An example SSL Certificate configuration for Nessus to Tenable Security Center authentication is included below:

In the example described here, Tenable Security Center and the Nessus scanner are defined as follows. Your configuration varies:

Tenable Security Center:

IP: 192.0.2.50

OS: Red Hat ES 5

Nessus Scanner:

IP: 192.0.2.202

OS: Red Hat ES 5

## Create Keys and User on Nessus Server

Log in to the Nessus scanner and use the `su` command to become the root user. Create the Certificate Authority and Nessus server certificate as follows:





```
# /opt/nessus/sbin/nessuscli mkcert
```

```
-----  
                          Creation of the Nessus SSL Certificate  
-----
```

This script will now ask you the relevant information to create the SSL certificate of Nessus. Note that this information will *\*NOT\** be sent to anybody (everything stays local), but anyone with the ability to connect to your Nessus daemon will be able to retrieve this information.

```
CA certificate life time in days [1460]:  
Server certificate life time in days [365]:  
Your country (two letter code) [US]:  
Your state or province name [NY]:  
Your location (e.g. town) [New York]:  
Your organization [Nessus Users United]: Tenable Network Security  
This host name [Nessus4_2]:
```

Congratulations. Your server certificate was properly created.

The following files were created :

. Certification authority :

```
Certificate = /opt/nessus//com/nessus/CA/cacert.pem  
Private key = /opt/nessus//var/nessus/CA/cakey.pem
```

. Nessus Server :

```
Certificate = /opt/nessus//com/nessus/CA/servercert.pem  
Private key = /opt/nessus//var/nessus/CA/serverkey.pem
```

Next, create the user ID for the Nessus client, which is Tenable Security Center in this case, to log in to the Nessus server with, key and certificate. This is done with the command `/opt/nessus/sbin/nessuscli mkcert-client`. If the user does not exist in the Nessus user database, it is created. If it does exist, it is registered to the Nessus server and have a distinguished name (dname) associated with it. It is important to respond **y** (yes) when prompted to register the user with the Nessus server for this to take effect. The user must be a Nessus admin, so answer **y** when asked. The following example shows the prompts and typical answers:



```
# /opt/nessus/sbin/nessuscli mkcert-client
Do you want to register the users in the Nessus server
as soon as you create their certificates ? [n]: y
```

```
-----
                        Creation Nessus SSL client Certificate
-----
```

This script will now ask you the relevant information to create the SSL client certificates for Nessus.

```
Client certificate life time in days [365]:
Your country (two letter code) [FR]: US
Your state or province name []: MD
Your location (e.g. town) [Paris]: Columbia
Your organization []: Tenable Network Security
Your organizational unit []:
```

```
*****
```

We are going to ask you some question for each client certificate  
If some question have a default answer, you can force an empty answer by entering a single dot '.'

```
*****
```

```
User #1 name (e.g. Nessus username) []: paul
User paul already exists
Do you want to go on and overwrite the credentials? [y]: y
Should this user be administrator? [n]: y
Country (two letter code) [US]:
State or province name [MD]:
Location (e.g. town) [Columbia]:
Organization [Tenable Network Security]:
Organizational unit []:
e-mail []:
```

User rules

```
-----
```

nessusd has a rules system which allows you to restrict the hosts that \$login has the right to test. For instance, you may want him to be able to scan his own host only.  
Please see the `nessus-adduser(8)` man page for the rules syntax

Type the rules for this user, and enter a BLANK LINE once you are done:



```
(the user can have an empty rules set)
```

```
User added to Nessus.  
Another client certificate? [n]: n  
Your client certificates are in /tmp/nessus-043c22b5  
You will have to copy them by hand  
#
```

The certificates created contain the username entered previously, in this case paul, and are located in the directory as listed in the example above (e.g., /tmp/nessus-043c22b5).

## Create the nessuscert.pem Key

In the above specified tmp directory, the certificate and key files in this example are named cert\_paul.pem and key\_paul.pem. These files must be concatenated to create nessuscert.pem as follows:

```
# cd /tmp/nessus-043c22b5  
# cat cert_paul.pem key_paul.pem > nessuscert.pem
```

**Note:** The nessuscert.pem file is used when configuring the Nessus scanner on Tenable Security Center. This file needs to be copied to somewhere accessible for selection from your web browser during the Nessus configuration.

## Configure Nessus Daemons

To enable certificate authentication on the Nessus server, the **force\_pubkey\_auth** setting must be enabled. Once enabled, log in to the Nessus server may only be completed by SSL certificates. Username and password login are disabled. As the root (or equivalent) user on the Nessus server, run the following command:

```
# /opt/nessus/sbin/nessuscli fix --set force_pubkey_auth=yes
```

Restart the Nessus daemons with the appropriate command for your system. The example here is for Red Hat:



```
# /sbin/service nessusd restart
```

## Change the Nessus Mode of Authentication

In Tenable Security Center, update your Tenable Nessus scanner configuration to use SSL certificate-based authentication. For more information, see [Add a Tenable Nessus Scanner](#).

### Edit Nessus Scanner ✕ Cancel

#### General

Name\*

Description

Host\*

Port\*

Enabled

Verify Hostname

Use Proxy

#### Authentication

Type

Certificate\*  ✕

## Considerations for Custom Certificates

During an upgrade, Tenable Security Center will check for the presence of custom SSL certificates. If certificates are found and the owner is not Tenable, any newly generated certificates will be named with a **.new** extension and placed in the `/opt/sc/support/conf` directory to avoid overwriting existing files.

## Deploy to Other Nessus Scanners

After you configure authentication on one Tenable Nessus scanner, you can use the same SSL certificates and user names to authenticate other Tenable Nessus scanners.



## Before you begin:

- Set up and configure all of your Tenable Nessus scanners.
- Add your Tenable Nessus scanners to Tenable Security Center, as described in [Add a Tenable Nessus Scanner](#).

## To duplicate the same authentication configuration on other Tenable Nessus scanners:

1. In the command line interface (CLI) on another Tenable Nessus server, run the following command to copy the certificate files onto your other Tenable Nessus server:

```
# cd /opt/nessus/var/nessus/CA
# scp cakey.pem serverkey.pem root@nessusIP:/opt/nessus/var/nessus/CA
# cd /opt/nessus/com/nessus/CA
# scp cacert.pem servercert.pem root@nessusIP:/opt/nessus/com/nessus/CA
```

2. Run the following command to create a user directory on your second Tenable Nessus server, using the same name as [the user you created on the first Tenable Nessus server](#). Replace *admin* with the user's name:

```
/opt/nessus/sbin/nessuscli adduser admin
```

A confirmation prompt appears.

3. Press *y* to confirm you want the user to have system administrator privileges.

Tenable Nessus creates the user.

4. Run the following command to copy the [the user you created on the first Tenable Nessus server](#) to the directory you created in step 2. Replace *admin* with the user's name:

```
# cd /opt/nessus/var/nessus/users
# tar -zcvf - admin | ssh -C root@nessusIP "tar -zxvf - -C
/opt/nessus/var/nessus/users"
```

5. Run the following command to force Tenable Nessus to authenticate via certificate:

```
/opt/nessus/sbin/nessuscli fix --set force_pubkey_auth=yes
```



- Restart the Nessus service on all the Nessus servers with the appropriate command for your system. This example is for Red Hat:

```
# /sbin/service nessusd restart
```

- In Tenable Security Center, update all of your Tenable Nessus scanner configurations to use SSL certificate-based authentication. For more information, see [Add a Tenable Nessus Scanner](#).



# Tenable Nessus Certificate Configuration for Windows

## Commands and Relevant Files

The following section describes the commands and relevant files involved in the Nessus SSL process on a Windows system.

## Certificate Authority and Nessus Server Certificate

The command `C:\Program Files\Tenable\Nessus\nessuscli mkcert` creates the Certificate Authority and generates the server certificate. This command creates the following files:

File Name Created	Purpose	Where to Copy to
C:\Program Files\Tenable\Nessus\nessus\CA\cacert.pem	This is the certificate for the Certificate Authority. If using an existing PKI, this will be provided to you by the PKI and must be copied to this location.	C:\Program Files\Tenable\Nessus\nessus\CA\ on any additional Nessus servers that need to authenticate using SSL.
C:\Program Files\Tenable\Nessus\nessus\CA\servercert.pem	This is the public certificate for the Nessus server that is sent in	C:\Program Files\Tenable\Nessus\nessus\CA\ on any additional Nessus servers that need to authenticate using SSL.



File Name Created	Purpose	Where to Copy to
	response to a CSR.	
C:\Program Files\Tenable\Nessus\nessus\CA\cakey.pem	This is the private key of the Certificate Authority. It may or may not be provided by the Certificate Authority, depending on if they allow the creation of sub users.	C:\Program Files\Tenable\Nessus\nessus\CA\ on any additional Nessus servers that need to authenticate using SSL.
C:\Program Files\Tenable\Nessus\nessus\CA\serverkey.pem	This is the private key of the Nessus server.	C:\Program Files\Tenable\Nessus\nessus\CA\ on any additional Nessus servers that need to authenticate using SSL.

## Nessus Client Keys

The Nessus user, which in this case is the user ID that Tenable Security Center uses to communicate with the Nessus server, is created by the command `C:\Program Files\Tenable\Nessus\nessuscli mkcert-client`.

This command creates the keys for the Nessus clients and optionally registers them appropriately with the Nessus server by associating a distinguished name (dname) with the user ID. It is important





to respond **y** (yes) when prompted to register the user with the Nessus server for this to take effect. The user name may vary and is referred to here as **user**.

The certificate filename is a concatenation of **cert\_**, the user name you entered and **.pem**. Additionally, the key filename is a concatenation of **key\_**, the user name you entered and **.pem**.

The following files are created by this command:

File Name Created	Purpose
C:\Documents and Settings\ <useraccount>\Local Settings\Temp\nessus-xxxxxxx\cert_&lt;user&gt;.pem</useraccount>	This is the public certificate for the specified user.
C:\Documents and Settings\ <useraccount>\Local Settings\Temp\nessus-xxxxxxx\key_&lt;user&gt;.pem</useraccount>	This is the private key for the specified user.
C:\Program Files\Tenable\Nessus\nessus\users\<user_name>\auth\dname	This is the distinguished name to be associated with this user. The distinguished name consists of a number of options separated by commas in the following format:  <b>"C={country}/ST={state}/L={location}/OU={organizational unit}/O={organization}/CN={common name}"</b>

## Creating and Deploying SSL Authentication for Nessus

### Create Keys and User on Nessus Server

To create the keys and user:

1. Create the Certificate Authority and Nessus server certificate using the command `C:\Program Files\Tenable\Nessus\nessuscli mkcert`
2. Provide the requested information.



**Caution:** Critical: Any Nessus Scanner that has previously processed scans will not initially accept these keys as a `policy.db` will have already been created on the Nessus Scanner. Remove the `policies.db` from the Nessus Scanner to ensure the deployment finishes successfully.

3. To remove the `policies.db` on a Linux system issue this command as root:

```
rm /opt/nessus/var/nessus/users/<UserName>/policies.db
```

4. To remove the `policies.db` on a Windows system, navigate to the `C:\Program Files\Tenable\Nessus` folder and remove the `policies.db` file. The actual location of the `policies.db` differs depending on the version of Windows that is running.
5. Create the user ID for the Nessus client, which is Tenable Security Center in this case, to log in to the Nessus server with, key and certificate using the following command:

```
C:\Program Files\Tenable\Nessus\nessuscli mkcert-client
```

If the user does not exist in the Nessus user database, it is created. If it does exist, it is registered to the Nessus server and have a distinguished name (`dname`) associated with it. It is important to respond **y** (yes) when prompted to register the user with the Nessus server for this to take effect. The user must be a Nessus admin, so answer **y** when asked.

The certificates created contain the username entered previously, in this case **admin**, and are located in the directory as listed in the example above (e.g., `C:\Documents and Settings\<UserAccount>\Local Settings\Temp\nessus-00007fb1`). In the specified directory, the certificate and key files in this example are named `cert_admin.pem` and `key_admin.pem`.

## Transfer Certificates and Keys to Tenable Security Center

Transfer the `cert_admin.pem` and `key_admin.pem` files to a desired location on Tenable Security Center, change into that directory and concatenate them as follows:

```
# cat cert_admin.pem key_admin.pem > nessuscert.pem
```

**Note:** The `nessuscert.pem` file will be used when configuring the Nessus scanner on Tenable Security Center. This file needs to be copied to somewhere accessible for selection from your web browser during the Nessus configuration.

## Configure Nessus Daemons



To enable certificate authentication on the Nessus server, the `force_pubkey_auth` setting must be enabled. Once enabled, log in to the Nessus server may only be completed by SSL certificates. Username and password login are disabled. As the root (or equivalent) user on the Nessus server, run the following command:

```
C:\Program Files\Tenable\Nessus\nessuscli fix --set force_pubkey_auth=yes
```

Open the Nessus Server Manager GUI, click **Stop Nessus Server** and then click **Start Nessus Server**.

## Change the Nessus Mode of Authentication

In Tenable Security Center, update your Tenable Nessus scanner configuration to use SSL certificate-based authentication. For more information, see [Add a Tenable Nessus Scanner](#).

### Edit Nessus Scanner ✕ Cancel

#### General

Name\*

Description

Host\*

Port\*

Enabled

Verify Hostname

Use Proxy

#### Authentication

Type

Certificate\*  ✕



---

## Offline Tenable Security Center Plugin and Feed Updates

---

You can perform offline plugin updates and feed updates in air-gapped Tenable Security Center environments.

- [Perform an Offline Nessus Plugin Update](#)
- [Perform an Offline Tenable Nessus Network Monitor Plugin Update](#)
- [Perform an Offline Tenable Security Center Feed Update](#)

**Note:** Tenable Security Center does not manage plugins for Log Correlation Engine. However, Log Correlation Engine plugins are required for event analysis.

For general information about best practices in air-gapped environments, see [Considerations for Air-Gapped Environments](#).



# Perform an Offline Nessus Plugin Update

**Required User Role:** Administrator

Before you begin:

- If you installed Tenable Security Center in an environment other than Tenable Core, install a temporary Tenable Nessus scanner on the same host as Tenable Security Center. You will use this temporary Tenable Nessus scanner to generate a challenge code for offline Tenable Security Center registration. Do not start or otherwise configure the temporary Tenable Nessus scanner.

To perform an offline Tenable Nessus plugin update:

1. In the command line interface (CLI), run the following command to prevent the Tenable Nessus scanner from starting automatically upon restarting the system:

```
/usr/bin/systemctl disable nessusd
```

2. Run the following command and save the challenge string that is displayed:

```
# /opt/nessus/sbin/nessuscli fetch --challenge
```

3. In your browser, navigate to <https://plugins.nessus.org/offline.php>.

**Note:** Do not click **here**, even if you have a newer version of Tenable Nessus installed. You cannot use the <https://plugins.nessus.org/v2/offline.php> page for Tenable Security Center downloads.

4. Paste the challenge string from Step 3 and your Activation Code in the appropriate boxes on the web page.
5. Click **Submit**.
6. On the next page, copy the link that starts with **https://plugins.nessus.org/get.php...** and save it as a favorite. Within the saved link change **all-2.0.tar.gz** to **sc-plugins-diff.tar.gz**. This link will be needed for future use.

**Caution:** Do not click the link for `nessus-fetch.rc`.



7. Go to the favorite you created.  
The page prompts you to download a file.
8. Download the file, which is called `sc-plugins-diff.tar.gz`.
9. Verify the file using the MD5 checksum, as described in the [knowledge base](#) article.
10. Save the `sc-plugins-diff.tar.gz` on the system used to access your Tenable Security Center web interface.
11. Log in to Tenable Security Center via the user interface.
12. Click **System > Configuration**.  
The **Configuration** page appears.
13. Click **Plugins/Feed**.  
The **Plugins/Feed Configuration** page appears.
14. In the **Schedules** section, expand the **Active Plugins** options.
15. Click **Choose File** and browse to the saved `sc-plugins-diff.tar.gz` file.
16. Click **Submit**.

After several minutes, the plugin update finishes and the page updates the **Last Updated** date and time.

#### What to do next:

- If you installed a temporary Tenable Nessus scanner on the same host as Tenable Security Center, uninstall the Tenable Nessus scanner.



# Perform an Offline Tenable Nessus Network Monitor Plugin Update

**Required User Role:** Administrator

Before you begin:

- If you installed Tenable Security Center in an environment other than Tenable Core, install a temporary Tenable Nessus scanner on the same host as Tenable Security Center. You will use this temporary Tenable Nessus scanner to generate a challenge code for offline Tenable Security Center registration. Do not start or otherwise configure the temporary Tenable Nessus scanner.

To perform an offline Tenable Nessus Network Monitor plugin update:

1. In the command line interface (CLI), run the following command to prevent the Tenable Nessus Network Monitor scanner from starting automatically upon restarting the system:

```
/usr/bin/systemctl disable nnm
```

2. Run the following command and save the challenge string that is displayed:

```
# /opt/nnm/bin/nnm --challenge
```

3. In your browser, navigate to the [Tenable Nessus Network Monitor plugins page](#).
4. Paste the challenge string from Step 3 and your Activation Code in the appropriate boxes on the web page.
5. Click **Submit**.
6. On the next page, copy the link that starts with **https://plugins.nessus.org/v2/...** and bookmark it in your browser. The other information on the page is not relevant for use with Tenable Security Center.
7. Click the bookmarked link.

The page prompts you to download a file.

8. Download the file, which is called `sc-passive.tar.gz`.



9. Verify the file using the MD5 checksum, as described in the [knowledge base](#) article.
10. Save the `sc-passive.tar.gz` on the system used to access your Tenable Security Center GUI.

**Note:** Access the Tenable Nessus Network Monitor feed setting and change the activation from off-line to Tenable Security Center.

11. Log in to Tenable Security Center via the user interface.
12. Click **System > Configuration**.

The **Configuration** page appears.

13. Click **Plugins/Feed**.

The **Plugins/Feed Configuration** page appears.

14. In the **Schedules** section, expand the **Passive Plugins** options.
15. Click **Choose File** and browse to the saved `sc-passive.tar.gz` file.
16. Click **Submit**.

After several minutes, the plugin update finishes and the page updates the **Last Updated** date and time.

What to do next:

- If you installed a temporary Tenable Nessus scanner on the same host as Tenable Security Center, uninstall the Tenable Nessus scanner.





# Perform an Offline Tenable Security Center Feed Update

**Required User Role:** Administrator

**Note:** If you already performed a Tenable Nessus offline plugin update, start at step 7.

Before you begin:

- If you installed Tenable Security Center in an environment other than Tenable Core, install a temporary Tenable Nessus scanner on the same host as Tenable Security Center. You will use this temporary Tenable Nessus scanner to generate a challenge code for offline Tenable Security Center registration. Do not start or otherwise configure the temporary Tenable Nessus scanner.

To perform an offline Tenable Security Center feed update:

1. In the command line interface (CLI), run the following command to prevent the Tenable Nessus scanner from starting automatically upon restarting the system:

```
/usr/bin/systemctl disable nessusd
```

2. To obtain the challenge code for an offline Tenable Security Center registration, do one of the following:
  - If you deployed Tenable Security Center + Tenable Core, navigate to the **Tenable Security Center** tab in Tenable Core and save the challenge code.
  - If you installed Tenable Security Center in an environment other than Tenable Core, run the following command and save the challenge code:

```
# /opt/nessus/sbin/nessuscli fetch --challenge
```

3. In your browser, navigate to <https://plugins-customers.nessus.org/offline.php>.
4. Paste the challenge code from Step 2 and your Activation Code in the appropriate boxes on the web page.
5. Click **Submit**.



6. On the next page, copy the link that starts with **https://plugins.nessus.org/get.php...** and save it as a favorite.
7. Within the saved link change **all-2.0.tar.gz** to **SecurityCenterFeed48.tar.gz**. This link is needed for future use.

**Caution:** Do not click the link for `nessus-fetch.rc` as it is not needed.

8. Go to the favorite link you created.

The page prompts you to download a file.

9. Download the file, which will be called `SecurityCenterFeed48.tar.gz`.
10. Verify the file using the MD5 checksum, as described in the [knowledge base](#) article.
11. Save the `SecurityCenterFeed48.tar.gz` on the system used to access your Tenable Security Center GUI.
12. Log in to Tenable Security Center via the user interface.

13. Click **System > Configuration**.

The **Configuration** page appears.

14. Click **Plugins/Feed**.

The **Plugins/Feed Configuration** page appears.

15. In the **Schedules** section, expand the **Tenable.sc Feed** options.
16. Click **Choose File** and browse to the saved `SecurityCenterFeed48.tar.gz` file.
17. Click **Submit**.

After several minutes, the plugin update finishes and the page updates the **Last Updated** date and time.

#### What to do next:

- If you installed a temporary Tenable Nessus scanner on the same host as Tenable Security Center, uninstall the Tenable Nessus scanner.



---

# Troubleshooting

---

This troubleshooting section covers some of the common issues encountered with Tenable Security Center.

- [General Tenable Security Center Troubleshooting](#)
- [Tenable Log Correlation Engine Troubleshooting](#)
- [Tenable Nessus Troubleshooting](#)
- [Tenable Nessus Network Monitor Troubleshooting](#)
- [Troubleshooting Issues with the custom\\_CA.inc File](#)



# General Tenable Security Center Troubleshooting

## Tenable Security Center does not appear to be operational

1. If a login page does not appear, close and reopen the web browser.
2. Ensure that the remote httpd service is running on the Tenable Security Center host:

```
# ps ax | grep httpd
1990 ?          Ss      0:01 /opt/sc/support/bin/httpd -k start
```

3. Ensure that sufficient drive space exists on the Tenable Security Center host:

```
# df

Filesystem                1K-
blocks      Used          Available      Use%      Mounted on
/dev/mapper/VolGroup00-LogVol100
8506784    0              100%      /
/dev/sda1
101086      24455          71412      26%
/boot
tmpfs
1037732    0%             /dev/shm
```

4. If there is not enough drive space, recover sufficient space and restart the Tenable Security Center service:

```
# df

Filesystem                1K-blocks
Used      Available      Use%      Mounted on
/dev/mapper/VolGroup00-LogVol100
85%      /
6816420  1251276
/dev/sda1
101086    24455          71412      26%      /boot
tmpfs
1037732    0              1037732    0%
/dev/shm
```



```
# service SecurityCenter restart
```

```
Shutting down SecurityCenter services:           [ OK ]
```

```
Starting SecurityCenter services:                [ OK ]
```

```
#
```

## Locked out of all Tenable Security Center user accounts

Contact Tenable Support.

## Invalid license error

If you receive an invalid license error while attempting to log in as a security manager or lower organizational user, an administrator user must log in and upload a new valid license key. A user with access to the host OS and valid permissions can also check that an up-to-date license exists in `/opt/sc/daemons`. Obtain a license from Tenable and copy it to the daemons directory as the `tns` user.

```
-rw-r--r--  1 tns tns    1942 Oct 29 12:14 license.key
```

## Reporting does not work

Check your Java version. The system only supports OpenJDK and Oracle JRE. The existence of another type of Java on the system will likely break reporting.



## Tenable Log Correlation Engine Troubleshooting

### Tenable Log Correlation Engine server does not appear to be operational

1. Confirm that the Tenable Log Correlation Engine server state is **Working** along with all attached Tenable Log Correlation Engine clients.
2. Check that you can SSH from the Tenable Security Center host to the Tenable Log Correlation Engine host.
3. Check that the Tenable Log Correlation Engine daemon is running on its host and listening on the configured port (TCP port 31300 by default):

```
# ss -pan | grep lced  
  
tcp          0      0 0.0.0.0:31300  0.0.0.0:*    LISTEN      30339/lced
```

4. Check that the listening ports can be reached from the network and are not blocked by a firewall.
5. If the Tenable Log Correlation Engine server is not operational, attempt to start the service:

```
# service lce start  
  
Starting Log Correlation EngineLCE Daemon Configuration  
LICENSE: Tenable Log Correlation Engine 3-Silo Key for [user]  
EXPIRE: 11-10-2011  
REMAIN: 30 days  
MESSAGE: LCE (3-silo license)  
MESSAGE: Valid authorization  
-----  
[ OK ]
```

### No events from an attached Tenable Log Correlation Engineserver



1. Confirm that the Tenable Log Correlation Engine server state is **Working** along with all attached Tenable Log Correlation Engine clients.
2. Confirm connectivity by checking that heartbeat events show up in the Tenable Security Center UI.
3. Check the Tenable Log Correlation Engine configuration settings in accordance with the Tenable Log Correlation Engine documentation.
4. Check the individual Tenable Log Correlation Engine client configuration and authorization. If syslog is being used to collect information and events, ensure that the syslog service is running and configured correctly on the target syslog server in accordance with Tenable Log Correlation Engine documentation.
5. Check for NTP time synchronization between the Tenable Security Center, Tenable Log Correlation Engine, and Tenable Log Correlation Engine clients.

## Invalid Tenable Log Correlation Engine license

1. Check that an up-to-date license exists on the Tenable Log Correlation Engine server.

## Tenable Log Correlation Engine plugins fail to update

1. Manually test a plugin update under **Plugins** with **Update Plugins**. If successful, the line **Passive Plugins Last Updated** will update to the current date and time.
2. Ensure that the Tenable Security Center host is allowed outbound HTTPS connectivity to the Tenable Log Correlation Engine Plugin Update Site.
3. For all other Tenable Log Correlation Engine plugin update issues, contact Tenable Support.



# Tenable Nessus Troubleshooting

## Tenable Nessus server does not appear to be operational

1. Verify that the Tenable Nessus scanner **Status** is **Unable to Connect**.
2. SSH to the remote Tenable Nessus host to make sure the underlying operating system is operational.
3. Confirm that the Tenable Nessus daemon is running (Linux example below):

```
# service nessusd status
nessusd (pid 3853) is running...
```

4. If the Tenable Nessus service is not running, start the service:

```
# service nessusd start
Starting Nessus services:
# ps -ef | grep nessusd
root      8201  8200  60 11:41 pts/2    00:00:05 nessusd -q
root      8206  7842   0 11:41 pts/2    00:00:00 grep  nessusd
#
```

## Cannot add a Tenable Nessus server

1. Make sure the Tenable Nessus daemon was registered using the Tenable Security Center option for registration.
2. Check connectivity from Tenable Security Center to the port the Tenable Nessus system is running on (e.g., 8834). For example, run:

```
curl -k https://<scannerIPAddress>:<port>
```

## Tenable Nessus scans fail to complete





1. Ensure that the Tenable Nessus service is running on the Tenable Nessus host.
2. Ensure that Tenable Nessus scanner is listed in Tenable Security Center under **Resources > Nessus Scanners** and that the status of the Tenable Nessus scanner is listed as **Working**. For more information, see [Tenable Nessus Scanner Statuses](#).
3. Click **Edit** to ensure that the IP address or hostname, port, username, password, and selected repositories for the Tenable Nessus scanner are all correct.
4. Edit any incorrect entries to their correct state.
5. Click **Submit** to attempt to reinitialize the Tenable Nessus scanning interface.
6. Right click the scan results and click **Scan Details** to obtain a more detailed description of the error.

If the scan details indicate a Blocking error, this is indicative of a license IP address count that has reached the limit. Either remove a repository to free up IP addresses or obtain a license for more IP addresses.

7. Ensure that scan targets are permitted within the configured scan zones.
8. Ensure the Tenable Nessus scanner is running a supported Tenable Nessus version. For minimum Tenable Nessus scanner version requirements, see the [Tenable Security Center Release Notes](#) for your version.

## Tenable Nessus plugins fail to update

1. Click **System > Configuration**.

The **Configuration** page appears.

2. Click **License** and ensure that the Tenable Nessus Activation Code is marked as **Valid**.
3. Ensure the Tenable Nessus scanner is running a supported Tenable Nessus version. For minimum Tenable Nessus scanner version requirements, see the [Tenable Security Center Release Notes](#) for your version.
4. Ensure that the user used to connect to the Tenable Nessus server is a Tenable Nessus administrator.



5. Ensure that the Tenable Security Center system is allowed outbound HTTPS connectivity to the Tenable Nessus Plugin Update Site.
6. Under **System, Configuration**, and **Update** in Tenable Security Center, ensure that Active Plugins is not set to **Never**.
7. Manually test a plugin update under **Plugins** with **Update Plugins**.  
If successful, the line **Active Plugins Last Updated** updates to the current date and time.
8. For all other Tenable Nessus plugin update issues, contact Tenable Support.



# Tenable Nessus Network Monitor Troubleshooting

## Tenable Nessus Network Monitor server does not appear to be operational

1. Verify that the Tenable Nessus Network Monitor server appears as **Unable to Connect** under **Status**.
2. SSH to the remote Tenable Nessus Network Monitor host to make sure the underlying operating system is operational.
3. Confirm that the Tenable Nessus Network Monitor is running (Linux example below):

```
# service pvs status

NNM is stopped
NNM Proxy (pid 3142) is running
#
```

4. If the Tenable Nessus Network Monitor service is not running, start the service:

```
# service nnm start
Starting NNM Proxy [ OK ]
Starting NNM [ OK ]
#
```

## Cannot add a Tenable Nessus Network Monitor server

1. Confirm that the Tenable Nessus Network Monitor proxy is listening on the same port as Tenable Security Center (port 8835 by default):

```
# ss -pan | grep 8835
tcp      0      0 0.0.0.0:8835  0.0.0.0:*    LISTEN   406/pvs
```

2. Check connectivity by telnetting from the Tenable Security Center console into the Tenable Nessus Network Monitor server on port 8835 (the Tenable Nessus Network Monitor listening port). If successful, the response includes: Escape character is '^]'



---

## No vulnerabilities are being received from the Tenable Nessus Network Monitor server

1. Ensure that the Tenable Nessus Network Monitor service is running on the Tenable Nessus Network Monitor host.
2. Ensure that the Tenable Nessus Network Monitor appears in Tenable Security Center under **Resources > Tenable Nessus Network Monitors** and that the status of the Tenable Nessus Network Monitor appears as **Working**.
3. Click **Edit** to ensure that the IP address or hostname, port, username, password, and selected repositories for the Tenable Nessus Network Monitor are correct.
4. Edit any incorrect entries to their correct state.
5. Click **Submit** to attempt to reinitialize the Tenable Nessus Network Monitor scanning interface.

## Tenable Nessus Network Monitor plugins fail to update

1. Manually test a plugin update under **Plugins** with **Update Plugins**.  
If successful, **Passive Plugins Last Updated** updates to the current date and time.
2. Ensure that the Tenable Security Center host allows outbound HTTPS connectivity to the Tenable Nessus Network Monitor Plugin Update Site.
3. For all other Tenable Nessus Network Monitor plugin update issues, contact Tenable Support.

---

## Error Messages

---

For Tenable Security Center API status codes, see the [Tenable Security Center API Guide](#).

**Note:** Some errors are dependent on internal processes. If the error code you received is not listed, it may not indicate a specific Tenable Security Center error.

## Scanning

For more information about creating, modifying, and launching scans, see [Configure Scans](#).

For more information about statuses, see [Tenable Nessus Scanner Statuses](#), [Scan Result Statuses](#), and [View Your Scan Zones](#).

Code	Message	Recommended Action
14	Progress handler has died.	Your system processes may be overloaded during the scan. Confirm your available system resources and re-run the scan.
14	Error creating Email notifying User '<username>' of Scan launch.	Do any of the following: <ul style="list-style-type: none"><li>• Confirm the alert specifies one or more valid email addresses. For more information, see <a href="#">Email</a>.</li><li>• Confirm the job queue database is not locked.</li></ul>
14	Error creating Email notifying User '<username>' of Scan completion.	Do any of the following: <ul style="list-style-type: none"><li>• Confirm the alert specifies one or more valid email addresses. For more information, see <a href="#">Email</a>.</li><li>• Confirm the job queue database is not locked.</li></ul>
60	Available Zones do not cover any accessible Scan IPs for Scan job # <jobIDorPID> ('<scanDefin-	For troubleshooting assistance, see the <a href="#">knowledge base</a> article.



Code	Message	Recommended Action
	<i>itionName&gt;' - # &lt;scanDefinitionID&gt;).</i>	
62	No scanners ready to scan	The scan may be using incorrect or insufficient credentials, or another issue is blocking the scan. For troubleshooting assistance, see the <a href="#">knowledge base</a> article.
64	Scan # <scanDefinitionID> is disabled.	You may have insufficient permissions to run the scan. For troubleshooting assistance, see the <a href="#">knowledge base</a> article.
64	Scan Policy # <scanPolicyID> in Scan # <scanDefinitionID> is disabled.	You may have insufficient permissions to run the scan. For troubleshooting assistance, see the <a href="#">knowledge base</a> article.
70	Unable to launch Scan progress process	Tenable Security Center is unable to fork the running scan process. You may need to raise the stack size for the tns user. Contact your system administrator for assistance.
102	Could not open '<nessusFile>' for writing.	Tenable Security Center may have insufficient disk space. Free up disk space in Tenable Security Center, as described in the <a href="#">knowledge base</a> article.
106	Error getting contents of AuditFile '<auditFileName>' for Scan job # <scanJobID>.	Tenable Security Center cannot access the audit file definition. Do any of the following: <ul style="list-style-type: none"><li>• Verify the specified audit file is valid.</li><li>• Create a new audit file to use with the scan.</li></ul> For more information, see <a href="#">Audit Files</a> .
106	Error creating temp SCAP directory '<scapDir>'.	Tenable Security Center may have insufficient disk space. Free up disk space in Tenable Security Center, as described in the <a href="#">knowledge base</a> article.



Code	Message	Recommended Action
106	Error creating temp OVAL directory '<ovalDir>'.	Tenable Security Center may have insufficient disk space. Free up disk space in Tenable Security Center, as described in the <a href="#">knowledge base</a> article.
106	Error creating temp directory '<tempDir>'.	Tenable Security Center may have insufficient disk space. Free up disk space in Tenable Security Center, as described in the <a href="#">knowledge base</a> article.
106	Error untaring SCAP results file '<file>' (rc = \$rc).	Tenable Security Center may have insufficient disk space. Free up disk space in Tenable Security Center, as described in the <a href="#">knowledge base</a> article.
106	Error moving <type> result file '<curFile>' to '<newFile>'.	Tenable Security Center may have insufficient disk space. Free up disk space in Tenable Security Center, as described in the <a href="#">knowledge base</a> article.
106	Unable to get current working directory.	Tenable Security Center may have insufficient disk space. Free up disk space in Tenable Security Center, as described in the <a href="#">knowledge base</a> article.
106	Failed to change to the SCAP directory for zipping.	Tenable Security Center may have insufficient disk space. Free up disk space in Tenable Security Center, as described in the <a href="#">knowledge base</a> article.
106	Error building SCAP results file '<scapFile>' (rc = <zipReturnCode>).	Tenable Security Center may have insufficient disk space. Free up disk space in Tenable Security Center, as described in the <a href="#">knowledge base</a> article.
106	Failed to change back to originating directory.	Tenable Security Center may have insufficient disk space. Free up disk space in Tenable Security Center, as described in the <a href="#">knowledge base</a> article.
106	Unable to get current working directory.	Tenable Security Center may have insufficient disk space. Free up disk space in Tenable Security Center, as described in the <a href="#">knowledge base</a> article.
106	Failed to change to the	Tenable Security Center may have insufficient disk



Code	Message	Recommended Action
	OVAL directory for zipping.	space. Free up disk space in Tenable Security Center, as described in the <a href="#">knowledge base</a> article.
106	Error building OVAL results file '\$ovalFile' (rc = \$rc).	Tenable Security Center may have insufficient disk space. Free up disk space in Tenable Security Center, as described in the <a href="#">knowledge base</a> article.
106	Failed to change back to originating directory.	Tenable Security Center may have insufficient disk space. Free up disk space in Tenable Security Center, as described in the <a href="#">knowledge base</a> article.
106	No results file found for Scan job # <jobIDorPID> ('<scanDefinitionName>' - # <scanDefinitionID>).	Tenable Security Center cannot locate /opt/sc/data/scans/#jobID/results.xml. Verify the following: <ul style="list-style-type: none"><li>• /opt/sc/data/scans/#jobID/results.xml is in the correct directory.</li><li>• The tns user can access the file and directory.</li></ul>
106	Error creating new VDB directory for Scan job # <jobIDorPID> ('<scanDefinitionName>' - # <scanDefinitionID>).	Verify the tns user can access the following directory: /opt/sc/orgs/#orgID/VDB/#dateOfScan/.
106	Error moving results for Scan job # <jobIDorPID> ('<scanDefinitionName>' - # <scanDefinitionID>).	Verify the tns user can access the following directory: /opt/sc/orgs/#orgID/VDB/#dateOfScan/.
145	Error reading AuditFile " for Scan job # <scanJobID>. Unable to retrieve AuditFile # <auditFileID>"	Add an audit file to the scan policy, then re-run the scan. For more information, see <a href="#">Audit Files</a> and <a href="#">Scan Policies</a> .





Code	Message	Recommended Action
146	Unable to find template maps for Policy template # <i>&lt;policyTemplateID&gt;</i> .	Check for any errors with the last plugin update. If needed perform another plugin update. For more information, see <a href="#">Offline Tenable Security Center Plugin and Feed Updates</a> .
146	Diagnostic target is outside IPs of original Scan.	The scan target is not included in the scan configuration. If you want to include the target in the scan, update the scan settings and then re-run the scan.
146	Diagnostic target is not a single host.	The target of the diagnostic scan must be a single IP or FQDN. Update the scan configuration, then re-run the scan.
146	Zone Selection is locked but no Zone is specified.	You may have insufficient permissions to run the scan, or you may need to adjust your scan configuration.  For troubleshooting assistance, see the <a href="#">knowledge base</a> article.
146	Zone Selection is selectable but no Zone is specified.	You may have insufficient permissions to run the scan, or you may need to adjust your scan configuration.  For troubleshooting assistance, see the <a href="#">knowledge base</a> article.
146	Entered IPs and Assets are empty.	One or more scan targets do not exist in the selected import repository. For troubleshooting assistance, see the <a href="#">knowledge base</a> article.
146	Scan IPs are restricted.	You may have insufficient permissions to run the scan, or you may need to adjust your scan configuration.  For troubleshooting assistance, see the <a href="#">knowledge base</a> article.



Code	Message	Recommended Action
		<a href="#">base</a> article.
146	Scan IPs are not within your accessible range.	You may have insufficient permissions to run the scan, or you may need to adjust your scan configuration.  For troubleshooting assistance, see the <a href="#">knowledge base</a> article.
146	The number of Scan IPs is too large (more than 2 <sup>24</sup> unique IPs).	Reduce the number of scan targets and re-run the scan.
147	Job # <scanJobID> not found.	Confirm the job queue database is not locked, then re-run the scan.
201	Error Setting up Scan database. <details>	Do any of the following, then re-run the scan: <ul style="list-style-type: none"><li>• Confirm you have adequate disk space</li><li>• Confirm the tns user can access /opt/sc/data/scans/#jobID/</li></ul>
201	Error creating Scan database tables. <details>	Do any of the following, then re-run the scan: <ul style="list-style-type: none"><li>• Confirm you have adequate disk space</li><li>• Confirm the tns user can access /opt/sc/data/scans/#jobID/</li><li>• Confirm there are no corrupted databases</li></ul>
202	<i>Error message varies.</i>	Your system processes may be overloaded during the scan. Confirm your available system resources and re-run the scan. If the error persists, contact your Tenable representative.
400	Scan job # <scanJobID> stopped due to scanner inactivity.	Your system processes may be overloaded during the scan. Confirm your available system resources and re-run the scan.



Code	Message	Recommended Action
65536	Failed to resolve <numFailed> scan target hostnames in Scan #job # <jobIDorPID> ('<scanDefinitionName>' - #<scanDefinitionID>)."	Tenable Security Center cannot resolve the specified scan target hostnames. For troubleshooting assistance, see the <a href="#">knowledge base</a> article.
65536	Unable to scan <numRestrictedTargets> Restricted target<plural> in Scan job # <jobIDorPID> ('<scanDefinitionName>' - # <scanDefinitionID>).	You may have insufficient permissions to run the scan, or you may need to adjust your scan configuration.  For troubleshooting assistance, see the <a href="#">knowledge base</a> article.
65536	Unable to scan <numInaccessibleTargets> target (s) outside your accessible ranges in Scan #job # <jobIDorPID> ('<scanDefinitionName>' - # <scanDefinitionID>).	You may have insufficient permissions to run the scan, or you may need to adjust your scan configuration.  For troubleshooting assistance, see the <a href="#">knowledge base</a> article.
65536	Usable Zones fail to cover <unscannableCount> accessible Scan IP<plural> for Scan job # <jobIDorPID> ('<scanDefinitionName>' - # <scanDefinitionID>).	You may have insufficient permissions to run the scan, or you may need to adjust your scan configuration.  For troubleshooting assistance, see the <a href="#">knowledge base</a> article.
65536	Available Zones do not cover accessible Scan IPs for Scan job # <jobIDorPID> ('<scanDefinitionName>' - # <scanDefinitionID>).	You may have insufficient permissions to run the scan, or you may need to adjust your scan configuration.  For troubleshooting assistance, see the <a href="#">knowledge base</a> article.